

# NightTrace User's Guide

**Version 7.3** 

(NightStar LX)



Copyright 2013 by Concurrent Computer Corporation. All rights reserved. This publication or any part thereof is intended for use with Concurrent products by Concurrent personnel, customers, and end–users. It may not be reproduced in any form without the written permission of the publisher.

The information contained in this document is believed to be correct at the time of publication. It is subject to change without notice. Concurrent Computer Corporation makes no warranties, expressed or implied, concerning the information contained in this document.

Concurrent Computer Corporation and its logo are registered trademarks of Concurrent Computer Corporation. All other Concurrent product names are trademarks of Concurrent while all other product names are trademarks or registered trademarks of their respective owners.

Linux® is used pursuant to a sublicense from the Linux Mark Institute.

NightStar's integrated help system is based on Assistant, a Qt® utility. Qt is a registered trademark of Digia Plc and/or its subsidiaries.

NVIDIA® CUDA<sup>TM</sup> is a trademark of NVIDIA Corporation.

## **Preface**

## Scope of Manual

This manual is a reference document and user's guide for NightTrace $^{TM}$  - a graphical, interactive debugging and performance analysis tool.

## Structure of Manual

The manual includes four major parts as shown below:

- Event Logging and Capture Chapters 2 through 6
- Graphical Analysis Chapters 7 through 17
- Programmatic Analysis Chapter 18
- Reference appendices and index

Man page descriptions of programs, system calls, subroutines, and file formats appear in the system manual pages.

## **Syntax Notation**

The following notation is used throughout this guide:

italic

Books, reference cards, and items that the user must specify appear in *italic* type. Special terms and comments in code may also appear in *italic*.

### list bold

User input appears in **list bold** type and must be entered exactly as shown. Names of directories, files, commands, options and man page references also appear in **list bold** type.

list

Operating system and program output such as prompts and messages and listings of files and programs appears in list type. Keywords also appear in list type.

## window

Keyboard sequences and window features such as push buttons, radio buttons, menu items, labels, and titles appear in window type.

1	
Brackets enclose command options and argum not type the brackets if you choose to specify su	*

Braces enclose mutually exclusive choices separated by the pipe (|) character, where one choice must be selected. You do not type the braces or the pipe character with the choice.

. . .

{ }

[

An ellipsis follows an item that can be repeated.

# **Contents**

Chapter 1	Introduction	
	User Trace Point Placement.  Timestamps  Languages  Information Displayed	.1-2
Chapter 2	Using the NightTrace Logging API	.1-0
	Language-Specific Source Considerations  C. Fortran Java. CUDA. Inter-Process Communication and Library Routines Understanding NightTrace Library Calls trace_begin, Trace.begin. trace_event, Trace.event and their variants trace_enable, trace_disable, and their variants. trace_flush, Trace.flush, trace_trigger, and Trace.trigger. trace_set_thread_name, Trace.setThreadName trace_close_thread, Trace.closeThread. trace_end, Trace.end trace_end, Trace.end trace_diag_mode. trace_diag_func Disabling Tracing Threads and Logging. NightTrace CUDA Tracing API ntrace_cuda.h ntrace_cuda_device.h Compiling and Linking C C compilation and Linking Fortran Compilation and Linking. Java Example CUDA Example	.2-12 .2-2 .2-2 .2-5 .2-6 .2-7 .2-18 2-22 2-24 2-25 2-23 2-31 2-31 2-32 2-36 2-36 2-37 2-37
Chapter 3	Capturing User Events with ntraceud	2-31
	The ntraceud Daemon ntraceud Modes The Default User Daemon Configuration ntraceud Options Invoking ntraceud	.3-2 .3-2

## **Chapter 4 Application Illumination**

Overview	. 4-2
Illuminator	. 4-2
nlight	. 4-2
Work Flow Illustration	. 4-2
Provided Illuminators	. 4-3
Detail Levels	. 4-3
Limitations	. 4-5
The nlight Graphical User Interface	. 4-6
File	. 4-7
View	4-10
Tools	4-13
Help	4-15
Wizard	4-17
Navigation Panel	4-17
Common Buttons	4-19
Select Programs with Debug Information	4-20
Define an Illuminator for each Program	4-22
Select Predefined Illuminators for each Program	4-26
Relink Illuminated Programs	4-29
Activate Illuminators in each Program	4-32
Run Scripts to Launch Programs and NightTrace	4-35
Session Manager	4-40
The Application Illumination Root Item	4-41
Select Code with Debug Information	
Context Menus	
Building Object	4-44
Create, Customize, and Build Illuminators	
Context Menu	4-45
Context Menu on Individual Illuminators	4-47
Relink Programs	
Context Menus	4-49
Path	4-50
Relink Command	4-50
Illuminators	4-52
Activation Sets	4-54
Settings For "main" Illuminator	4-55
Settings For Ordinary Illuminators	
Context Menu for an Illuminator	4-56
Context Menu for a Program	4-57
Context Menu for an Activation Set	4-58
Scripts	4-60
New Script	
New Script from Activation Set (NightTrace in File Mode)	4-61
New Script from Activation Set (NightTrace in Stream Mode),	
New Script from Activation Set (Launch Programs)	4-62
Console	
Predefined Illuminators	4-64
Detail Levels	
main	4-64
glibc	
pthread	
ccur rt	

1	4
cuda	
Illuminator Files	
config.xml	
next_event.txt	4-66
illuminator.h	4-66
illuminator.map	4-66
illuminator_level.fmt	4-67
illuminator_level.o	4-67
illuminator_level.list	4-67
illuminator.o	4-67
illuminator.vararg	
nlight Command Line Mode	
Commands for Manipulating an Illuminator	
nlightcreate	
nlightpopulate	
nlightbuild	
nlightreport	
Commands for Linking with Illuminators	
nlightgcc	
nlightg77	
nlightcf77	
nlightada	
Command for Activating and Deactivating Illuminators	
Using NightTrace with Illuminators	4-75
Customizing an Illuminator with the Editor	4-77
Buttons	4-77
Search Editor	4-79
Options	
Event IDs.	
Limit on Size of Aggregates Recorded	
Include Functions without Dwarf Debug Info	
Regular Expressions	
Object Filenames.	
Detail Levels.	
Variables to Record	
Groups	
Create a Group	
Customize a Group	
Selecting Members of a Group	
Functions	
Adding a Function	
Customizing a Function	4-95
Adding a Function to a Group	4-98
Customizing an Illuminator by Editing the config.xml File	.4-100
comments	.4-100
config	.4-100
declare	.4-101
defaults	
exclude	
function.	
group	
level	
caller={yes/no}	
carrer -/ hes/110/	
frame=/vec/no!	4-105

	aggregate_limit=limit	
	args={yes/no}	
	addr_args={yes/no}	
	return_val={yes/no}	
	addr_ret={yes/no}	
	variables={yes/no}	
	errno={yes/no}	
	exclude={yes/no}	
	options	
	event_ids=" <i>N-[M]</i> "	
	$aggregate\_limit="limit" \dots \dots \dots \dots$	
	nodebug={yes/no}	
	underscores={yes/no}	
	std={yes/no}	
	iregex="regex", xregex="regex"	
	filename="filename"	
	variable	
	wrapper	
	wrapper_file_scope	
	wrapper_post	
	wrapper_pre	
	wrapper_real	
	Examples	4-112
Chapter 5	Performance Tuning	
	Preventing Trace Event Loss	5-1
	Daemon Scheduling Adjustment	
	Increasing Trace Buffer Size.	
	Programmatic Flushing	
	Conserving Disk Space	
	Conserving Memory and Accelerating ntrace	
Chapter 6	Invoking NightTrace	
	Common I I'm O d'ann	6.1
	Command-line Options	
	Summary Criteria	
	Command-line Arguments	
	Trace Event Files	
	Event Map Files	
	Table Files	
	String Tables	
	Pre-Defined Strings Tables	
	Format Tables	
	Session Configuration Files	
	Trace Data Segments	0-22
Chapter 7	The NightTrace Main Window	
	Menu Bar	7-2
	File	
	View	
	VIEW	/-/

	Daemons	
	Search	
	Summary	
	Profiles	
	Export Profiles to NightTrace API Source File	
	Timelines	
	Tools	
	Help	
	Toolbars	
	Pages	
	Panels	
	Preferences Dialog	
	General Preferences	
	Timeline Preferences	
	Font Preferences	
	NightStar Global Fonts Dialog	
	Advanced Preferences	
Chapter 8 Dae	emons Panel	
2 <b>.</b>		
	Context Menu	
	Control Buttons	
	Edit Daemon Definition	
	General Settings	
	Trace Buffer Settings	
	Trace Daemon Runtime Settings	
	Enabled Events	
	Triggers	
	Edit Triggers Dialog	
	Streaming Memory Usage Control	
	Streaming Memory Usage Control Dialog	8-1
Chapter 9 Tra	ice Segments Panel	
	Trace Segments Table	9_
	Context Menu	
	Control Buttons	
	Connor Buttons	
Chapter 10 Ev	vents Panel	
	Textual Event Tables	
	Context Menu  Event Panel Search Dialog	
Chantar 11 Tir	<u> </u>	
Chapter 11 Tir	menne raneis	
	Default Timeline	
	Current Timeline Indicator	
	Global Ruler	
	Interval Ruler	
	Event Graphs	
	Event Description Area	

		Keyboard Traversal	
		Creating Timeline Objects	
		Event Graph	1-10
		State Graph1	
		Data Graph	
		Data Graph Options Dialog	1-13
		Drawing and Coloring Examples	
		Color Selection Dialog	1-17
		Standard Color Names	1-19
		Interval Ruler	1-20
		Global Ruler	1-20
		Label	1-20
		Data Box	1-20
		Default CUDA AI Timeline	1-22
		Default CUDA GPU Timeline	1-23
Chapter 12	Profiles	Profiles Dialog	12-2 12-3 12-4
		Summarizing Statistical Information	2-13
		Condition Summaries	2-13
		State Summaries	2-13
		Summary Scripts	2-13
		Summary Script Environment Variables	2-14
Chapter 13	Event De	escriptions Panel	
onaptor 10	_ Tont Bo		
Chapter 14	Tags List	t Panel	
		Creating Tags	14_1
		Tags List Table	
		Context Menu.	
		Control Buttons	
		Condoi Buttons	17-5
Chapter 15	Using Ex	pressions	
		Overview	15-1
		Operators	
		Operands	
		Constants	
		Functions	
		Function Parameters	
		Function Terminology	
		String Functions	
		stremn()	
		stremp()	
		strncmp()	5-18
			5-18 5-19

	start_blk_arg_long_ubits()	
	start_blk_arg_string()	15-77
	start_blk_arg_ubits()	15-78
	start_blk_arg_uchar()	15-79
	start blk arg uint()	15-80
	start_blk_arg_ulong_long()	15-81
	start_blk_arg_ushort()	15-82
	start_num_args()	15-83
	start_pid()	15-83
	• "	
	start_thread_id()	15-85
	start_tid()	15-86
	start_cpu()	15-87
	start_offset()	15-88
	start_time()	15-89
	start_node_id()	15-90
	start_node_name()	15-91
End	Functions	15-92
	end_id()	15-94
	end_arg().	15-95
	end_arg_dbl()	15-96
	end_arg_long()	15-97
		15-98
	end_arg_long_dbl()	
	end_arg_long_long()	15-99
	end_blk_arg()	
	end_blk_arg_bits()	
		15-102
		15-103
	end_blk_arg_flt()	15-104
	end_blk_arg_long()	15-105
	end_blk_arg_long_bits()	15-106
	end_blk_arg_long_dbl()	
	end_blk_arg_long_long()	
	end_blk_arg_long_ubits().	
		15-110
	end_blk_arg_string()	
	end_blk_arg_ubits()	
	end_blk_arg_uchar()	
	end_blk_arg_uint()	
	end_blk_arg_ulong_long()	
	end_blk_arg_ushort()	
	end_num_args()	15-117
	end_pid()	15-118
	end_thread_id()	15-119
	end_tid()	15-120
	end_cpu()	
	end_offset().	
	end_time().	
	end_node_id().	
	end_node_name()	
	ti-State Functions	
	state_gap()	
	state_dur()	
	state_matches()	15-128

state_status()	.15-129
Offset Functions	.15-130
offset_id()	.15-132
offset_arg()	.15-133
offset_arg_dbl()	.15-134
offset_arg_long()	.15-135
offset_arg_long_dbl()	.15-136
offset_arg_long_long()	.15-137
offset_blk_arg()	
offset_blk_arg_bits()	
offset_blk_arg_char()	.15-140
offset_blk_arg_dbl()	
offset_blk_arg_flt()	
offset_blk_arg_long()	
offset_blk_arg_long_bits()	
offset_blk_arg_long_dbl()	
offset_blk_arg_long_long()	
offset_blk_arg_long_ubits()	
offset_blk_arg_short()	
offset_blk_arg_string()	
offset_blk_arg_ubits()	
offset_blk_arg_uchar()	
offset_blk_arg_uint()	
offset_blk_arg_ulong_long()	
offset_blk_arg_ushort()	
offset_num_args()	
——————————————————————————————————————	
offset_pid()	
offset_thread_id()	
offset_tid()	
offset_cpu()	
offset_time()	
offset_node_id()	
offset_node_name()	
offset_process_name()	
offset_thread_name()	
Summary Functions	
min()	
max()	
avg()	
sum()	
min_offset()	
max_offset()	
summary_matches()	
Format and Table Functions	
get_string()	
get_item()	
get_format()	
format()	.15-178
lookup_pc()	.15-179
Profile References	.15-181

## Chapter 16 Using the NightTrace Analysis API

NightTrace Analysis Application Programming Interface	
Data Structures	
tr_arg_t	16-3
tr_cb_t	
tr_cond_cb_func_t	16-4
tr_cond_func_t	16-5
tr_cond_t	16-5
tr_dir_t	16-5
tr_offset_t	16-5
tr_state_action_t	16-6
tr_state_cb_func_t	16-6
tr_state_info_t	16-7
tr_state_t	16-8
tr_stream_event_t	16-8
tr_stream_func_t	16-8
tr_string_node_t	16-8
tr_t	16-9
Functions	16-10
API Initialization and Destruction	16-15
tr_init()	
tr_destroy()	16-15
Error Detection, Collection, and Reporting	16-17
tr_error_clear()	16-17
tr_error_check()	16-18
Input Specification and Streaming Control	16-19
tr_open_file()	16-19
tr_open_stream()	16-20
tr_close()	16-21
tr_stream_notify()	16-22
tr_stream_read()	16-23
tr_stream_size()	16-24
tr_free()	16-25
Event Offset Positioning	16-26
tr_next_event()	
tr_next_event_()	
tr_prev_event()	
tr_prev_event_()	
tr_search()	16-29
tr_seek()	
Basic Event Attribute Functions	
tr_id()	
tr_id_()	
tr_time()	
tr_time_()	
tr_nargs()	
tr_nargs_()	
tr_arg_int()	
tr_arg_int_()	
tr_arg_dbl()	
tr_arg_dbl_()	
tr_arg_long()	
tr arg long ()	16-41

tr_arg_long_dbl()
tr_arg_long_dbl_()
$tr\_arg\_long\_long() \dots \dots 16-43$
tr_arg_long_long_()16-44
tr_arg_int_()16-45
tr_arg_dbl()
tr_arg_dbl_()
tr_arg_long()
tr_arg_long_()
tr_arg_long_dbl()
tr_arg_long_dbl_()
tr_arg_long_long()
tr_argtype()
tr_argtype_()
tr_blk_arg()
tr_blk_arg_()
tr_blk_arg_bits()
tr_blk_arg_bits_()
tr_blk_arg_char()
tr_blk_arg_char_()
tr_blk_arg_dbl()
tr_blk_arg_dbl_()
tr_blk_arg_flt()
tr_blk_arg_flt_()
tr_blk_arg_long()
tr_blk_arg_long_()
tr_blk_arg_long_bits()
tr_blk_arg_long_bits_()
tr_blk_arg_long_dbl()
tr_blk_arg_long_dbl_()
tr_blk_arg_long_long()
tr_blk_arg_long_long_()16-66
tr_blk_arg_long_ubits()
tr_blk_arg_long_ubits_()
tr_blk_arg_short()
tr_blk_arg_short_()
tr_blk_arg_string()
tr_blk_arg_string_()
tr_blk_arg_ubits()16-72
tr_blk_arg_ubits_()16-73
tr_blk_arg_uchar()
tr_blk_arg_uchar_()
tr_blk_arg_ushort()
tr_blk_arg_ushort_()
tr_pid()
tr_pid_()
tr_tid()
tr_tid_()
tr_thread_id()
tr_thread_id_()
tr_cpu()
tr_cpu_()
tr_node()
tr node ()

	tr_process_name()	16-85
	tr_process_name_()	16-86
	tr_thread_name()	16-86
	tr_thread_name_()	16-87
Con	ditions	16-88
	tr_cond_create()	16-89
	$tr\_cond\_reset() \dots \dots$	16-90
	tr_cond_find()	16-90
	tr_cond_id()	16-91
	tr_cond_id_range()	16-92
	tr_cond_id_clear()	16-93
	tr_cond_cpu()	16-94
	tr_cond_cpu_clear()	16-95
	tr_cond_pid()	16-96
	tr_cond_pid_name()	16-97
	tr_cond_pid_clear()	16-98
	tr_cond_tid()	16-99
		16-100
		16-101
		16-102
		16-103
		16-104
		16-106
		16-108
		16-109
	•	16-110
	tr_cond_not()	
		16-111
		16-113
		16-113 16-114
	17 ~	16-114 16-116
		16-116 16-116
	· · · ·	16-116 16-117
	E v	16-118
		16-119
		16-120
		16-120
	tr_state_find()	
	tr_state_name()	
	tr_state_start_id()	
	tr_state_start_id_range()	
	tr_state_start_id_clear()	
	tr_state_end_id()	
	tr_state_end_id_range()	
	tr_state_end_id_clear()	
	tr_state_start_cond()	
	tr_state_start_cond_clear()	
	tr_state_end_cond()	
	tr_state_end_cond_clear()	
		16-131
	=	16-132
		16-133
	tr_state_active()	
	tr state active ()	16-135

	Output Function	
	tr_copy_input()	.16-136
	tr_copy_input_range()	.16-137
	String Table Functions	.16-138
	tr_get_string()	
	tr_get_item()	.16-139
	tr_create_table()	.16-140
	tr_append_table()	.16-141
	Callback Interfaces	.16-143
	tr_iterate()	.16-143
	tr_halt()	.16-144
	tr_cancel_cb()	.16-144
	tr_cond_cb()	.16-145
	tr_state_cb()	.16-146
Appendix A	NightStar LX Licensing	
	License Keys	
	License Requests	
	License Server	
	License Reports	
	Firewall Configuration for Floating Licenses	
	Serving Licenses with a Firewall	
	Running NightStar LX Tools with a Firewall	
	License Support	A-6
Appendix B	Kernel Dependencies	
	Advantages for NightView	R-1
	Advantages for NightTrace	
	Advantages for NightProbe	
	Advantages for NightTune.	
	Frequency Based Scheduler.	
Appendix C	Privileged Access	
	Capabilities	C 1
	Capabilities	C-1
Appendix D	NightTrace Logging API Examples	
	Single Threaded C Example	D-1
	Multi-Threaded C++ Example	
	Fortran Example	D-6
	Simple Java Example	
	Multi-Threaded Java Example	
	Rare Occurrence Example	D-9
	CUDA Example	
Appendix E	NightTrace Analysis API Examples	
	list	E-2
	list c	F 2

	search E-4
	search.c
	watchdog.c
	ptime E-9
	ptime.c. E-10
	browse
	browse.c
	detect
	detect.c
Appendix F	NightTrace Application Illumination Examples
	Illuminating Some Object Files
	Illuminating A Library F-5
	Illuminating An Entire Program F-6
	Illuminating A C++ Class Excluding Some Functions F-7
	Illuminating An API Libraries Without Source or Debug Info F-9
	Customizing an Illuminator Logging Extra Information F-11
	Tutorial Files
	main.c
	math.c
	work.c
	api.h. F-15
	wp
Appendix G	Answers to Common Questions
Appendix H	Closson
	Glossary
	Glossary
Index	Glossary
Index	Giossary
	Giossary
	Figure 2-1. Inter-Process Communication and Library Routines
	Figure 2-1. Inter-Process Communication and Library Routines 2-4
	Figure 2-1. Inter-Process Communication and Library Routines
	Figure 2-1. Inter-Process Communication and Library Routines. 2-4 Figure 8-1. NightTrace Main Window 8-1 Figure 8-2. File Menu 8-2 Figure 8-3. View Menu 8-6 Figure 8-4. Toolbars Menu 8-7
	Figure 2-1. Inter-Process Communication and Library Routines 2-4 Figure 8-1. NightTrace Main Window 8-1 Figure 8-2. File Menu 8-2 Figure 8-3. View Menu 8-6 Figure 8-4. Toolbars Menu 8-7 Figure 8-5. Daemons Menu 8-8
	Figure 2-1. Inter-Process Communication and Library Routines 2-4 Figure 8-1. NightTrace Main Window 8-1 Figure 8-2. File Menu 8-2 Figure 8-3. View Menu 8-6 Figure 8-4. Toolbars Menu 8-7 Figure 8-5. Daemons Menu 8-8 Figure 8-6. Search Menu 8-9
	Figure 2-1. Inter-Process Communication and Library Routines 2-4 Figure 8-1. NightTrace Main Window 8-1 Figure 8-2. File Menu 8-2 Figure 8-3. View Menu 8-6 Figure 8-4. Toolbars Menu 8-7 Figure 8-5. Daemons Menu 8-8 Figure 8-6. Search Menu 8-9 Figure 8-7. Summary Menu 8-11
	Figure 2-1. Inter-Process Communication and Library Routines       2-4         Figure 8-1. NightTrace Main Window       8-1         Figure 8-2. File Menu       8-2         Figure 8-3. View Menu       8-6         Figure 8-4. Toolbars Menu       8-7         Figure 8-5. Daemons Menu       8-8         Figure 8-6. Search Menu       8-9         Figure 8-7. Summary Menu       8-11         Figure 8-8. Profiles Menu       8-13
	Figure 2-1. Inter-Process Communication and Library Routines       2-4         Figure 8-1. NightTrace Main Window       8-1         Figure 8-2. File Menu       8-2         Figure 8-3. View Menu       8-6         Figure 8-4. Toolbars Menu       8-7         Figure 8-5. Daemons Menu       8-8         Figure 8-6. Search Menu       8-9         Figure 8-7. Summary Menu       8-11         Figure 8-8. Profiles Menu       8-13         Figure 8-9. Export Profiles Dialog       8-14
	Figure 2-1. Inter-Process Communication and Library Routines       2-4         Figure 8-1. NightTrace Main Window       8-1         Figure 8-2. File Menu       8-2         Figure 8-3. View Menu       8-6         Figure 8-4. Toolbars Menu       8-7         Figure 8-5. Daemons Menu       8-8         Figure 8-6. Search Menu       8-9         Figure 8-7. Summary Menu       8-11         Figure 8-8. Profiles Menu       8-13         Figure 8-9. Export Profiles Dialog       8-14         Figure 8-10. Timelines Menu       8-17
Index Illustrations	Figure 2-1. Inter-Process Communication and Library Routines       2-4         Figure 8-1. NightTrace Main Window       8-1         Figure 8-2. File Menu       8-2         Figure 8-3. View Menu       8-6         Figure 8-4. Toolbars Menu       8-7         Figure 8-5. Daemons Menu       8-8         Figure 8-6. Search Menu       8-9         Figure 8-7. Summary Menu       8-11         Figure 8-8. Profiles Menu       8-13         Figure 8-9. Export Profiles Dialog       8-14         Figure 8-10. Timelines Menu       8-17         Figure 8-11. Default User Timeline       8-18
	Figure 2-1. Inter-Process Communication and Library Routines       2-4         Figure 8-1. NightTrace Main Window       8-1         Figure 8-2. File Menu       8-2         Figure 8-3. View Menu       8-6         Figure 8-4. Toolbars Menu       8-7         Figure 8-5. Daemons Menu       8-8         Figure 8-6. Search Menu       8-9         Figure 8-7. Summary Menu       8-11         Figure 8-8. Profiles Menu       8-13         Figure 8-9. Export Profiles Dialog       8-14         Figure 8-10. Timelines Menu       8-17         Figure 8-11. Default User Timeline       8-18         Figure 8-12. Create Custom Kernel Timeline Dialog       8-19
	Figure 2-1. Inter-Process Communication and Library Routines       2-4         Figure 8-1. NightTrace Main Window       8-1         Figure 8-2. File Menu       8-2         Figure 8-3. View Menu       8-6         Figure 8-4. Toolbars Menu       8-7         Figure 8-5. Daemons Menu       8-8         Figure 8-6. Search Menu       8-9         Figure 8-7. Summary Menu       8-11         Figure 8-8. Profiles Menu       8-13         Figure 8-9. Export Profiles Dialog       8-14         Figure 8-10. Timelines Menu       8-17         Figure 8-11. Default User Timeline       8-18
	Figure 2-1. Inter-Process Communication and Library Routines       2-4         Figure 8-1. NightTrace Main Window       8-1         Figure 8-2. File Menu       8-2         Figure 8-3. View Menu       8-6         Figure 8-4. Toolbars Menu       8-7         Figure 8-5. Daemons Menu       8-8         Figure 8-6. Search Menu       8-9         Figure 8-7. Summary Menu       8-11         Figure 8-8. Profiles Menu       8-13         Figure 8-9. Export Profiles Dialog       8-14         Figure 8-10. Timelines Menu       8-17         Figure 8-11. Default User Timeline       8-18         Figure 8-12. Create Custom Kernel Timeline Dialog       8-19         Figure 8-13. Tools Menu       8-20

TI 0.45 34 B D1.1	
Figure 8-17. Move Page Dialog	
Figure 8-18. Page with Profile Panels	
Figure 8-19. Panel Detaches from Page	
Figure 8-20. Panel Movement in Progress	
Figure 8-21. Profile Status List Panel on Top of Profile Definition Panel	
Figure 8-22. Event Descriptions Panel added to Page	
Figure 8-23. Panel in Motion Creating Tab	
Figure 9-1. Daemons Panel	
Figure 9-2. Daemons Panel Context Menu	
Figure 9-3. Import Daemon Definitions Dialog	
Figure 9-4. Attach to Running Daemons Dialog	
Figure 9-5. Edit Triggers Dialog	
Figure 9-6. Add Triggers Entry Dialog	
Figure 9-7. Edit Daemon Definition Dialog	
Figure 10-1. Trace Segments Panel	
Figure 10-2. Trace Segment Panel Context Menu	
Figure 10-3. Trace Data Segment Properties Description Dialog	
Figure 11-1. Events Panel	
Figure 11-2. Events Panel Context Menu	
Figure 11-3. Search Events for Text Dialog	
Figure 11-4. Edit Event Description Dialog	
Figure 12-1. Default User Timeline	
Figure 12-2. Global Ruler	
Figure 12-3. Interval Ruler	
Figure 12-4. Event Graph with Labels	
Figure 12-5. Event Description Area	
Figure 12-6. Timeline Editing	
Figure 12-7. Timeline Context Menu	.12-9
Figure 12-8. Edit Event Graph Profile Dialog	12-10
Figure 12-9. Edit State Graph Profile Dialog	12-11
Figure 12-10. Edit Data Graph Profile Dialog	
Figure 12-11. Edit Data Box Profile	
Figure 13-1. Profile Definition Panel	.13-2
Figure 13-2. Profile Status List Panel	
Figure 13-3. Profile Status List Panel Context Menu	13-13
Figure 14-1. Event Descriptions Panel	
Figure 14-2. Event Description Dialog	
Figure 15-1. Tags List Panel	.15-1
Figure 15-2. Tags List Panel Context Menu	.15-3
Figure 16-1. Function Terminology Illustrated	16-12
Figure 16-2. States and Events	16-12
Figure 17-1. Sample Kernel timeline	17-10
Figure 17-2. Node and CPU Box	
Figure 17-3. Context Switch Lines	
Figure 17-4. Interrupt Box and Interrupt Graph	17-12
Figure 17-5. Exception Box and Exception Graph	17-12
Figure 17-6. System Call Box and System Call Graph	17-13
Figure 17-7. Process Information Row	17-14
Figure 17-8. Kernel Events Row	17-14
Figure 17-9. Color Key	17-15
Figure B-1. Automatically Generated Data Display Page	. C-5

## NightTrace LX User's Guide

## **Tables**

Table 3-1. NightTrace Configuration Defaults	3-3
Table 5-1. Character Entities	5-15
Table 5-2. System Defaults	5-19
Table 12-1. Timeline Keyboard Traversal	12-7
Table 16-1. Time Units and Constant Suffixes	16-3
Table 16-1. NightTrace Functions	16-5
Table 17-1. PROCESS Event Codes	17-6
Table 17-2. NETWORK Kernel Event Sub-ID Codes	17-6
Table 17-3. MEMORY Kernel Event Sub-ID Codes	17-7

## Introduction

NightTrace is a member of the NightStar<sup>TM</sup> family of tools. NightTrace provides an interactive debugging and performance analysis tool, trace data collection daemons, and two Application Programming Interfaces (APIs) allowing user applications to log data values as well as analyze data collected from user daemons. NightTrace allows you to graphically display information about important events in your application, including event occurrences, timings, and data values. NightTrace consists of the following parts:

### ntrace

a graphical tool that controls daemon sessions and presents user trace events for interactive analysis

#### ntraceud

a daemon program that copies user applications' trace events from shared memory to trace event files

## NightTrace Logging API

libraries and include files for use in user applications that log trace events to shared memory

## NightTrace Analysis API

libraries and include files for use in user applications that want to analyze data collected from user daemons

### nlight

a command line tool for generating code to log trace events at function entry and return points

NightTrace operates in conjunction with other members of theNightStar LX family. NightView, a multi-process and multi-thread application debugger, provides for dynamic insertion of trace points in programs being debugged. The NightProbe data recording utility allows sampled data to be passed directly to NightTrace for graphic or textual display.

NightTrace uses the NightStar License Manager (NSLM) to control access to the NightStar tools. See "NightStar LX Licensing" on page A-1 for more information.

## **User Trace Point Placement**

A user trace point is a place of interest in application source code. At each user trace point, you make your application log some user-specified information. This logged infor-

mation is collectively called a *trace event*. Each trace event has a user-defined *trace event ID* number and optional user-supplied arguments.

Some typical user trace-point locations include:

- Suspected bug locations
- · Process, subprogram, or loop entry and exit points
- · Timing points
- Synchronization points for multi-process interaction
- Endpoints of atomic operations

The Application Illumination facility can be used to automatically generate user trace points for function entry and return. These trace events can include return address, parameter values, return values, etc. as arguments.

In addition to the user-supplied information, trace events automatically contain information identifying the process ID of the program generating the trace event. For multi-threaded applications, the thread ID of the specific thread generating the trace is recorded.

## **Timestamps**

Each trace event is tagged with a timestamp with sub-microsecond precision. This allows you to view and comprehend complex interactions between multiple processes and the operating system, executing on single or multiple CPU systems.

By default, an architecture-specific timing source is utilized. For Intel and AMD64, the Intel Time Stamp Counter (TSC register) is used.

If your operating system supports the Real-Time Clock and Interrupt Module (RCIM), that clock can be also used as a timestamp source.

The RCIM is a hardware module available from Concurrent Computer Corpration which provides a variety of clocks and interrupt sources, including two high-resolution timers which may be synchronized between multiple systems. Use of the RCIM timing source by NightTrace is advantageous when gathering data from multiple systems simultaneously. NightTrace can then present a synchronized view of user activity on multiple systems from a single session.

NightTrace can also present such a synchronized view of activity between systems if the systems utilize an alternative method of time synchronization, such as NTP or PTP. RCIM time synchronization is extremely accurate; other solutions often are not as accurate, or may take a long time to actually synchronize system time.

For more information about the RCIM, please see the clock\_synchronize(1M), rcim(7), rcimconfig(1M), and sync\_clock(7) man pages.

## Languages

The application programming interface for logging trace events is provided in C and Fortran for use with the following compilers:

- Concurrent Ada
- GNU C/C++
- GNU Fortran
- Intel C/C++
- Intel Fortran
- Concurrent Fortran 77
- CUDA a mechanism for executing C/C++ code on an NVIDIA Graphical Processing Unit

The application programming interface for trace event analysis is provided solely in C for use with C and C++ programs.

## **Information Displayed**

The **ntrace** display utility lets you examine trace events. Data appear as numerical statistics and as graphical images. You can create and configure the graphical components called *display objects* or use the defaults. By creating your own display objects, you can make the graphical displays more meaningful to you. You can customize display objects to reflect your preferences in content, labeling, position, size, color, and font.

With the **ntrace** display utility, you can perform customized searches and summaries for individual events or user-defined states. Summaries can be generated via command line invocation of **ntrace** for generating automated reports.

# **Using the NightTrace Logging API**

This chapter describes language-specific considerations for using NightTrace with user applications.

Sample programs using these functions are also provided (see "NightTrace Logging API Examples" on page D-1).

## **Language-Specific Source Considerations**

NightTrace applications can be written in C, C++, Fortran, or Java.

The NightTrace Logging API has been tested with the following compilers:

- GNU C/C++
- GNU Fortran
- Intel C/C++
- Intel Fortran
- Sun Java 1.5 or later
- Aonix Perc Ultra Java 5.1 or later
- NVIDIA nvcc CUDA preprocessor

Generally, for your applications to trace events, you must edit your source code and insert NightTrace library routine calls. This is called *instrumenting your code*. Alternatively, the Application Illumination facility (see "Application Illumination" on page 4-1) can be used to instrument your code without making any source changes. Before you begin the task of inserting trace event calls, read the following section that applies to the language in which your application is written.

C

NightTrace applications written in C or C++ include the NightTrace header file /usr/include/ntrace.h with the following line:

```
#include <ntrace.h>
```

The **ntrace.h** file contains the following:

• Function prototypes for all NightTrace library routines

- Return values for all NightTrace library routines
- Macros (described in "Disabling Tracing" on page 2-31)

The library routine return values identify the type of error, if any, the NightTrace routine encountered.

Programs that are multi-thread can also be traced with the NightTrace library routines. For multi-thread programs, a thread identifier is stored in each trace event, uniquely identifying which thread was running at the time the trace event was logged.

### **IMPORTANT**

To fully utilize the features of NightTrace with multi-threaded applications, additional considerations must be taken into account. See the description of "Threads and Logging" on page 2-31 for more information.

Minimally, a C or C++ program can log trace points using the following sequence of library routine invocations:

```
trace_begin("file",NULL); // Called once
...
trace_event(11,2) // Log Event ID 11 with argument 2
```

## **Fortran**

All NightTrace library routines return INTEGERS, but because they begin with a "t", Fortran implicitly types them as REAL. You must include the NightTrace-provided file /usr/include/ntrace\_.h or explicitly type them as INTEGER so that return values are interpreted correctly.

Minimally, a Fortran program can log trace points using the following sequences of library calls:

```
call trace_begin("data",0) (called once)
...
call trace_event(11)
```

## Java

Java applications can access the NightTrace library routines via classes in the ntrace.logging package. Java NightTrace class files are located in /usr/lib; be sure to add this path when using the -classpath java option or CLASSPATH environment variable. The Java bindings are provided via the Java Native Interface (JNI). The JNI component of the NightTrace bindings is provided in libntrace-java.so, which will be automatically loaded by the Java Virtual Machine. libntrace-java.so resides in the /usr/lib directory.

The ntrace.logging package contains the Trace class, along with two nested static classes which are used by routines in the outer Trace class:

```
Trace.Config
```

Defines a configuration object, which can be specified to the Trace.begin() call to define daemon logging options.

```
Trace.Error
```

Exception class to hold NightTrace error returns and accessor functions to describe the specific error.

Minimally, a Java program can log trace points using the following sequences of code:

```
import ntrace.logging;
...
Trace.Begin("data"); // (called once)
...
Trace.Event(11);
```

### The Java Trace Class

Unlike C, Ada and Fortran, the files associated with the Java API do not contain a header-like file which you can refer to when coding.

The relevant public portions of the Trace class and its nested classes are described in the following sections for each routine.

However, for convenience, a listing of all relevant public portions of the Trace class is shown below:

```
public class Trace {
   public static class Error extends RuntimeException {
      public enum Msg {
         NTNOERROR,
         NTNODAEMON,
         NTNOTRACEFILE,
         NTINVALID,
         NTPERMISSION,
         NTALREADY,
         NTNOSHMID,
         NTRESOURCE,
         NTINIT,
         NTLOSTDATA,
         NTPGLOCK,
         NTNOMEM,
         NTMAPCLOCK,
         NTBADVERSION,
         NTLISTEN,
         NT_THREAD_ERR,
         DEFAULT;
      public final Msg getError();
   }
   public static class Config {
      public enum ClockSource { DefaultClock, RCIMTickClock; }
      public enum PageLocking { Default, Locked, Unlocked; }
```

```
public Config();
      public PageLocking getPageLocking();
      public boolean getDaemonSettingsPreferred();
     public int getBufferLength();
     public int getNumBuffers();
     public int getSharedMemoryPermissions();
     public ClockSource getClockSource();
     public void setPageLocking(PageLocking pl);
     public void setDaemonSettingsPreferred(boolean dsp);
     public void setBufferLength(int bl);
     public void setNumBuffers(int nb);
     public void setSharedMemoryPermissions(int smp);
     public void setClockSource(ClockSource cs);
  public static void begin(String file, Config config);
  public static void begin(String file);
   public static void setThreadName(String name);
  public static void event(int id);
   public static void event(int id, int argl);
  public static void event(int id, int arg1, int arg2);
  public static void event(int id, int arg1, int arg2, int arg3);
  public static void event(int id, int arg1, int arg2, int arg3, int
arg4);
  public static void event(int id, float argl);
  public static void event(int id, float arg1, float arg2);
  public static void event(int id, double arg1);
  public static void event(int id, double arg1, double arg2);
  public static void event(int id, long argl);
  public static void event(int id, long arg1, long arg2);
  public static void event(int id, String arg1);
  public static void event(int id, boolean[] arg1);
  public static void event(int id, byte[] argl);
  public static void event(int id, char[] arg1);
  public static void event(int id, short[] arg1);
  public static void event(int id, int[] arg1);
  public static void event(int id, long[] argl);
  public static void event(int id, float[] arg1);
  public static void event(int id, double[] argl);
  public static void disable(int id);
  public static void disable(int id_low, int id_high);
  public static void disable();
  public static void enable(int id);
   public static void enable(int id_low, int id_high);
  public static void enable();
   public static void flush();
  public static void trigger();
   public static void closeThread();
   public static void end();
   public static void enableDiagnostics(boolean on);
```

## **Error Handling**

Unlike the other language interfaces, error conditions in the Java API are handled by throwing a Trace. Error object.

Objects of that class can be caught and queried for a specific enumerated reason associated with the error.

The public members of the Error class are shown in "The Java Trace Class" on page 2-3.

The following snippet of code demonstrates how you might use this class:

```
try {
   Trace.event(5);
} catch (Trace.Error e) {
   if (e.getError() == Trace.Error.Msg.NTINIT) {
       System.out.println("Oops; forgot to start ntraceud!");
   }
}
```

## **CUDA**

CUDA applications that wish to include trace points in GPU-executed code should include the following header files:

```
#include <ntrace_cuda.h>
#include <ntrace_cuda_device.h>
```

The former is required for calls that setup the NightTrace session in CPU-executed code, while the latter is for calls that actually log trace points in GPU-executed code.

Minimally, a CUDA program can use tracing with the following sequence of library routine invocations in CPU-executed code:

```
ntrace_cuda_context *ncc =
ntrace_cuda_begin("file",NULL); // Called once

gpu_code<<<x,y>>>(ntrace_cuda_sync(ncc));
/* ntrace_cuda_sync called once for each GPU kernel invocation */

ntrace_cuda_flush(); // Called once to flush events
ntrace_cuda_end(); // Called once to terminate tracing
```

To actually log trace points in code executed by an NVIDIA GPU, use the following functions:

```
ntrace_cuda_event(ncs,1);
ntrace_cuda_event(ncs,2,int_arg);
ntrace_cuda_evnet(ncs,3,float_arg1,float_arg2);
ntrace_cuda_event(ncs3,ptr,bytes);
```

where *ncs* is the return value from ntrace\_cuda\_sync that was passed into your GPU-executed code.

There are additional overloaded functions named ntrace\_cuda\_event in ntrace cuda device.h.

For a complete description of CUDA-related NightTrace interfaces, please see "NightTrace CUDA Tracing API" on page 2-32

## **Inter-Process Communication and Library Routines**

Your application logs trace events to a shared memory area. A user daemon copies trace events from shared memory buffers to the trace event file or to the NightTrace graphical analysis tool. The relationship between your application and the user daemon and the sequence of library calls needed to maintain this relationship appears in the figure below.




Figure 2-1. Inter-Process Communication and Library Routines

## **Understanding NightTrace Library Calls**

There are C Fortran, and Java versions of each NightTrace library routine. These routines perform the following functions:

- · Initialize a tracing session
- Log trace events to shared memory
- Enable and disable specified trace events
- Explicitly notify the daemon to copy shared memory to disk
- · Control how diagnostics are generated
- Terminate a tracing session

## trace\_begin, Trace.begin

The trace\_begin and Trace.begin routines initialize the tracing session and acquire resources for your process.

### **SYNTAX**

```
C:
    int trace_begin(char *trace_file,
                     ntconfig_t * cfg);
Fortran:
    integer function trace_begin(trace_file, cfg)
    character *(*) trace_file
    integer cfg(NTC\_SIZE)
Java:
    package ntrace.logging;
    public class Trace {
       static class Config {
              Config();
              enum ClockSource {
                 DefaultClock,
                 RCIMTickClock;}
              enum PageLocking {
                 Default,
                 Locked,
                 Unlocked; }
              PageLocking getPageLocking();
              boolean getDaemonSettingsPreferred();
              int getBufferLength();
              int getNumBuffers();
```

```
int getSharedMemoryPermissions()
    ClockSource getClockSource();
    void setPageLocking(PageLocking);
    void setDaemonSettingsPreferred(boolean);
    void setBufferLength(int);
    void setNumBuffers(int);
    void setSharedMemoryPermissions(int);
    void setClockSource(ClockSource);
};
static void begin (String trace_file);
static void begin (String trace_file, Config cfg);
};
```

### **PARAMETERS**

trace\_file

The user daemon logs trace events to an output file, <code>trace\_file</code>. When you invoke the user daemon, you must specify this file's name. For the user daemon to log your process' trace events to this file, the trace event file parameter in your <code>trace\_begin</code> call must correspond to the key file value on the daemon invocation. The names do not have to exactly match textually, but they do have to refer to the same actual pathname; for example, one path name may begin at your current working directory and the other may begin at the root directory. When a user daemon is sending trace data directly to the NightTrace graphical analysis tool, this file name serves only as a handle so that the user daemon and the application can communicate -- no data is transferred to the file in this case.

cnf

C

cfg must be either a NULL pointer, in which case the default settings are used, or a pointer to a ntconfig\_t structure.

The following function can also be used to initialize *cfg* to appropriate default values:

```
void trace_default_config (ntconfig_t * config);
```

Therefore, the following code sequence:

```
ntconfig_t config;
trace_default_config(&config);
trace_begin("file",&config);
is equivalent to:
trace_begin("file",NULL);
```

This is most useful when you wish to change just a few specific configuration parameters without having to explicitly define all parameters. For example:

```
ntconfig_t config;
trace_default_config(&config);
config.ntc_num_buffers = 64;
trace_begin("file",&config);
```

### Fortran

The *cfg* record must be represented by an array of NTC\_SIZE integer items. Member of the array must be provided as described below.

Java

The *cfg* parameter is optional. If specified, it must be an instance of the Trace. Config class. You can use the mutator methods within that class to set options in the Trace. Config object.

The following describe the individual parameters or mutator Java functions:

C: ntc\_version

Fortran: config(ntc\_version)

Java: n/a

The value of the NTC\_VERSION macro from ntrace.h

C: ntc\_lock\_pages

Fortran: *cfg*(ntc\_lock\_pages)

Java: cfg.setPageLocking(PageLocking)

For C and Fortran, one of the following values:  $ntp\_default$ , which specifies that page locking should default;  $ntp\_lock$ , which specifies that critical pages are to be locked in memory; or  $ntp\_no\_lock$ , which specifies that critical pages shall not be locked in memory.  $ntp\_default$  does not request page locking, but does conflict with a user daemon configuration setting of  $ntp\_lock$  or  $ntp\_no\_lock$ .

For Java, one of the values:

PageLocking.Default PageLocking.Locked PageLocking.Unlocked

which specifies that page locking should default, be locked, or be unlocked, respectively.

C: ntc\_clock

Fortran: cfg(ntc clock)

Java: cfg.setClockSource(ClockSource)

Specifies which clock to use as a timing source.

For C and Fortran, this value must be NT\_USE\_ARCHITECTURE\_CLOCK.

For Java, one of the following values:

ClockSource.Default ClockSource.RCIMTickClock

The daemon default is to use the Default (Architecture) clock.

C: ntc\_shmid\_perm

Fortran: cnf(ntc\_shmid\_perm)

Java: cnf.setSharedMemoryPermissions(int)

Specifies the permissions to use when creating the shared memory segment. The user daemon default value is 0666.

C: ntc\_daemon\_preferred

Fortran: cnf(ntc\_daemon\_preferred)

Java: cnf.setDaemonSettingsPreferred(boolean)

When set to TRUE, this parameter causes conflicts between the configuration as specified by the user and by the corresponding user daemon to be resolved in favor of the daemon. Otherwise, conflicts will be resolved in favor of the first configuration that executes, which will cause the subsequent user daemon invocation or trace\_begin (or Trace.begin) call to fail.

C: ntc\_num\_buffers, ntc\_buffer\_length

Fortran: cnf(ntc\_num\_buffers), cnf(ntc\_buffer\_length)
Java: cnf.setNumBuffers(int), cnf.setBufferLength(int)

These two parameters define the amount of memory used to hold trace events. The user daemon configuration defaults to 8 buffers which individually hold 32768 events. The values as specified here will be rounded up to the closest power of two. The units of buffer length are in units of minimally-sized events. Some trace event interfaces with additional user-specified arguments require additional space. The default daemon values for these fields are 8 buffers of length 32768.

C: ntc\_daemon\_wait\_usec

Fortran: config(ntc\_daemon\_wait\_usec)

Java: n/a

Specifies the number of microseconds the user daemon should pause between busy-wait contention for control of the shared memory buffers when flushing buffers to the output device. The user daemon configuration for this parameter defaults to 100~us. This value should be kept relatively short to prevent data loss if massive user application trace activity prevents the daemon from flushing the shared memory buffers.

C: ntc\_reserved

Fortran: *cnf*(ntc\_reserved)

Java: n/a

These parameters are reserved for future use; currently, they must be set to zero for proper future operation.

### **DESCRIPTION**

The trace\_begin and Trace.begin routines perform the following operations:

- Verify that the version of the NightTrace library linked with the application is compatible with the version used by the user daemon if it is already running
- Verify the supplied configuration settings are not in conflict with a pre-existing daemon or define the configuration with these settings if the user daemon does not yet exist.
- Attach the shared memory buffer (after creating it if needed)
- Lock critical NightTrace library routine pages in memory as directed.
   Note that you must have the CAP\_SYS\_NICE capability to lock pages in memory (see "Privileged Access" on page C-1 for details).
- Initialize trace event tracing in this process

A process that results from the **execve(2)** system service does <u>not</u> inherit a trace mechanism. Therefore, if that process is to log trace events, it must initialize the trace with trace\_begin or Trace.begin. Processes that result from a fork in a process that has already initialized the tracing session need not call trace\_begin.

The trace\_begin or Trace.begin routine must be called only once per parent process (unless an intervening trace\_end or Trace.end call has been made).

If Application Illumination is used, the main illuminator (see "Application Illumination" on page 4-1) will perform a trace\_begin() call. The **nlight** tool (see "Settings For "main" Illuminator" on page 4-55) can be used to set some of the parameters to this call.

### **RETURN CONDITIONS**

C, and Fortran:

Upon successful operation, the trace\_begin routine returns NTNOERROR or NTLISTEN; the latter in the case where no daemon has yet been started. Otherwise, an error value as defined in ntrace.h and ntrace\_.h is returned, as shown in the Error Code section below.

Java:

The Trace.begin() routine has no return value. It returns if the call is successful (including the case of where no daemon has yet been started). Otherwise, a Trace.Error exception object is thrown, which further describes the error. When caught, you can use the exception object's getError() routine to obtain the specific error enumeration value from the Trace.Error.Msg enumerated type; relevant error code descriptions are shown below.

#### Error Code Enumerations:

#### NTNOERROR

A daemon has already been started that matches the filename passed as *key\_file*.

### NTLISTEN

All operations were successful, but no user daemon matching the filename passed as *key\_file* could be found. The application can continue to make NightTrace API calls but attempts to log events will fail until a daemon is started, at which point logging of events will succeed.

### NOTE

This error enumeration is not ever thrown by the Java API. Calls to Trace.begin() will silently succeed even if a matching daemon has not yet been started.

#### NTALREADY

The application has already initialized the trace without an intervening trace\_end or Trace.end call. Tracing can continue in spite of this error.

### NTBADVERSION

The calling application is linked with the static NightTrace library and the static library is not compatible with the NightTrace library being used by the user daemon. Solution: Relink the application with the static library version which matches the library version being used by the daemon.

### NTPERMISSION

The calling application lacks permission to attach the shared memory buffer. Solution: Make sure that the same user who started the user daemon is the current user logging trace events in the application.

### NTPGLOCK

Permission to lock the text and data pages of the NightTrace library routines was denied. Normally, root access is required to lock pages in memory.

## NTNOSHMID

This can occur if the size of the shared memory buffer exceeds the system limits or the shared memory buffer already exists but the size required by the parameters defining the number of buffers and buffer length exceeds the current size. To increase the system limits on shared memory, adjust the *kernel.shmmni*, *kernel.shmmall*, and *kernel.shmmax* parameters using <code>systcl(8)</code>. Use <code>ipcrm(1)</code> to remove the existing shared memory segment if it is not being used by another application.

#### **SEE ALSO**

• trace\_end(), Trace.end()

# trace\_event, Trace.event and their variants

The following routines log an enabled trace event and possibly some arguments to the shared memory buffer.

# **SYNTAX**

C:

```
int trace_event (int ID);
     int trace_event_arg (int ID, int arg);
     int trace_event_two_arg (int ID, int arg1, int arg2);
     int trace_event_three_arg (int ID, int arg1, int arg2, int arg3);
     int trace_event_four_arg(int ID, int arg1, int arg2, int arg3, int
     arg4);
     int trace_event_long (int ID, long arg);
     int trace_event_two_long (int ID, long arg1, long arg2);
     int trace_event_long_long (int ID, long long arg);
     int trace_event_two_long_long (int ID, long long arg1, long long
     arg2);
     int trace_event_flt (int ID, float arg);
     int trace_event_two_flt (int ID, float arg1, float arg2);
     int trace_event_dbl (int ID, double arg);
     int trace_event_two_dbl (int ID, double arg1, double arg2);
     int trace_event_long_dbl (int ID, long double arg);
     int trace_event_blk(int ID, void *args, int bytes);
     int trace_event_string(int ID, char *str);
Fortran:
     integer function trace_event (ID)
     integer ID
     integer function trace_event_arg (ID, arg)
     integer function trace_event_two_arg(ID, arg1, arg2)
     integer function trace_event_three_arg (ID, arg1, arg2, arg3)
     integer function trace_event_four_arg (ID,arg1,arg2,arg3,arg4)
     integer ID, arg, arg1, arg2, arg3, arg4
     integer function trace_event_long (ID, arg)
```

integer function trace\_event\_two\_long (ID, arg1, arg2)

```
integer ID
     integer arg, arg1, arg2
                                (32-bit OS)
     integer*8 arg, arg1, arg2
                                (64-bit OS)
     integer f unction trace_event_long_long (ID, arg)
     integer function trace_event_two_long_long (ID, arg1, arg2)
     integer ID
     integer*8 arg, arg1, arg2
     integer function trace_event_dbl (ID, arg)
     integer function trace_event_two_dbl (ID, arg1, arg2)
     integer ID
     double precision arg, arg1, arg2
Java:
     package ntrace.logging;
     class Trace {
        static void event(int ID);
        static void event(int ID, int arg);
        static void event(int ID, int arg1, int arg2);
        static void event(int ID, int arg1, int arg2, int arg3);
        static void event(int ID, int arg1, int arg2, int arg3, int arg4);
        static void event(int ID, long arg);
        static void event(int ID, long arg1, long arg2);
        static void event(int ID, double arg);
        static void event(int ID, double arg1, double arg2);
        static void event(int ID, String arg);
        static void event(int ID, char[] arg);
        static void event(int ID, int[] arg);
        static void event(int ID, double[] arg);
        static void event(int ID, byte[] arg);
        static void event(int ID, float[] arg);
        static void event(int ID, long[] arg);
        static void event(int ID, short[] arg);
        static void event(int ID, boolean[] arg);
     }
```

#### **PARAMETERS**

ΙD

Each trace event has a user-defined trace event ID, *ID*. This ID is a valid integer in the range reserved for user trace events (0-4095, and 3,000,000-3,999,999). See "Pre-Defined Strings Tables" on page 6-15 for more information about trace event IDs.

# **IMPORTANT**

Trace event IDs in the range 3,000,000 through 3,999,999 cannot be disabled ("Disabling Tracing" on page 2-31) and can only be used with the function trace\_event\_arg\_blk().

argN

Sometimes it is useful to log the current value of a variable or expression, *arg*, along with your trace event. The trace event logging routines provide this capability. They differ by how many and what types of numeric arguments they accept. If you want the **ntrace** display utility to display these trace event arguments in anything but decimal integer format, you can enter the trace event in an event-map file. See "Event Map Files" on page 6-9 for more information on event-map files and formats. Alternatively, you could call the format function. See "format()" on page 15-178 for details.

### **DESCRIPTION**

A *trace point* is a place in your application's source code where you call a trace event logging routine. Usually this location marks a line that is important to debugging or performance analysis.

## **TIP**

To save time re-editing, recompiling, and relinking your application, consider beginning with many trace points in the source code. You can dynamically enable or disable specific trace events.

Some typical trace points include the following:

- Suspected bug locations
- Process, subprogram, or loop entry and exit points
- Timing points, especially for clocking I/O processing
- Synchronization points for multi-process interaction
- Endpoints of atomic operations
- Endpoints of shared memory access code

Call one trace event logging routine at each of the trace points you have selected. When you call this routine, it writes the trace event information (including timings and any arguments) to a shared memory buffer. By default, if this write fills the shared memory buffer or causes the buffer-full cutoff percentage to be reached, the user daemon wakes up and copies the trace event to the trace event file on disk.

By convention, each trace event logging invocation should log a different trace event ID number. This lets you easily identify which source line logged the trace event, how often that source line executed, and what order source lines executed in. However, it is sometimes useful to log the same trace event ID in multiple places. This makes it possible to group trace events from related, but not identical, activities. In this case, a change of trace event ID usually separates or subdivides groups.

Probably the most common use of trace events is to identify *states*. Typically, two different trace event IDs delimit the boundaries of a state. Most applications log recurring states with different time gaps (from the end of one instance of a state to

the start of another) and different state durations (from the start of one instance of a state to its end).

#### TIP

Consider putting related trace event IDs within a range. Library routines and user daemon options let you manipulate trace events by using trace event ID ranges.

By default, all trace events are enabled for logging. The NightTrace library contains routines that allow you to selectively or globally enable or disable trace events. The user daemon has options that provide similar control. Attempting to log a disabled trace event has no effect. See "trace\_enable, trace\_disable, and their variants" on page 2-18 for more information.

## TIP

Consider using symbolic constants instead of numeric trace event IDs. This would make your calls to NightTrace routines more readable.

Once your application logs all of its trace events, you can look at them and their arguments graphically with State Graphs, Event Graphs, and Data Graphs in the **ntrace** display utility. See "State Graph" on page 11-11, "Event Graph" on page 11-10, and "Data Graph" on page 11-12 for more information about these display objects.

## **RETURN CONDITIONS**

### C.and Fortran:

These routines return a zero value (NTNOERROR) on successful completion. Otherwise, an error value as defined in **ntrace.h** and **ntrace.h** is returned, as shown in the Error Code section below.

### Java:

On successful completion, these routines return without any value. Otherwise, a Trace.Error exception object is thrown, which further describes the error. When caught, you can use the exception object's getError() routine to obtain the specific error enumeration value from the Trace.Error.Msg enumerated type; relevant error code descriptions are shown below.

Error Code Enumerations:

#### NTINVALID

An invalid trace event ID has been supplied. Solution: Use trace event IDs only in the range 0-4095 (or 3,000,000-3,999,999 when used with trace\_event\_arg\_blk()).

#### NTINIT

The NightTrace library routines were not initialized or they were initialized but no user daemon has yet been initiated. Ensure a trace\_begin or Trace.begin call precedes the trace event logging routine call. Once a user daemon is started, subsequent attempts at logging events will succeed.

#### NTLOSTDATA

The trace event was lost because the shared memory buffers were full. This can occur if the user daemon cannot empty the shared memory buffer quickly enough. Increase the priority of the user daemon and/or schedule it on a CPU with less activity. Additionally, the size of the shared memory buffers can be increased using the --num\_bufs and --buflen options to ntraceud, the User Event Buffer settings on the User Trace tab of the Daemon Definition dialog in ntrace tool, or the number of buffers or buffer length can be adjusted as part of the trace\_begin or Trace.begin calls.

### **SEE ALSO**

- trace flush(), Trace.flush()
- trace\_trigger(), Trace.trigger()
- trace\_enable(), Trace.enable()
- trace\_enable\_range()
- trace\_enable\_all()
- trace\_disable(), Trace.disable()
- trace disable range()
- trace\_disable\_all()

# trace\_enable, trace\_disable, and their variants

By default, all trace events are enabled for logging to the shared memory buffer. The trace\_disable, trace\_disable\_range, trace\_disable\_all, and Trace.disable routines respectively make your application ignore requests to log one or more trace events. The trace\_enable, trace\_enable\_range, trace\_enable\_all and Trace.enable routines respectively make your application notice previously disabled requests to log one or more trace events.

## **SYNTAX**

C:

```
int trace_enable (int ID);
     int trace_enable_range (int ID_low, int ID_high);
     int trace_enable_all ();
     int trace_disable (int ID);
     int trace_disable_range (int ID_low, int ID_high);
     int trace_disable_all ();
Fortran:
     integer function trace_enable (I\!D)
     integer ID
     integer function trace_enable_range (ID_low, ID_high)
     integer ID_low, ID_high
     integer function trace_enable_all ()
     integer function trace_disable (ID)
     integer ID
     integer function trace_disable_range (ID\_low, ID\_high)
     integer ID_low, ID_high
     integer function trace_disable_all ()
Java:
     package ntrace.logging;
     class Trace {
        static void enable(int ID);
        static void enable(int ID low, int ID high);
        static void enable();
        static void disable(int ID);
        static void disable(int ID_low, ID_high);
        static void disable();
```

#### **PARAMETERS**

ΙD

Each trace event has a user-defined trace event ID, *ID*. This ID is a valid integer in the range reserved for user trace event IDs (0-4095, inclusive). See "trace\_event, Trace.event and their variants" on page 2-13 for more information.

#### **IMPORTANT**

Trace event IDs in the range 3,000,000-3,999,999 cannot be used with these functions. Such event IDs are always enabled.

ID\_low

It is possible to manipulate groups of trace event IDs by specifying a range of trace event IDs. *ID\_low* is the smallest trace event ID in the range.

ID\_high

It is possible to manipulate groups of trace event IDs by specifying a range of trace event IDs. *ID high* is the largest trace event ID in the range.

#### DESCRIPTION

The enable and disable library routines allow you to select which trace events are enabled and which are disabled for logging. A discussion of disabling trace events appears first because initially all trace events are enabled.

Sometimes, so many trace events that it is hard to understand the **ntrace** display. Occasionally you know that a particular trace event or trace event range is not interesting at certain times but is interesting at others. When either of these conditions exist, it is useful to disable the extraneous trace events. You can disable trace events temporarily, where you disable and later re-enable them. You can also disable them permanently, where you disable them at the beginning of the process or at a later point and never re-enable them.

#### NOTE

These routines enable and disable trace events in <u>all</u> processes that rely on the same user daemon to log to the same trace event file.

All <u>disable</u> library routines make your application start ignoring requests to log trace event(s) to the shared memory buffers. The disable routines differ by how many trace events they disable. trace\_disable, and Trace.disable with a single argument, disable one trace event ID. trace\_disable\_range, and Trace.disable with two arguments, disable a range of trace event IDs, including both range endpoints. trace\_disable\_all, and Trace.disable without any arguments, disable all trace events. Disabling an already disabled trace event has no effect.

All <u>enable</u> library routines let you re-enable a trace event that you disabled with a disable library routine or user daemon. The effect is that your application resumes

noticing requests to log the specified trace event to the shared memory buffers. The enable routines differ by how many trace events they enable. trace\_enable, and Trace.enable with a single argument, enable one trace event ID. trace\_enable\_range, and Trace.enable with two arguments, enable a range of trace event IDs, including both range endpoints. trace\_enable\_all, and Trace.enable without arguments, enable all trace events. Enabling an already enabled trace event has no effect.

#### TIP

Consider invoking the user daemon with events disabled instead of calling the enable and disable routines. Using these options saves you from re-editing, recompiling and relinking your application.

#### TIP

If you want to log only a few of your trace events, disable all trace events and then selectively enable the trace events of interest.

#### **RETURN CONDITIONS**

#### C.and Fortran:

These routines return a zero value (NTNOERROR) on successful completion. Otherwise, an error value as defined in ntrace.h and ntrace\_.h is returned, as shown in the Error Code section below.

## Java:

On successful completion, these routines return without any value. Otherwise, a Trace. Error exception object is thrown, which further describes the error. When caught, you can use the exception object's getError() routine to obtain the specific error enumeration value from the Trace. Error. Msg enumerated type; relevant error code descriptions are shown below.

## Error Code Enumerations:

#### NTINIT

The NightTrace library routines were not initialized. Solution: Be sure a trace\_begin or Trace.begin call precedes the call to the disable or enable routine.

#### NTINVALID

An invalid trace event ID has been supplied. Solution: Use trace event IDs only in the range 0-4095, inclusive.

# **SEE ALSO**

• trace\_event, Trace.event and its variants

# trace\_flush, Trace.flush, trace\_trigger, and Trace.trigger

The flush and trigger routines asynchronously wake the user daemon and direct it to copy trace events from the shared memory buffers to the trace event file on disk. Note: These routines do <u>not</u> wait for the copy to complete.

## **SYNTAX**

```
C:
    int trace_flush();
    int trace_trigger();
Fortran:
    integer function trace_flush()
    integer function trace_trigger()

Java:
    package ntrace.logging;
    class Trace {
        static void flush();
        static void trigger();
    }
```

## **DESCRIPTION**

When the user daemon is idle, it sleeps. The process of copying trace events from the shared memory buffers to a trace event file is called *flushing the buffers*. The user daemon wakes up and flushes when any of these conditions exist:

- At least one of the individual buffers is filled with trace events
- Your application calls trace\_flush, trace\_trigger, trace\_end, Trace.flush, Trace.trigger, or Trace.end
- ntraceud is invoked with the --flush-now option
- The NightTrace graphical analysis tool requests a flush for immediately analysis of the latest trace events

### **TIP**

The trigger functions work identically to the flush functions, except that the trigger functions work only in buffer-wraparound mode. Call trace\_trigger instead of trace\_flush so that only buffer-wraparound's performance is affected.

When you run in buffer-wraparound mode, you are telling NightTrace to intentionally discard older (and therefore presumably less-vital) trace events when the shared

memory buffer gets full. In buffer-wraparound mode, you must explicitly call trace\_flush, Trace.flush, trace\_trigger, or Trace.trigger. Only then, does the user daemon copy the remaining trace events from the shared memory buffer to the trace event file. However, do not call these functions too often or you will reduce the effectiveness of this mode. See "ntraceud Options" on page 3-3 for more information on buffer-wraparound mode.

# **RETURN CONDITIONS**

# C, and Fortran:

The trace\_flush and trace\_trigger routines return a zero value (NTNOERROR) on successful completion. Otherwise, an error value as defined in **ntrace.h** and **ntrace\_.h** is returned, as shown in the Error Code section below.

#### Java:

On successful completion, these routines return without any value. Otherwise, a Trace. Error exception object is thrown, which further describes the error. When caught, you can use the exception object's getError() routine to obtain the specific error enumeration value from the Trace. Error. Msg enumerated type; relevant error code descriptions are shown below.

# Error Code Enumerations:

#### NTFLUSH

A failure occurred while attempting to flush the shared memory buffer. Solution: Verify the status of the user daemon; if necessary, restart it and rerun the trace.

## **SEE ALSO**

• trace\_event, Trace.event and its variants

# trace\_set\_thread\_name, Trace.setThreadName

The trace\_set\_thread\_name and Trace.setThreadName routines associate the current C thread, or Java thread with a user-specified name. Use of this library routine is optional, as described in the Description paragraph below.

## **SYNTAX**

```
C:
    int trace_set_thread_name(const char *thread_name);
Fortran:
    integer function trace_set_thread_name(thread_name)
    character *(*) thread_name

Java:
    package ntrace.logging;
    class Trace {
        static void setThreadName(String thread_name);
    }
```

#### **PARAMETERS**

thread\_name

NightTrace's graphical displays and textual summary information indicate which threads logged trace events.

Naming your threads can make the displays much more readable. This function lets you associate a meaningful character string name with the current threads' more cryptic numeric ID. If you provide a character string as the thread name, the **ntrace** display utility uses it as a label in its displays. Because **ntrace** may be unable to display long strings in the limited screen space available, keep thread names short.

Thread names should be limited to alpha-numeric characters and should contain at least one non-numeric character. Names that are entirely numeric may be discarded if a more descriptive name is available (including the default thread name "main"). Some special characters are allowed, but their use is not recommended. Do not use the names "ALL" or "NONE" as they are used internally within NightTrace and may cause unexpected results.

### **DESCRIPTION**

When using Java or when linking with the thread-aware version of the NightTrace Logging API library (libntrace\_thr), the default thread name is formed directly from the thread's internal gettid(2) value.

For C programs, if not using the thread-aware version of the library, you cannot distinguish which threads logged which trace events -- all threads share the same name.

By default, the main program thread is called "main".

Calling trace\_set\_thread\_name or Trace.setThreadName sets the name of the calling thread to the specified name, overriding any previous name, default or otherwise, given to the thread.

Calling trace\_set\_thread\_name or Trace.setThreadName multiple times for the same thread is not recommended, as it can cause confusion. Depending on the mode of trace event collection, some trace event may have the prior name and some may have the new name -- or, all trace events may have the name associated with the last call to trace\_set\_thread\_name.

## **RETURN CONDITIONS**

#### C.and Fortran:

The trace\_set\_thread\_name routine returns a zero value (NTNOER-ROR) on successful completion. Otherwise, an error value as defined in **ntrace.h** and **ntrace\_.h** is returned, as shown in the Error Code section below.

Java:

On successful completion, Trace.setThreadName returns without any value. Otherwise, a Trace.Error exception object is thrown, which further describes the error. When caught, you can use the exception object's getError() routine to obtain the specific error enumeration value from the Trace.Error.Msg enumerated type; relevant error code descriptions are shown below.

Error Code Enumerations:

NTINVALID

An invalid thread name was specified.

# SEE ALSO

- trace\_begin(), Trace.begin()
- trace\_close\_thread(), Trace.closeThread()

# trace\_close\_thread, Trace.closeThread

The trace\_close\_thread and Trace.closeThread routines inform the Night-Trace Logging API library that the calling thread will no longer log trace events. These functions are only useful when you have a multi-threaded application which has been linked with the thread-aware version of the NightTrace Logging API library (libntrace\_thr) or you have a multi-threaded Java program.

#### **SYNTAX**

```
C:
    int trace_close_thread;
Fortran:
    integer function trace_close_thread
Java:
    package ntrace.logging;
    class Trace {
        static void closeThread();
}
```

## **DESCRIPTION**

Use of this function is optional, but it is good practice to call this function for all threads which have logged trace events.

If you do not call trace\_close\_thread or Trace.closeThread and you have logged trace events from a thread other than the main program thread, then the shared memory resources associated with the NightTrace logging API session will remain attached to the process even after a call to trace\_end or Trace.end is made.

#### **RETURN CONDITIONS**

C,and Fortran:

The trace\_close\_thread routine returns a zero value (NTNOERROR) on successful completion. Otherwise, it returns a non-zero value to identify the error condition. A list of trace\_close\_thread error codes follows.

Java:

On successful completion, Trace.closeThread returns without any value. Otherwise, a Trace.Error exception object is thrown, which further describes the error. When caught, you can use the exception object's getError() routine to obtain the specific error enumeration value from the Trace.Error.Msg enumerated type; relevant error code descriptions are shown below.

Error Code Enumerations:

NTINIT

The NightTrace library routines were not initialized by a call to trace begin or Trace.begin.

# **SEE ALSO**

• trace\_begin(), Trace.begin()

trace\_end(), Trace.end()

# trace\_end, Trace.end

The trace\_end and Trace.end routines free resources and terminate the trace session in your process. Use of these routines is not strictly necessary, since all tracing resources are automatically freed when the application exits. However, for applications that may continue to execute but have no need for subsequent tracing, calling these routines is appropriate.

# **SYNTAX**

```
C:
    int trace_end;
Fortran:
    integer function trace_end
Java:
    package ntrace.logging;
    class Trace {
        static void end();
    }
```

# **DESCRIPTION**

This routine performs the following operations:

- Terminates trace event tracing in this process
- Flushes trace events from the shared memory buffer to the trace event file
- Detaches the shared memory buffer

## **NOTE**

If you have a multi-threaded program linked with the thread-aware version of the NightTrace logging API, the shared memory will not be detached from the process if you have logged trace events from threads which have not yet called trace\_close\_thread.

 Notifies the user daemon that the current process has finished logging trace events

#### **RETURN CONDITIONS**

C,and Fortran:

The trace\_end routine returns a zero value (NTNOERROR) on successful completion. Otherwise, an error value as defined in **ntrace.h** and **ntrace.h** is returned, as shown in the Error Code section below.

#### Java:

On successful completion, Trace.end returns without any value. Otherwise, a Trace.Error exception object is thrown, which further describes the error. When caught, you can use the exception object's getError() routine to obtain the specific error enumeration value from the Trace.Error.Msg enumerated type; relevant error code descriptions are shown below.

## Error Code Enumerations:

# NTFLUSH

A failure occurred while attempting to flush the shared memory buffer. Solution: Verify the status of the user daemon; if necessary, restart it and rerun the trace.

#### NTNODAEMON

There is no user daemon with a trace event file name that matches the one on the trace\_begin or Trace.begin call attached to the shared memory region. This condition is not always detectable. Solution: Use the **ntrace** display utility to analyze your logged trace events.

## **SEE ALSO**

- trace\_begin(), Trace.begin()
- trace\_close\_thread(), Trace.closeThread

# trace\_diag\_mode

The trace\_diag\_mode routine controls the generation of diagnostics for critical Night-Trace API routines.

The NightTrace API diagnostic routine is called when critical errors occur for some NightTrace API routines if the diagnostic mode is set to TRUE (on).

#### **SYNTAX**

```
C:
    void trace_diag_mode (int on);
Fortran:
    external trace_diag_mode

Java:
    package ntrace.logging;
    class Trace {
        static void enableDiagnostics(boolean);
    }
```

#### DESCRIPTION

These functions control whether diagnostic text is sent to stderr by NightTrace logging API routines when significant or critical errors are encountered. Regardless of the setting of the diagnostic mode, individual functions within the NightTrace logging API will use return values (or exceptions in the case of Java) to inform you of error conditions.

For C and Fortran, specify a zero value to turn diagnostics off, or a non-zero value to enable diagnostics.

For Java, pass true to enable diagnostics, and false to disable them.

For C, the NightTrace API diagnostic routine may be changed via the trace\_diag\_func routine.

## **NOTE**

Setting the **NTRACE\_SILENT** environment variable to a non-null value will prevent diagnostics routines from being called, regardless of the diagnostic mode setting.

#### SEE ALSO

• trace\_diag\_func()

# trace\_diag\_func

The trace\_diag\_func routine replaces the default NightTrace API diagnostic routine with one supplied with the function invocation.

#### SYNTAX

C:

```
void trace_diag_func (void(*func)(char*,int));
```

## **DESCRIPTION**

The specified function is invoked when critical errors occur for some NightTrace API routines if the trace diagnostic mode is set to TRUE. If this function is not called, an internal NightTrace library routine is invoked when significant errors occur, which prints a diagnostics to stderr, unless the diagnostics have been turned off via trace\_diag\_mode().

# **NOTE**

Setting the **NTRACE\_SILENT** environment variable to a non-null value will prevent diagnostics routines from being called, regardless of the diagnostic mode setting.

# **SEE ALSO**

• trace\_diag\_mode()

# **Disabling Tracing**

There are five ways to disable tracing in your application:

 For C applications that include /usr/include/ntrace.h, you must recompile your application with the -DNNTRACE preprocessor option or insert the following preprocessor control statement <u>before</u> the #include <ntrace.h>.

#define NNTRACE

The NightTrace header file, ntrace.h, contains macro counterparts for each NightTrace library routine. When you define NNTRACE, the compiler treats your NightTrace routine calls as if they were macro calls that always return a success (zero) status.

• Call the trace\_disable\_all routine near the top of the source, recompile, and relink your application. (For more information about this routine, see "trace\_enable, trace\_disable, and their variants" on page 2-18.) If your application calls any of the enable routines, this method is not entirely effective.

#### NOTE

Event IDs in the range 3,000,000-3,999,999 cannot be disabled by this mechanism.

- Start a user daemon with all events disabled.
- Do not start a user daemon.

The trace library routines have been highly optimized to have minimal overhead, especially when no user daemon has been initiated.

• If you application trace instrumentation was done solely via Application Illumination, you can make the instrumentation 100% inert with zero overhead to the application by deactivating it using the nlight tool. You can then reactivate instrumentation (without relinking) at a subsequent time. See "Command for Activating and Deactivating Illuminators" on page 4-74 for more information.

# **Threads and Logging**

In order to distinguish between multiple threads in a multi-threaded application, the following step must be taken:

• C applications must be linked with the thread-aware version of the Night-Trace logging API by specifying the **-lntrace\_thr** link option. • Threaded Java applications automatically include the **-lntrace\_thr** library when using the ntrace.logging.Trace class.

If the thread-aware version of the library is not used, calls to log trace events from threads will succeed but cannot be distinguished from other threads or the main thread.

By default, when using the thread-aware version of the library, threads are named using their internal **gettid(2)** value. You can explicitly set the name of a thread to something more useful by calling trace\_set\_thread\_name or Trace.setThread-Name.

# NightTrace CUDA Tracing API

The API for CUDA tracing consists of functions found in the following include files:

```
/usr/include/ntrace_cuda.h
/usr/include/ntrace_cuda_device.h
```

# ntrace\_cuda.h

This include file defines the functions and types used to initiate a tracing session for a CUDA application and to flush any trace data from memory to the collecting daemon.

See "ntrace\_cuda\_device.h" on page 2-35 for information on functions used to actually generate trace points in GPU-executed code.

# **SYNTAX**

```
ntrace_cuda_context ntrace_cuda_begin(
    const char * filename,
    ntconfig_t * config = NULL,
    unsigned    flags = 0,
    int        buffer_size_events = 0x1000);

ntrace_cuda_handle * ntrace_cuda_sync(
    ntrace_cuda_context ncc);

int ntrace_cuda_flush(
    ntrace_cuda_context ncc);

vooid ntrace_cuda_end(
    ntrace_cuda_context ncc);
```

## **PARAMETERS**

filename

This parameter to ntrace\_cuda\_begin identifies the tracing session and enables inter-process communication between a NightTrace collection daemon and the application generating trace events. This parameter would also be passed to the invocation of a NightTrace daemon as a command line arguments. See "The ntraceud Daemon" on page 3-1 for more information.

The file must be writable and may already exist, but its contents will be overwritten.

config

This optional parameter to ntrace\_cuda\_begin allows you to specify daemon collection parameters. See /usr/include/ntrace.h for more information.

flags

This optional parameter to ntrace\_cuda\_begin is reserved for future use. If specified, its value must currently be zero.

buffer size events

This optional parameter defines the size of the memory block which is allocated out of GPU memory to hold trace events. It is specified in units of a minimally sized event (an event with no arguments, which is 24 bytes).

Trace events logging in GPU-executed code reside completely in GPU memory until flushed out to the collection daemon by a call to ntrace\_cuda\_flush().

If the memory buffer fills during GPU execution, it will overwrite the oldest events, preserving the latest events.

ncc

This parameter is used with many of the API functions. It defines the context of the NightTrace CUDA session.

It is returned from ntrace\_cuda\_begin and must be passed to the other functions described above.

### **SEMANTICS**

ntrace\_cuda\_begin

This function initiates a NightTrace CUDA session. No other NightTrace CUDA API calls can be made until this function is called and completes successfully.

It creates or attaches to a shared memory segment based on the name of the *filename* parameter. This shared memory segment allows a NightTrace daemon to collect data from the application.

It also allocates a memory buffer in CUDA device memory. This buffer is used to hold all CUDA trace events until ntrace cuda flush is called.

This function also initiates a normal NightTrace session, in the same manner as trace\_begin (see "trace\_begin, Trace.begin" on page 2-7). Thus after ntrace\_cuda\_begin completes, you can log trace events in CPU-executed code as well as in GPU-executed code.

ntrace\_cuda\_sync

This function synchronizes the GPU clocks with the system timing device and returns a handle which must be passed through to user code that executes on the GPU. The handle is a required parameter for logging all trace points in GPU-executed code.

#### **IMPORTANT**

Do not make copies or otherwise reuse the return value of ntrace\_cuda\_sync in CPU-executed code. Only pass the return value through to GPU- executed code on each *kernel* launch (*kernel* is this context is a CUDA term representing a segment of user code that is executed by the GPU).

ntrace\_cuda\_flush

This function transfers all the events from the buffer in CUDA device memory to the shared memory buffer so that a NightTrace daemon may collect the events.

# **IMPORTANT**

No CUDA trace events will be passed to the NightTrace daemon until this function is called. Typically, you will launch a kernel, wait for the GPU to finish its execution, and then call this function to copy the events from GPU memory into the shared memory buffer.

ntrace\_cuda\_end

This function terminates the NightTrace CUDA session. While it is not strictly necessary to call this function, it does free up the memory resources it allocated and detaches from the shared memory buffer created or attached in ntrace\_cuda\_begin.

### **RETURN VALUES**

ntrace\_cuda\_begin

A non-zero *ntrace\_cuda\_context* value is returned on success. Otherwise, a zero value is returned and a diagnostic is printed to stderr describing the problem.

ntrace\_cuda\_sync

An *ntrace\_cuda\_handle\** is returned. This value should be passed to a kernel invocation as it is required as a paramter to all ntrace\_cuda\_event functions. See "ntrace\_cuda\_device.h" on page 2-35 for more information.

```
ntrace_cuda_flush
```

A zero value is returned on success. Otherwise, a diagnostic is printed to stderr describing the problem.

# ntrace cuda device.h

## **SYNTAX**

```
void ntrace cuda event(
    ntrace cuda handle * h,
    int id);
void ntrace_cuda_event(
    ntrace_cuda_handle * h,
    int id,
    int arg1 [,arg2[,arg3[,arg4[,arg5]]]]);
void ntrace cuda event(
    ntrace_cuda_handle * h,
    int id,
    long arg1 [,arg2]);
void ntrace_cuda_event(
    ntrace cuda handle * h,
    float arg1 [,arg2[,arg3[,arg4[,arg5]]]]);
void ntrace cuda event(
    ntrace_cuda_handle * h,
    int id
    double arg1 [,arg2]);
void ntrace_cuda_event(
    ntrace cuda handle * h,
    int
                          id.
    void
                        * data,
    int
                         bytes);
```

# **SEMANTICS**

The required *ntrace\_cuda\_handle\** parameter should be the value returned from ntrace\_cuda\_sync that was passed as an argument during the CUDA kernel launch.

An trace event is logged into GPU device memory with the specified *id* and optional *arguments*. Valid values of *id* include 0-4095 and 3,000,000-3,999,999.

The following information is automatically logged with the event; you do not need to pass this information as arguments:

• The symmetric processor ID

- The thread dimensions
- The block dimensions
- The lane ID
- The warp ID
- The raw clock time

See "cuda functions" on page 15-45 for a description on how you can retrieve this information from events within **ntrace**.

As indicated in the pseudo-syntax above, you can pass from 1 to 5 int arguments, 1 to 5 float arguments, and 1 to 2 long or double arguments.

The last form of the function allows you to pass an arbitrary number of bytes as arguments, as defined by the *data* and *bytes* parameters.

The events are stored into the buffer in wrap-around mode. Thus if the buffer fills, the newest events overwrite the oldest events in the buffer.

The buffer is flushed by a call to ntrace\_cuda\_flush in CPU-executed code only.

Some example source code can be found in the section entitled "CUDA Example" on page D-11.

# **Compiling and Linking**

You must link in the NightTrace library so that your application can initialize its trace mechanism and log trace events.

For single-threaded applications, specify the /usr/lib/libntrace.a library.

For multi-threaded applications, specify the /usr/lib/libntrace\_thr.a library (Multi-threaded Java applications will automatically use the threaded NightTrace library).

# **C** Compilation and Linking

Single-threaded example:

```
$ cc app.c -Intrace
```

Multi-threaded example:

```
$ cc app.c -lntrace_thr -lpthread
```

See "NightTrace Logging API Examples" on page D-1 for more demonstrative examples.

# **Fortran Compilation and Linking**

```
$ g77 app.f -Intrace
```

See "NightTrace Logging API Examples" on page D-1 for more demonstrative examples.

# **Java Example**

Ensure that a path to a valid Java development environment **bin** directory is in your \$PATH variable.

```
$ javac -classpath /usr/lib:. app.java
```

See "NightTrace Logging API Examples" on page D-1 for more demonstrative examples.

# **CUDA Example**

Single-threaded example:

```
$ nvcc \
--gencode=arch=compute_11,code=\"sm_11,code=compute_11\" \
--gencode=arch=compute_20,code=\"sm_20,code=compute_20\" \
--compiler-options -DUNIX -g -G -I/usr/include \
-c device_code.cu
$ cc main.c device_code.o ... -Intrace_cuda -Intrace
```

Multi-threaded example:

```
$ nvcc \
--gencode=arch=compute_11,code=\"sm_11,code=compute_11\" \
--gencode=arch=compute_20,code=\"sm_20,code=compute_20\" \
--compiler-options -DUNIX -g -G -I/usr/include \
-c device_code.cu
$ cc main.c device_code.o ... -lntrace_cuda -lntrace_thr
```

See "NightTrace Logging API Examples" on page D-1 for more demonstrative examples.

# Capturing User Events with ntraceud

A user daemon is required in order to capture trace events logged by user applications. There are two methods for controlling user daemons:

- Use the graphical user interface provided in the **ntrace** dialog as described in "Edit Daemon Definition" on page 8-8.
- Use the command line tool **ntraceud**.

The interactive interface is often more convenient and easier to use and additionally offers concurrent viewing of trace events while the application continues to log trace data; this optional feature is called <u>streaming</u>. Alternatively, the **ntraceud** command line tool is useful in scripts where automation is required.

This chapter describes the **ntraceud** command line tool broken down into the following topics:

- "The ntraceud Daemon" on page 3-1
- "ntraceud Modes" on page 3-2
- "The Default User Daemon Configuration" on page 3-2
- "ntraceud Options" on page 3-3
- "Invoking ntraceud" on page 3-6

# The ntraceud Daemon

When you start up **ntraceud**, it creates a daemon background process and then returns control to the invoking program, normally the shell. The daemon creates a shared memory buffer in global memory. Your application writes trace events into this buffer, and the daemon copies these trace events to the output device, usually a file.

You supply the name of the trace event file on your **ntraceud** invocation and in the trace\_begin() library call in your application. If this file does not exist, **ntraceud** creates it; otherwise, **ntraceud** overwrites it.

A single **ntraceud** daemon may service several running applications or processes. Several **ntraceud** daemons can run simultaneously; the system identifies them by their distinctive trace event file names. The **ntraceud** daemon resides on your system under/**usr/bin/ntraceud**.

The daemon remains idle until one of the following conditions exist:

· One of the shared memory buffers fills

- You terminate execution of ntraceud
- Your application calls trace\_flush(), trace\_trigger(), or trace\_end()
- A subsequent invocation of **ntraceud** explicitly requests a flush

# ntraceud Modes

By default, **ntraceud** operates in an expansive mode, continually increasing the size of the output file as events are copied from the shared memory buffers to disk.

**ntraceud** also offers a file-wrap mode. This mode essentially places a limit on the maximum size the file can grow to. Once the limit is reached, the oldest events in the file are overwritten.

**ntraceud** also offers a buffer-wrap mode. In this mode, the shared memory buffers are filled without waking the daemon. When all buffers have been filled, the oldest events are overwritten with the newest ones. No disk activity occurs until **ntraceud** is terminated, or an explicit flush operation is requested, at which time, all buffers are copied to the output file.

Both file-wrap and buffer-wrap modes may be used together.

# The Default User Daemon Configuration

Invoking **ntraceud** with a trace event file argument and without any options will attempt to start a user daemon with the default user daemon configuration. You can override defaults by invoking **ntraceud** with particular options. Table 3-1 summarizes these options. Detailed descriptions of these options are described in the following section.

However, if a user application has already been initiated, it may have specified a non-default configuration via the trace\_begin() call. If the critical settings in the configuration defined by the user application differ from those specified by **ntraceud**, then **ntraceud** will fail to initialize with an appropriate diagnostic.

In the default configuration, <u>all</u> trace events are enabled for logging. Your application logs trace events to the shared memory buffer. By default, an architecture-specific timing source is utilized, which for Intel and AMD Opteron based machines is the Time Stamp Counter (TSC register). On operating systems that support the Real-Time Clock and Interrupt Module (RCIM), the RCIM's clock can be used as a timestamp source by using the **-rcim** option to **ntraceud** (see "ntraceud Options" on page 3-3).

**ntraceud** and the NightTrace library routines optionally use page locking to prevent page faults during trace event logging.

A summary of NightTrace configuration defaults follows.

Table 3-1. NightTrace Configuration Defaults

Characteristic	Default	Modifying Option
Number of buffers	8	numbufs=number
Size of each buffer	32768 raw events	buflen=len
Buffer wrap mode	No wrapping	bufferwrap
Trace event file size	Indefinite	filewrap=bytes
Trace events enabled for logging	All	disable =ID and enable=ID
Page Locking	No Page Locking	lock

# ntraceud Options

**ntraceud** copies trace events from shared memory buffers to the output device, which is normally a file.

The **ntraceud** invocation syntax is:

ntraceud [options] trace-filename

The *trace-filename* parameter is required for all **ntraceud** invocations. When starting a daemon, it defines the shared memory identifier that the daemon and application will use to communicate. When requesting statistics for a running daemon or when stopping a daemon, it identifies the running daemon. Finally, unless run in streaming mode, the *trace-filename* defines the output file which will hold trace events as they are copied from memory.

The command-line options to **ntraceud** are:

# --bufferwrap

-b

Collect events in the shared memory buffers, but do not output them to the output device until **ntraceud** is terminated or an explicit flush request occurs via an **ntraceud** invocation or from the NightTrace Logging API.

When the shared memory buffers are completely filled, the oldest trace events are overwritten by the newest events.

# --buflen=buflen

-Bl buflen

Sets the length of each of the shared memory buffers used by **ntraceud** to *buflen*. The value represents the number of parameterless events that can be stored in each buffer. The value *buflen* should be a power of 2 -- otherwise the

value is automatically adjusted by **ntraceud**. Use this option in conjunction with **--numbufs** to control the amount of shared memory to be used. The default value for *buflen* is 32768. Note that trace\_event\_arg API calls (and other similar interfaces which include parameters) consume more space than those without parameters.

Specifying a large value may exceed the system limitation on the maximum size of shared memory. You can adjust the system limitation by changing the *kernel.shmmax* and *kernel.shmall* variables via the **sysctl(8)** command.

```
--disable=ID[-ID]
--enable=ID[-ID]
-d ID[-ID]
-e ID[-ID]
```

Disable or enable one trace event ID or a range of trace event IDs, as defined by *ID* or the range *ID-ID*, from being logged. Any number of these options may be specified. Upon the first invocation of **ntraceud** that creates the daemon process, the first **--enable** option disables all other trace events. When **ntraceud** is invoked subsequently to adjust status of events for the current session, **--enable** options only enable the specified trace events. By default, all trace events are enabled.

```
--filewrap=bytes
-fw bytes
```

Start the **ntraceud** daemon in file-wrap mode such that the maximum trace file size will be *bytes* bytes. A *K* or *M* suffix indicates that the size is in kilobyte or megabyte units, respectively. Once the maximum size has been reached, **ntraceud** overwrites the oldest trace events logged by the application.

### --flush

This option forces a flush of all shared memory buffers that contain trace events. This is especially useful when the daemon is operating in bufferwrap mode or **ntraceud** is stream data to an application linked with the Night-Trace Analysis API when the rate of events is relatively low.

```
--help
```

Display a brief description of **ntraceud** options to *stdout* and exit.

```
--info
```

Display summary information about a running **ntraceud** daemon. The display includes information about the number of events generated, events in the shared memory buffers, events written to the output device and any data loss that has occurred.

Data loss usually occurs because your application is writing trace events to the shared memory buffers faster than **ntraceud** can copy them to the trace-event file. Limit data loss by increasing the **--numbufs** and

--buflen option settings or using --bufferwrap and by executing ntraceud with urgent priority.

# --join

-j

Allow the initiation of an **ntraceud** daemon even if a user application has already initiated a trace session using the specified *trace-filename* argument.

#### --lock

#### --no-lock

Specify whether critical pages are to be locked in memory or should not be locked in memory. Note that you must have the CAP\_IPC\_LOCK capability to lock pages in memory (see "Privileged Access" on page C-1 for details).

## --numbufs=numbufs

## -Bn numbufs

Sets the number of shared memory buffers used by **ntraceud** to *numbufs*. The value *numbufs* should be a power 2 -- the value is automatically adjusted by **ntraceud** if this is not the case. Use this option in conjunction with **--buflen** to control the amount of shared memory to be used. The default value of *numbufs* is 8.

Specifying a large value may exceed the system limitation on the maximum size of shared memory. You can adjust the system limitation by changing the *kernel.shmmax* and *kernel.shmmall* variables via the **sysct1(8)** command.

# --policy=pol

This option sets the scheduling policy under which the daemon will operate. The *pol* parameter must be *other*, *fifo*, or *rr*, indicating standard interactive, real-time first-in first-out or real-time round-robin scheduling, respectively. By default, *pol* is *other*. Use this option in conjunction with --priority and --processor to adjust the scheduling attributes of ntraceud. See sched\_setscheduler(2) for more information on scheduling policies. Note that you must have the CAP\_SYS\_NICE capability to set a real-time scheduling policy (see "Privileged Access" on page C-1 for details).

#### --priority=prio

This option sets the scheduling priority under which the daemon will operate. The *prio* parameter must be an integer priority value which is consistent with the range of priorities allowed by the associated scheduling class set via the **--policy** option. By default, *prio* is 0 and the scheduling policy is *other* which dictates normal interactive scheduling. See **sched\_setscheduler(2)** for more information on scheduling priorities. Note that you must have the CAP\_SYS\_NICE capability to set a real-time scheduling priority (see "Privileged Access" on page C-1 for details)

## --processor=bias

The *bias* parameter must be a comma-separated list of logical CPU numbers or ranges. This option restricts the daemon to only run on the specified CPU(s).

# --quit -q

After all processes associated with the **ntraceud** session defined by *trace-filename* have exited or called trace\_end, flush all remaining events in the shared memory buffers, terminate the corresponding **ntraceud** daemon, remove the corresponding shared memory identifier, and close the file. This option causes **ntraceud** to wait for all processes to either exit or call trace\_end before tracing is terminated, whereas the **--quit-now** option terminates the daemon without waiting.

# --quit-now -qn

Immediately flush all remaining events in the shared memory buffers, terminate the corresponding **ntraceud** daemon, remove the corresponding shared memory identifier, and close the file.

#### --rcim

Specify use of the RCIM synchronized tick clock as the timing source. This option is useful when simultaneously capturing data from multiple systems since the RCIM tick clock can be synchronized between systems.

This option is only available on operating systems that support the RCIM.

#### --stream

This option causes binary trace data to be output to *stdout*. This option is intended to provide streaming data to applications using the NightTrace Analysis API; e.g. ntraceud --stream /tmp/key | a.out. In this case, the *trace-filename* specified is not modified (although it will be created if it does not already exist).

# --version

Display the current **ntraceud** version to *stdout* and exit.

# Invoking ntraceud

This section describes a few common **ntraceud** invocation examples. In each example, the *trace\_file* argument corresponds to the trace event file name you supply on your call to the trace\_begin() library routine.

Normally, your first **ntraceud** invocation looks something like the following sample.

```
ntraceud trace_file
```

The following invocation might be used when tuning your NightTrace configuration because you lost trace events last time.

```
ntraceud --numbufs=16 --buflen=65536 trace_file
```

To eliminate any disk activity, or to run for long periods of time and only capture the latest data, the following invocation might be used.

```
ntraceud --bufferwrap trace_file
```

To conserve disk space for long runs, the following invocation might be used.

```
ntraceud --filewrap=bytes trace_file
```

The following invocation should be used when the user application is already running and you wish to start collecting trace data from it.

```
ntraceud --join trace_file
```

To obtain information on the status of an active daemon, the following invocation could be used:

```
ntraceud --info trace_file
```

The following invocation waits for all user applications associated with the running **ntraceud** daemon to terminate, flushes remaining trace events to the trace event file, closes the file, removes the shared memory buffer, then terminates the running **ntraceud**.

```
ntraceud --quit trace_file
```

Similarly, the following invocation immediately flushes remaining trace events to the trace file, closes the file, and terminates the running **ntraceud** daemon. User applications can continue to run and make NightTrace Logging API calls, but no trace events will be logged. Subsequently, a new user daemon can be initiated and trace events will start being logged again:

```
ntraceud --quit-now trace_file
```

To provide streaming trace data to an application written using the NightTrace Analysis API, the following information could be used:

```
ntraceud --stream trace_file | ./a.out
```

Note that in the above invocation, the *trace\_file* parameter serves only as a handle for communication between the daemon and the user application that is logging the events; no data is written to the file. The **--stream** option instructs that the binary data stream be redirected to *stdout*. See "NightTrace Analysis Application Programming Interface" on page 16-1 for more information.

NightTrace LX User's Guide

# **Application Illumination**

The challenge of debugging real-time programs is that problems are often time sensitive. Stepping through the program one statement at a time with a traditional debugger is little help in debugging such problems. Even the expedience of inserting printf() statements may introduce sufficient I/O overhead to interfere with the behavior of a real-time program. NightTrace's trace points have little overhead, but it can be tedious to insert large numbers of them into the source code.

Application Illumination is a facility to automatically generate trace points for function calls and returns. It patches them into the object code, and thus requires no source changes.

This chapter describes the Application Illumination facility and consists of the following sections:

- "Overview" on page 4-2
- "The nlight Graphical User Interface" on page 4-6
- "Wizard" on page 4-17
- "Session Manager" on page 4-40
- "Console" on page 4-63
- "Predefined Illuminators" on page 4-64
- "Illuminator Files" on page 4-66
- "nlight Command Line Mode" on page 4-68
- "Customizing an Illuminator with the Editor" on page 4-77
- "Customizing an Illuminator by Editing the config.xml File" on page 4-100

# **Overview**

# Illuminator

An *illuminator* is a directory that contains an object file with a set of "wrapper" routines, an event map and format tables for **ntrace** to use, and various other support files. Calls to the routines that are going to be traced will be diverted to their corresponding "wrapper" functions, which record the entry event, call the real function, record the return event, and then return to the original call site.

# nlight

**nlight** is the tool used to create, manipulate, and use illuminators. It can be used via command line options or in GUI mode.

# **Work Flow Illustration**

The following transcript illustrates illuminating the code of a simple user program using nlight command line options.

1. Build your code with debug information so that Application Illumination knows the signatures of your functions:

```
$ gcc -g -c *.c
$ gcc *.o
```

2. Create and build an illuminator called a.ai for the a.out program:

```
$ nlight --build=a.ai a.out
```

3. Relink your program with the illuminator that was constructed in step 2, along with a predefined illuminator called main that performs the trace\_begin() operation. At this point, although the illuminators are linked into the program, they are inert. Calls to the routines to be traced are still called directly. Illuminators may sit in your program unused and not interfering with performance at all until you need them.

```
$ gcc *.o -o a.outAI 'nlight --gcc main a.ai'
```

4. Activate the illuminators in **a.outAI**. Calls to the routines to be traced are now diverted to the "wrapper" functions.

```
$ nlight --illuminate=a.outAI main a.ai
```

5. Start up a daemon to record the events, run the program, shut the daemon down, and run **ntrace**, which finds the trace file and illuminator support files from paths embedded in **a.outAI**:

- \$ ntraceud trace\_file
- \$ a.outAI
- \$ ntraceud -q trace\_file
- \$ ntrace a.outAI

## **Provided Illuminators**

Illuminators are provided for some system libraries: glibc, pthread, ccur\_rt, and cuda (on some systems). Since the building of illuminators depends on DWARF debug information which is not normally in system libraries, creating custom illuminators for system libraries requires the installation of appropriate debug-info RPMs or versions of the system libraries with debug information still in them (different Linux distributions take differing approaches to this).

An illuminator for main() is also provided that will perform the trace\_begin() operation for programs that aren't already using NightTrace (see "trace\_begin, Trace.begin" on page 2-7).

## **Detail Levels**

When activating an illuminator, a named detail level may be specified (the default one is called 2). A detail level may be customized to trace a particular subset of the functions that can be traced and to log more or less information as arguments to the events. By default, illuminators have detail levels called 1, 2, and 3, providing increasing amounts of detail recorded in the arguments of the events. Custom detail level names are not limited to numbers.

1. Relink the previous example to include the **glibc** illuminator:

```
$ gcc *.o -o a.outAI 'nlight --gcc main a.ai glibc'
```

- 2. Activate the **a.ai** illuminator specifying a higher level of detail than we used above, and **glibc** with a low level of detail:
  - \$ nlight --illuminate=a.outAI main a.ai=3 glibc=1
- 3. Start up a daemon to record the events, run the program, shut the daemon down, and run **ntrace**, which finds the trace file and illuminator support files from paths embedded in **a.outAI**:
  - \$ ntraceud tracefile
  - \$ a.outAI
  - \$ ntraceud -q tracefile
  - \$ ntrace a.outAI

## Here is some sample output of a few events with detail level 3:

```
9: cpu=?? ENTER_regcomp
                           test_illuminator main
                                                      0.010745903
   calling regcomp(preg=0x60f120,pattern=0x60f170,cflags=9)
      *preg={
         buffer=0x0,
         allocated=0,
         used=0,
         syntax=0,
         ...}
      *pattern="^main$"
      caller=0x478f44
      frame=0x7fbfff5870
10: cpu=?? RETURN_regcomp test_illuminator main
                                                        0.010800482
   returning from regcomp()=0
      errno=0
11: cpu=?? ENTER_strlen
                         test_illuminator main
                                                        0.010801628
   calling strlen(s=0x4bb374)
      *s=".*\.internal_io\.ada"
      caller=0x478f07
      frame=0x7fbfff5870
12: cpu=?? RETURN_strlen
                           test_illuminator main
                                                      0.010802240
   returning from strlen()=20
      errno=0
```

# Limitations

**nlight** automatically instruments the function entry and return of the following types of functions:

- Functions at the global scope in statically linked portions of a program
- Function entry points in shared libraries (those functions accessed from outside the shared library)

**nlight** does **not** illuminate the following types of functions:

- Functions within a shared library that are not called from outside the shared library
- Functions defined with the C/C++ keyword static
- Inlined functions
- Functions without compiler debug information (this can be overridden as explained below)

Functions that take a variable number of arguments (often called varargs functions) only have their entry point instrumented. There will be no trace point logged for their return due to a limitation in the Application Binary Interface (ABI). Note that a Night-Trace string table is generated automatically by **nlight** which identifies these functions. It is automatically included when analyzing the resultant data in **ntrace**. The name of the string table is vararg\_functions. See "Tables" on page 6-12 for more information about using string tables.

nlight uses debug information generated by compilers to automatically describe the arguments passed to functions in detail. When debug information is not available, this argument information is absent. However, function entry events can still generated if you explicitly tell nlight to pay attention to such functions. Use the --do\_nodebug option to nlight or override the default behavior in the graphical user interface. See "Commands for Manipulating an Illuminator" on page 4-68 and "Include Functions without Dwarf Debug Info" on page 4-81 for more information. Since there is no description available as to the number of arguments or their type, nlight treats these functions as vararg\_functions. No trace event will be associated with the return of such functions.

# The nlight Graphical User Interface

To invoke the **nlight** graphical user interface, invoke **nlight** without any options:

\$ nlight &

This will open the New Session window:




Figure 4-1. nlight Main WIndow

You may also specify a previously saved session or the path to an illuminator on the command line.

The first five radio buttons on the left side of the Wizard page correspond to the five steps outlined in the "Work Flow Illustration" on page 4-2. The Wizard guides you with step-by-step instructions on how to use the most common features of the tool.

There is also a Manager page that contains five similar nodes in a tree. Most actions within it are taken through context menus by right clicking on the various items in the tree.

The menu bar provides access to session configuration services, additional tools, and help. The menu bar provides the following menus:

• File

- View
- Tools
- Help

Each menu is described in the sections that follow:

## **File**

Accelerator: Alt+F

The File menu contains session-related items such as creating a new session, saving the current session or illuminator, and opening a previously-saved session or illuminator.




Figure 4-2. File Menu

The following paragraphs describe the options on the File menu in more detail.

## **New Session**

Mnemonic: N
Accelerator: Ctrl+N

Creates a new session.

If an existing session is open, it is first closed by this operation.

If changes have been made to the current session but have not yet been saved, **nlight** will ask you if you wish to save the current session before proceeding.

## **Open Session**

Mnemonic: O
Accelerator: Ctrl+O

Launches a standard file selection dialog which allows you to specify a previously-saved session file.

If changes have been made to the current session but have not yet been saved, **nlight** will ask you if you wish to save the current session before proceeding.

#### **Save Session**

Mnemonic: S
Accelerator: Ctrl+S

Saves the current session to a session configuration file quickly.

You are not prompted for the filenames where the session is to be saved. It is automatically saved to the same file it was opened from or previously saved to.

If the current session has not been saved to a file in the past, a Save Session As action will be done.

#### **Save Session As**

Mnemonic: A

Accelerator: Ctrl+A

Launches a standard file selection dialog which allows you to specify the filename where the session will be saved

## **Open Illuminator**

Launches a standard file selection dialog which allows you to specify an illuminator's **config.xml** file to edit.

If changes have been made to the current illuminator but have not yet been saved, nlight will ask you if you wish to save the current illuminator before proceeding.

The illuminator is opened in the Editor page (or window), but is not added to the session. To add an illuminator to the session, open the illuminator through the context menu on the Create, Customize, and Build branch of the Manager page (or window).

### **Save Illuminator**

Saves the current illuminator to a **config.xml** file quickly (see "Illuminator Files" on page 4-66).

You are not prompted for the filename where the illuminator is to be saved. It is automatically saved to its previously associated filename.

## **Save Illuminator As**

Launches a standard file selection dialog which allows you to specify the filename where the illuminator's **config.xml** will be saved (see "Illuminator Files" on page 4-66).

#### Exit

Mnemonic: X

Accelerator: Ctrl+Q

Closes the session and exits nlight completely.

If changes have been made to the current session or illuminator but have not yet been saved, **nlight** will ask you if you wish to save the session or illuminator before exiting.

## **Exit Immediately**

Mnemonic: I

Accelerator: Alt+Q

Closes the session and illuminator and exits **nlight** without prompting to save changes that have been made. Any changes will be lost.

## **View**

Accelerator: Alt+V

The View menu contains items for controlling the appearance of Console, Editor, and Wizard pages (or windows) of the graphical user interface. The Console page (or window) captures output from external commands that **nlight** invokes. The Editor page (or window) is used to customize an illuminator. The Wizard page (or window) provides a simplified guide through the work flow.




Figure 4-3. View Menu

## **Console in Page**

Accelerator: Alt+K

Toggles placing the Console window (the window to which output from invoked commands is logged) in a tabbed page within the main window.

## **Show Console**

Mnemonic: C
Accelerator: Ctrl+K

Toggles showing or hiding the Console window (or page).

#### **Clear Console**

Clears the contents of the Console window (or page).

## **Editor in Page**

Accelerator: Alt+E

Toggles placing the Editor window (the window in which an individual illuminator may be customized) in a tabbed page within the main window.

## **Show Editor**

Mnemonic: E

Accelerator: Ctrl+E

Toggles showing or hiding the Editor window (or page).

## **Search Editor**

Mnemonic: S

Accelerator: Ctrl+F

Toggles displaying the search bar in the Editor window (or page).

## **Search Editor Again**

Mnemonic: A

Accelerator: Ctrl+G

Repeats the search in the search bar in the Editor window (or page).

## Wizard in Page

Accelerator: Alt+W

Toggles placing the Wizard window (the window that provides a simpler guided interface through the workflow) in a tabbed page within the main window.

#### **Wizard Console**

Mnemonic: W

Accelerator: Ctrl+W

Toggles showing or hiding the Wizard window (or page).

#### **Verbose Wizard**

Accelerator: Alt+V

Toggles whether the Wizard window (or page) includes verbose instructions guiding you through the workflow.

The figure below shows the main window if the Console and Editor are shown in tabbed pages, the search bar is displayed on the Editor page, and the Wizard is hidden:




Figure 4-4. Console and Editor in Tabbed Pages with Search Bar Displayed

## **Tools**

Mnemonic: Alt+L



Figure 4-5. Tools Menu

The following describe the options on the Tools menu:

## **NightProbe Monitor**

Mnemonic: P

Opens the NightProbe Data Monitoring tool. NightProbe is a real-time graphical tool for monitoring, recording, and altering program data within one or more executing programs without significant intrusion. NightProbe can be used in a development environment as a tool for debugging or in a production environment for data capture or to create a "control panel" for program input and output.

#### NightSim Scheduler

Mnemonic: S

Opens the NightSim Application Scheduler. NightSim is a tool for scheduling and monitoring real-time applications which require predictable, repetitive process execution. With NightSim, application builders can control and dynamically adjust the periodic execution of multiple coordinated processes, their priorities, and their CPU assignments.

### NOTE

NightSim is not available on some systems. NightSim depends on the Frequency Based Scheduler. See "Kernel Dependencies" on page B-1 for more information.

## NightTune Tuner

Mnemonic: U

Opens the NightTune Tuner. NightTune is a graphical tool for analyzing the status of the system in terms of processes, interrupts, context switches, interrupt CPU affinity, processor shielding and hyper-threading control as well as network and disk

activity. NightTune can adjust the scheduling attributes of individual or groups of processes, including priority, policy, and CPU affinity.

For systems that support CPU shielding, NightTune provides a handy interface for controlling shielding, including downing sibling hyper-threaded CPUs to avoid interference.

## NightView Debugger

Mnemonic: V

Opens the NightView Source-Level Debugger. NightView is a graphical source-level debugging and monitoring tool specifically designed for real-time applications and multi-threaded applications. NightView can monitor, debug, and patch multiple real-time processes running on multiple processors with minimal intrusion.

# Help

Mnemonic: Alt+H




Figure 4-6. Help Menu

The following describe the options on the Help menu:

#### On Context

Mnemonic: C

Gives context-sensitive help on dialogs and various items within dialogs, pages, and windows.

Help for a particular item is obtained by first choosing this menu option, then clicking the mouse pointer on the object for which help is desired (the mouse pointer will become a floating question mark when the On Context menu item is selected). The cursor turns to a circle with a backslash when the item under the cursor has no help description associated with it.

In addition, context-sensitive help may be obtained for the currently highlighted option by pressing the F1 key. NightStar's online help system will open with the appropriate topic displayed.

## NightTrace User's Guide

Mnemonic: G

Opens the online version of the NightTrace User's Guide in the NightStar help viewer.

#### NightStar LX Tutorial

Mnemonic: T

Opens the online version of the NightStar LX Tutorial in the online help viewer.

## **License Report**

Mnemonic: L

Opens a license dialog which indicates the current license server and the number of licenses available on the system.

#### On Version

Mnemonic: V

Displays a short description of the current version of nlight.

## Check for Updates...

Mnemonic: U


Launches NUU (Network Update Utility) enabling you to update your system with the latest NightStar software. This requires network access to Concurrent's Updates web site. Updates require a login and user ID issued by Concurrent. Refer to <a href="http://redhawk.ccur.com/updates">http://redhawk.ccur.com/updates</a> for complete information.

Note that this option is not available on Ubuntu/Debian distributions, in which case **synaptic** should be used to check for NightStar updates.

## **Wizard**

The wizard guides you through the basic functionality of the **nlight** tool with more descriptive on-screen text than the session manager provides. It consists of a sequence of six pages that may be accessed in any order via the navigation panel on the left edge of each page, or sequentially via the Prev and Next buttons at the bottom of each page.

# **Navigation Panel**



## Figure 4-7. Wizard Navigation Panel

The four buttons at the top are for creating, opening, and saving sessions. These commands may also be accessed through the File menu (see "File" on page 4-7).

#### **New Session**

Creates a new session. If the current session has unsaved modifications, you will will be prompted to save it before the new session is created.

## **Open Session**

Opens a saved session. If the current session has unsaved modifications, you will be prompted to save it before the saved session is opened.

## **Save Session**

Saves the current session. If the session has never been saved to a file, you will be prompted for a filename to save it to.

#### **Save Session As**

Saves the current session to a new filename that you will be prompted for.

The next six buttons are radio buttons that select which of the six Wizard pages to display.

## **Select Programs**

Goes directly to the Select Programs with Debug Information page. In this dialog, you will tell **nlight** about the programs you wish to instrument with trace events. See "Select Programs with Debug Information" on page 4-20.

#### **Define Illuminators**

Goes directly to the Define an Illuminator for each Program page. On this page, you will optionally create an illuminator for the statically linked portion of each program. See "Define an Illuminator for each Program" on page 4-22.

#### **Select Illuminators**

Goes directly to the Select Predefined Illuminators for each Program page. On this page, you will select from the illuminators provided with NightTrace (main, glibc, pthread, and ccur\_rt) to link with each program. See "Select Predefined Illuminators for each Program" on page 4-26.

## **Relink Programs**

Goes directly to the Relink Illuminated Programs page. On this page, you will tell NightTrace how to relink your programs to include the user-defined and provided illuminators. See "Relink Illuminated Programs" on page 4-29.

#### **Activate Illuminators**

Goes directly to the Activate Illuminators in each Program page. On this page, you will select the illuminators to activate, the trace file name, and the amount of detail to record with each illuminator's events. See "Activate Illuminators in each Program" on page 4-32.

## **Run Scripts**

Goes directly to the Run Scripts to Launch Programs and NightTrace page. On this page, you will create scripts to run your programs and analyze the resulting events with NightTrace. See "Run Scripts to Launch Programs and NightTrace" on page 4-35.

# **Common Buttons**

These buttons are found at the bottom of each page.




Figure 4-8. Wizard Common Buttons

#### Advanced...

Opens the appropriate spot in the Manager to perform more advanced operations related to the current page. On the Define an Illuminator for each Program page, this button is actually a menu of advanced operations.

## Prev

Goes to the previous page in the workflow.

## Next

Goes to the next page in the workflow.

## Help

Gets help on the current page.

# **Select Programs with Debug Information**

Informs nlight about the programs that you wish to instrument with trace points.




Figure 4-9. Select Programs with Debug Information Page

## **Program**

Selects which program is the current program. Add or remove programs from this list with the Browse... and Delete buttons.

#### Browse...

Browses for another program to add to the list of programs using the standard file selection dialog. The program does not have to be built already (see Build Command, below).

#### **Delete**

Removes the current program from the list of programs. The program's executable file is not deleted.

## **Build Command**

Specifies a command that may be used to build the current program. If the program isn't already built, **nlight** will automatically invoke this command when it needs to access the program. To explicitly rebuild a program, build it at a shell prompt or use the Build or Build All buttons.

## **Build**

Builds the current program by invoking the Build Command.

#### **Build All**

Builds all programs listed in the Program list by invoking their Build Commands.

#### Advanced...

Brings the session manager to the top and expands the Select Code with Debug Information branch down to the current program (see "Select Code with Debug Information" on page 4-42). There, object files, archives, and shared objects may also be selected. Illuminators may be constructed for any of these. In most situations, creating illuminators for whole programs is what you will want to do.



Figure 4-10. Select Programs Advanced Settings

# **Define an Illuminator for each Program**

Optionally defines an illuminator for the functions in the statically linked portion of each program. The default is to create the illuminator. Clear the check box to delete the illuminator. Regular expressions may be used to control which functions the illuminator will trace




Figure 4-11. Define an Illuminator for each Program Page

#### **Program**

Selects the current program. To add or remove programs from this list, see "Select Programs with Debug Information" on page 4-20.

## Define an illuminator for this program

Creates an illuminator to hold the code to record trace events on function entry and return for functions defined in the statically linked portion of the current program. This item will be selected by default. Clearing the checkbox will delete the illumi-

nator. To temporarily disable the illuminator, see "Activate Illuminators in each Program" on page 4-32. The name of illuminator will be *currentProgramName.ai*.

## **Functions Included or Excluded from Being Traced**

Controls which functions are traced with a list of regular expressions that are applied in sequence from top to bottom. To restrict instrumentation to a small list of functions, first exclude all functions matching the POSIX regular expression ".\*", then include those functions you wish to trace. See "Add" on page 4-23 for documentation on the various regular expressions available. By default, all functions are included except those beginning with underscore, those in the C++ std namespace, main, and Ada's internal routines (see "Regular Expressions" on page 4-82).

#### Add

Adds a regular expression that will include or exclude functions from being traced. Select the expression from the menu of choices that pop up when this button is clicked.

# Include functions beginning with an underscore Exclude functions beginning with an underscore

Includes or excludes functions whose names start with an underscore character. All aliases of a function and the fully qualified C++ name (if applicable) must begin with an underscore in order to match these criteria. A fully qualified C++ name matches if the function name or the name of any containing classes start with an underscore.

The rationale for this is that functions and class names that begin with underscores are typically vendor implementation routines that are of less interest. But it is also common practice to create a strongly defined function that starts with an underscore, then weakly define aliases to that function that do not. These functions, like many in Glibc, are likely to be interesting, and so aren't matched by these expressions.

The default is to exclude functions beginning with an underscore.

# Include functions in the C++ std namespace Exclude functions in the C++ std namespace

Includes or excludes C++ functions in the std namespace.

The default is to exclude C++ functions in the std namespace. Such functions are often inlined: inlined instances cannot be traced.

# Include functions matching POSIX regex Exclude functions matching POSIX regex

Includes or excludes functions whose names match a POSIX regular expression (see **regex(7)**). A function name matches the regular expression if any alias or fully qualified C++ name (if applicable) matches it. The regular expression must match the whole name (an implicit ^ and \$ are placed before and after the regular expression respectively).

By default main and Ada's internal I/O routines are excluded.

You will be prompted for a POSIX regular expression to type in when this menu item is selected.

#### Edit...

Edits the POSIX regular expression of the currently selected regular expression.

#### **Delete**

Deletes the currently selected regular expression.

#### Up

Moves the currently selected regular expression up one place in the list.

#### **Down**

Moves the currently selected regular expression down one place in the list.

#### **Advanced**

Provides a menu of advanced actions to choose from.

#### Edit...

Opens the illuminator for the current program in the Editor window (or page) to perform advanced customization. See "Customizing an Illuminator with the Editor" on page 4-77

## Manage...

Brings the session manager to the top and expand the Create, Customize, and Build Illuminators branch. Additional custom illuminators may be created and customized here. The provided illuminators (main, glibc, pthread, and ccur\_rt) may also be customized (requires that the debuginfo packages for Glibc be installed). See "Create, Customize, and Build Illuminators" on page 4-45.




Figure 4-12. Define Illuminators Advanced Settings

## **Populate**

Populates the illuminator for the current program with the functions and variables found in the program. It is not necessary to populate an illuminator to customize, build, or use it. Populating an illuminator can be convenient for making lots of customizations to it. See "Populate" on page 4-47 and "nlight --populate" on page 4-71.

## Report

Creates a report about the functions being traced by the illuminator for the current program. The report is written to the Console window (or page). See "nlight --report" on page 4-72.

## **Build**

Builds the illuminator. If an illuminator's config.xml file or the program or object files it illuminates have changed, **nlight** will update the illuminator anytime it needs to access its files. So, it is normally not necessary for you to use this button. However, initiating the build manually is useful to verify that customizations done through the Editor window (or page) will build successfully.

# **Select Predefined Illuminators for each Program**

Selects predefined illuminators to link into the illuminated program (in addition to the user-defined illuminator created in the previous page). See "Predefined Illuminators" on page 4-64.




Figure 4-13. Select Predefined Illuminators for each Program Page

#### **Program**

Selects the current program. To add or remove programs from this list, see "Select Programs with Debug Information" on page 4-20.

#### main

Links the main illuminator into the current program, which does not record any events, but calls trace\_begin() before main() is called. This is necessary if the traced program does not do its own trace\_begin() call. Do not use the main illuminator in programs that already call trace\_begin() on their own. See "main" on page 4-64.

#### glibc

Links the glibc illuminator into the current program, which illuminators calls to the system C library. See "glibc" on page 4-64.

### pthread

Links the pthread illuminator into the current program, which illuminates calls to the system POSIX threads library. See "pthread" on page 4-65.

#### ccur\_rt

Links the ccur\_rt illuminator into the current program, which illuminates calls to the Concurrent real-time library. See "ccur\_rt" on page 4-65.

#### **NOTE**

This illuminator will only appear in the list if it is available.

#### cuda

Links the cuda illuminator into the current program, which illuminates calls to the CUDA libraries.

#### **NOTE**

This illuminator will only appear in the list if it is available.

#### Advanced...

Brings the session manager to the top and expands the Create, Customize, and Build Illuminators branch and the Relink Programs branch down to the Illuminators list of the current program. Additional illuminators may be created or linked with programs. See "Create, Customize, and Build Illuminators" on page 4-45 and "Relink Programs" on page 4-49.





Figure 4-14. Select Illuminators Advanced Settings

## **NOTE**

The list of predefined illuminators (those in italics) may differ on your system. On Concurrent RedHawk systems, additional illuminators may be available.

# **Relink Illuminated Programs**

Links a copy of each program to include the code from their illuminators to record the events.



#### **Program**

Selects the current program. To add or remove programs from this list, see "Select Programs with Debug Information" on page 4-20.

## **Illuminated Program Path**

Specifies the path name of the illuminated copy of the program. The original program is relinked with the illuminators specified for it in the previous two pages and is given a distinct name. By default, it is called *originalProgramPathAI*. See "Path" on page 4-50.

#### **Browse**

Browses the file system using the standard file selection dialog for the Illuminated Program Path.

#### **Relink Command**

Specifies the external command to relink the program. By default, it is a **make** command using the Illuminated Program Path as the target name. There are a number of substitution variables that may be specified in the command. These begin with the "%" character and are replaced by **nlight** when the command is invoked. See "Relink Command" on page 4-50

## **View Typical Makefile Target**

Displays a typical **Makefile** target assuming the default **make** command. You will need to modify your **Makefile** to include the Illuminated Program Path as a target.

#### View Substitution Variables

Displays a list and brief description of the available substitution variables for the Relink Command.

## %RELINK

Substituted with the Relink Path value. It is handy to use as a **make** target or as the operand of a **-o** option in **a.link**, **gcc**, or other compiler.

#### %AI

Substituted with the full paths of the illuminators to be linked in for use as a **make** file target's dependency list. The default **make** command passes **%AI** to **make** using the variable ILLUMINATORS.

## %GCC, %G77, %CF77, %ADA

Substituted with the options, files, and libraries that are need to link with the illuminators using the gcc, g77, cf77, or a.link commands (respectively). This includes the NightTrace library. The default make command passes %GCC to make using the variable ILLUMINATOR OPTIONS.

#### **Default Make**

Sets the Relink Command to the default make command.

#### Default a.link

Sets the Relink Command to the default a.link command (for Ada programs).

#### Relink

Relinks the current program by invoking the Relink Command. nlight will automatically relink your program (and apply the default activation set to it) whenever it is out-of-date and the relinked program is needed. The Relink button is useful to test changes to the Relink Command right away.

## Relink All

Relinks all programs listed in the Program list by invoking their Relink Commands.

#### Advanced...

Brings the session manager to the top and expands the Relink Programs branch down to the current program. There are no additional features here to access. See "Relink Programs" on page 4-49.




Figure 4-15. Relink Programs Advanced Settings

# **Activate Illuminators in each Program**

Activates illuminators so that they record events. Illuminators are "inert", having no run-time overhead and recording no events, when first linked into a program. They must first be activated. Check the box next to each illuminator you want activated. Only those illuminators that are actually linked into the program will appear on this page.




Figure 4-16. Activate Illuminators in each Program Page

main glibc pthread currentProgram.ai

Enables (if checked) or disables (if not checked) an illuminator. Only predefined or the user-defined illuminators that are actually linked into the illuminated program are listed. Additional custom illuminators added as an advanced feature in the session manager can only be enabled or disabled from the session manager. A notice will appear in the page if such illuminators exist.

Use Manager to activate and deactivate additional advanced illuminators.

## Figure 4-17. Notice That Additional Illuminators Are Linked In

## **Trace File**

Specifies the file that events will be recorded in. This is a parameter to the trace\_begin() call that the main illuminator does.

#### Browse...

Browses for the Trace File using the standard file selection dialog.

#### **Detail Level**

Specifies the level of detail that will be recorded as arguments to the events recorded by each illuminator. See "Detail Levels" on page 4-64 and "Detail Levels" on page 4-85.

## Advanced...

Brings the session manager to the top and expands the Activation Sets branch down through the default activation set. A different activation set may be designated as the default. The Wizard always manipulates the default activation set. If no default activation set has been designated, the Wizard will create one called Wizard. See "Activation Sets" on page 4-54.




Figure 4-18. Activation Sets Advanced Settings

# Run Scripts to Launch Programs and NightTrace

Runs scripts for collecting and analyzing trace data. NightTrace may collect data from programs in two ways. In File mode, your programs communicate with daemons to log events to a file on disk, then NightTrace is used to analyze those events. In Stream mode, your programs stream events directly to a running NightTrace. Simple scripts are automatically generated, and may then be customized, to run NightTrace and your programs in these two modes. See "Scripts" on page 4-60.




Figure 4-19. Run Scripts to Launch Programs and NightTrace Page in File Mode




Figure 4-20. Run Scripts to Launch Programs and NightTrace Page in Stream Mode

#### Mode

Selects between File mode and Stream mode. The page reconfigures itself to show the scripts appropriate to each mode.

In File mode, a single script (called Wizard in the session manager) is generated that will start daemons to record events in files, run your programs, stop the daemons, and run NightTrace on the trace files.

In Stream mode, two scripts (called Wizard Stream and Wizard Launch in the session manager) are generated. The first will run NightTrace in stream mode, and the second will run your programs.

### Script to Run Programs and NightTrace in File Mode

Launches (for File mode) user daemons for all your programs, runs your programs in sequence, halts the daemons, and runs NightTrace on the resulting trace files. nlight only knows the daemons to launch for programs that use the main illuminator to do the trace\_begin() call. For other programs, you will need to modify the script to launch them yourself.

If you add or remove programs, change the path to any of the relinked programs, or change the file events are recorded in, you can recreate the script by clicking on the Default button. Any edits you've done will be lost when you do this. In the session manager, this is the Wizard script.

## Script to Launch NightTrace in Stream Mode

Launches (for Stream mode) NightTrace in stream mode. You may then launch, start, and stop the daemons from within NightTrace. NightTrace will know the daemons needed only for programs linked with the main illuminator. For other programs, it will prompt for the daemon name. Events will stream directly into NightTrace when your programs are launched with the following script.

If you add or remove programs, change the path to any of the relinked programs, or change the file events are recorded in, you can recreate the script by clicking on the Default button. Any edits you've done will be lost when you do this. In the session manager, this is the Wizard Stream script.

## **Script to Launch Programs**

Launches (for Stream mode) your programs in sequence. If NightTrace has been launched and used to start the daemons, events from these programs will stream directly into NightTrace.

If you add or remove programs or change the path to any of the relinked programs, you can recreate the script by clicking on the Default button. Any edits you've done will be lost when you do this. In the session manager, this is the Wizard Launch script.

## Run

Runs the adjacent script using /bin/sh. The output from the script is written to the Console page (or window) by default. The scripts that launch your programs may optionally be run in other terminal sessions, such as an **xterm** by using the Terminal Session setting next to the script.

#### **Default**

Resets the adjacent script to a default value that is based on the current list of programs defined and options set for them. Any edits you've done will be lost when you do this.

#### **Terminal Session**

Selects from a menu of terminal sessions that the adjacent script may be run in.




Figure 4-21. Terminal Session Menu

#### Console

Captures all output from the adjacent script in the Console page (or window). This is inconvenient if the program needs to get input from the user.

## X Terminal Gnome Terminal KDE Terminal

Selects various kinds of virtual terminals to run the adjacent script in. These are convenient if the program needs to get input from the user or must run in a terminal emulator.

## Custom

Selects running the adjacent script using the Custom Terminal Session Command (which may only be modified through the Advanced... button). It defaults to being an X Terminal.

### Advanced...

Brings the session manager to the top and expands the Scripts branches for the current mode's scripts. See "Scripts" on page 4-60.




Figure 4-22. Run Scripts Advanced Settings

# **Session Manager**

The session manager guides you through the five-step work flow. Each branch of the tree structure represents one step. Hovering over each step will bring up a tool tip describing the step. Use context menus on each item of the tree to configure and execute each step. Click on the  $\blacksquare$  symbol to expand branches of the tree. Values in the Value column may be edited in place by clicking on them. Settings with Edit items in their context menus can usually be edited by double clicking on them.




Figure 4-23. Tool Tips in the Session Manager

# The Application Illumination Root Item

The root item in the Application Illumination tree displays a context menu when you right click on it.




Figure 4-24. Application Illumination Context Menu

## **Build All Objects, Illuminators, Programs**

Update steps 1-3 of the work flow. Also, if there is a default activation set (see "Make Default Activation Set" on page 4-58), that is applied to each relinked program.

### Kill Invoked Program

Kill any program that **nlight** has invoked to perform a task. This might be necessary if a user program or script (as in the illustration above) has entered an infinite loop. Note the busy indicator in the above illustration at the bottom of the window.

# **Select Code with Debug Information**

The first step in the **nlight** workflow is to select the code to have function entry and return events generated (that is, to be *illuminated*). **nlight** uses debug information to generate the illuminators and descriptions of the events that will be traced. These events can record values of parameters, global variables, return values, etc. The debug information is needed to know the names, types, and locations of these values.

### **Context Menus**

Right click on Select Code with Debug Information to inform nlight about objects and to build them.




Figure 4-25. Build Code with Debug Information Context Menu

New Object File New Archive New Shared Object New Program

Tells **nlight** about the various kinds of objects that you will be creating illuminators for.

#### **Build All**

Builds all the objects. Each object must have a Build Command configured for it for this to work, else you should build the objects outside of nlight control.

Associated with each object is a build command. The default command that is filled in is a simple **make** command. Shared objects may optionally have a separate object file containing the debug information, called a *debug info* file. Programs also automatically get an entry in the Relink Programs section (step 3 of the workflow, see "Relink Programs" on page 4-49).



Figure 4-26. Various Objects Added to the Session Manager

The context menu for each object may be used to create an illuminator for the functions in that object, build that object, rearrange that object, or remove that object from the session manager (removing does not delete the file).




Figure 4-27. Context Menu on an Object

### **Create Illuminator**

Creates an illuminator for the functions in this object.

### Add to Existing Illuminator

Causes an existing illuminator (selected in a page from those listed in the Create, Customize, and Build Illuminators section) to also illuminate the functions in this object.

#### Build

Builds this object using the Build Command.

## Move Up Move Down

Changes the order of objects in this branch.

### **Remove Object**

Removes all references to this object in **nlight**. It does not remove the actual file, nor does it remove references to the object in any illuminators.

To edit the build command, you may double click on the command itself and edit it in place, double click on Build Command and edit it in a dialog, or use the Edit Build Command item in Build Command's context menu.




Figure 4-28. Build Command Dialog

## **Building Object**

When **nlight** performs an action that requires accessing an object, such as building an illuminator for it, and that object has not been built yet, **nlight** will invoke its Build Command automatically.

However, since **nlight** knows nothing about the build dependencies of an object, it will not automatically rebuild an object if it is stale. You must do this manually. This may be done several ways:

- Build the object outside of nlight;
- Right click on the object in the Select Code with Debug Information section and select Build from the context menu that pops up;
- Right click on Select Code with Debug Information and select Build All from the context menu that pops up; or,
- Right click on Application Illumination (the root item in the tree) and select Build All Objects, Illuminators, and Programs from the context menu that pops up.

# Create, Customize, and Build Illuminators

The Create, Customize, and Build Illuminators section is pre-populated with the predefined illuminators:

- main, which sets up a trace\_begin() call.
- ccur\_rt, glibc and pthread, which trace functions in the corresponding system libraries.
- cuda (when available), which traces functions in the corresponding system library.

The predefined illuminators are displayed in an italic font unless they have been customized. A customized predefined illuminator is copied to the current working directory and is displayed using a plain roman font.

When building illuminators, **nlight** will automatically adjust illuminator event ranges so that they do not overlap with each other, unless you have explicitly specified a non-default range of event numbers. A default range of event numbers is one that ends in 29,999,999.

### **Context Menu**

The context menu on the root item of this section may be used to create, open, populate, or build illuminators.




Figure 4-29. Create, Customize, and Build Illuminators Context Menu

#### **New Illuminator**

Creates a new illuminator. A file dialog will prompt you for the illuminator's name. A directory of that name will be created with a **config.xml** file in it.

This illuminator must be customized and built before it can be used because the created **config.xml** file will not specify any object file to search for functions to illuminate.

### **New Illuminator from Object**

Creates a new illuminator. A dialog will prompt for an object containing the functions to be illuminated. Then a file dialog will prompt for the illuminator's name. A directory of that name will be created with a **config.xml** file in it.

An easier way to achieve the same result is to right click on the object in the Select Code with Debug Information section and select Create Illuminator from the context menu that pops up.



Figure 4-30. New Illuminator from Object Dialog

#### **Open Existing Illuminator**

Opens an illuminator created in another session, or with a command line option, or by manually creating a directory containing a **config.xml** file.

### **Populate All Illuminators**

Populates all non-predefined illuminators with functions and variables found in their objects. It is not necessary to populate an illuminator to customize, build, or use it. Populating an illuminator can be convenient for making customizations to it.

## **Build All Illuminators**

Builds all non-predefined illuminators. An illuminator must be built before using it. It is not necessary to explicitly build illuminators. They will be updated if necessary when they are used. This context menu item is useful mainly for convenience when debugging customizations (it is possible for a customization to result in an error at build time).

## **Context Menu on Individual Illuminators**

The context menu on an individual illuminator may be used to populate, edit (that is, customize), build, rearrange, or delete the illuminator.




Figure 4-31. Context Menu on an Individual Illuminator

## **Add Object**

Brings up a standard file browsing dialog which allows you to add additional object files to the illuminator.

### **Populate**

Populates a non-predefined illuminator with functions and variables found in its objects. It is not necessary to populate an illuminator to customize, build, or use it. Populating an illuminator can be convenient for making customizations to it.

### Report

Creates a report about all variables and functions found, and what groups the functions are in, on the Console window (or page).

#### Edit

Customizes an illuminator by editing its **config.xml** file in the **Editor** window (or page). If the illuminator is a predefined illuminator, a copy of it is made in the current working directory and it is this copy that is customized. The italic font used for predefined illuminators is changed to a plain roman font.

#### **Build**

Builds a non-predefined illuminator. An illuminator must be built before using it. It is not necessary to explicitly build illuminators. They will be updated if necessary when they are used. This context menu item is useful mainly for convenience when debugging customizations (it is possible for a customization to result in an error at build time).

### Move Up, Move Down

Rearranges the order of the illuminators in this section.

#### **Delete Illuminator**

### For customized predefined illuminators

Deletes the customized illuminator from the current working directory. All references to this illuminator revert to the pre-defined illuminator and the font used to display the name of this illuminator is changed back to italic.

### For predefined illuminators

Deletes all references to the pre-defined illuminator. The predefined illuminator will remain in the list.

#### For non-predefined illuminators

Deletes the illuminator from the disk and removes all references to it from the session manager, including from this section.

## **Relink Programs**

The third step in the workflow is to relink the programs, this time including the illuminators that have been built. The Relink Programs section is populated automatically with the programs that are in the Select Code with Debug Information section (see "Select Code with Debug Information" on page 4-42).

### **Context Menus**

The context menus for Relink Programs and for individual programs under that are fairly simple. You can relink all the programs or relink individual ones. Programs are relinked if they are stale when they are needed, so it should rarely be necessary to explicitly relink them unless you are using the relinked programs outside of the control of the nlight GUI. All programs may also be relinked by choosing the Build All Object, Illuminators, Programs item in the context menu on the root Application Illumination item. If there is a default activation set, it will be applied when the program is relinked (see "Activation Sets" on page 4-54).




Figure 4-32. Relink Programs Context Menu

#### Relink All

Relinks all the programs and applies the default activation set (if there is one).




Figure 4-33. Individual Relinked Program Context Menu

#### Relink

Relinks this single program and applies the default activation set.

### **Path**

The Path setting under individual programs is the file name of the relinked copy of the program. By default, it is the path of the original program (without illuminators linked in) with the capital letters "AI" appended.

The Path setting may be edited by double clicking on it or by right clicking on it and choosing the Edit Relink Path context menu item. A file selection dialog will display allowing you to select a new file path.

#### **Relink Command**

The Relink Command is the external command that will be used to relink the program. By default it is a **make** command. There are a number of *substitution variables* that may be specified in the command. These begin with the "%" character and are replaced by **nlight** when the command is invoked (see below for details).

There are a number of ways the Relink Command can be edited:

• Double click on the value of the Relink Command: this allows the command to be edited in place;



Figure 4-34. Editing Relink Command In Place

• Double click on the Relink Command label: this pops up a line editing dialog;




Figure 4-35. Edit Relink Command Dialog

• Right click on the Relink Command and select Edit Relink Command from the context menu: this also pops up a line editing dialog;



Figure 4-36. Relink Command Context Menu

Right click on the tree item and select Set to Default make Command: this sets it to:

or.

Right click on the tree item and select Set to Default a.link Command: this sets it to:

```
a.link -o %RELINK %ADA program
```

There are a number of substitution variables that may be specified in the Relink Command:

#### %RELINK

This is substituted with the Relink Path value. It is handy to use as a **make** target or as the operand of a **-o** option in **a.link**, **gcc**, or other compiler.

#### %AI

This is substituted with the full paths of illuminators to be linked in. This is convenient for adding to a **make** file target's dependency list. The default **make** command passes this to **make** using the variable ILLUMINATORS.

### %GCC, %G77, %CF77, %ADA

This is substituted with the options, files, and libraries that are needed to link with the illuminators using the gcc, g77, cf77, or a.link commands (respectively). This includes the NightTrace library. The default make command passes %GCC to make using the variable ILLUMINATOR\_OPTIONS.

### Illuminators

The Illuminators branch allows you to select which illuminators are linked into the program:




Figure 4-37. Illuminators Context Menu

By default the predefined main illuminator and any illuminator you create for the program are linked into it. You may select others:



Figure 4-38. Select Illuminators Dialog

#### **NOTE**

The list of illuminators shown in the dialog may differ on your system. Concurrent RedHawk systems have additional predefined illuminators now shown in the dialog above.

Remove illuminators from the list of illuminators linked in by unchecking them in the Select Illuminators Dialog, or by using the context menu to remove them:




Figure 4-39. Relinked Illuminator Context Menu

## **Activation Sets**

When illuminators are first linked with a program, they are inert. The fourth step in the work flow is to activate one or more of them. An *activation set* is a named set of activations that may be applied to your programs. During the course of analyzing a performance problem, you will typically turn on and off various illuminators, and adjust their options and detail levels. This can be done with one or more activation sets.

To create an activation set, right click on Activation Sets and select New Activation Set from the context menu that pops up:



Figure 4-40. Creating New Activation Set

You will be prompted to provide a name for the new activation set. By default every program will be included in the set and every illuminator in the program will be activated. The below figure illustrates the default values given to settings on each illuminator:





Figure 4-41. Default Options on Illuminators

To see a list of the current activations and options set for them, right click on Activation Sets and select Query Current Activations. You will get a dialog box showing the current activations:



### Figure 4-42. Query Current Activations Results

The "!" preceding an illuminator name indicates it is not activated. Periods in illuminator names are transformed to an underscore since internally these are parts of C symbol names.

# Settings For "main" Illuminator

The main illuminator is special. It does not generate any trace events, but it does do a trace\_begin() call before main() begins executing. The settings allow you to specify parameters to pass to that trace\_begin().

### **Activated**

Controls whether the illuminator will be activated (yes) or deactivated (no). It defaults to yes.

### TRACE\_FILE

Sets the path to the file that the NightTrace events will be recorded in. It defaults to "trace\_file" in the current working directory.

#### **NUM BUFFERS**

Sets the number of buffers that the NightTrace library will use for recording events. It defaults to 16 buffers.

#### **BUFFER\_LENGTH**

Sets the number of bytes in each buffer that the NightTrace library will use for recording events. It defaults to 65536 bytes.

## **Settings For Ordinary Illuminators**

All other illuminators record events. By default, there are three detail levels for each illuminator, named 1, 2, and 3. Each record more detail than the next lower numbered one. Customized illuminators may have additional detail levels, whose names are not limited to numbers, but may be anything.

#### **Activated**

Controls whether the illuminator will be activated (yes) or deactivated (no). It defaults to yes.

### **Detail Level**

Sets the name of the detail level that the activated illuminator will use to record events. It defaults to 2.

### **Context Menu for an Illuminator**

Right clicking on an illuminator in the Activation Sets section brings up a context menu:




Figure 4-43. Context Menu on an Illuminator in an Activation Set

### **Apply Activation**

Activates (or deactivates) a single illuminator in a single program. The other illuminators and other programs are not effected.

#### Remove Illuminator

Removes an illuminator from the activation set. Once removed from the activation set, that activation set will neither activate nor deactivate that illuminator. The illuminator remains linked with the program in whatever activation state it already has. For example, you can set up a collection of activation sets that control the activation of the glibc illuminator and another collection of activation sets that control all illuminators but glibc.

## **Context Menu for a Program**

Right clicking on a program in the Activation Sets section brings up a context menu:




Figure 4-44. Context Menu on a Program in an Activation Set

### **Apply Activations**

Applies the activations to just this program's illuminators, but does not modify any other program.

#### **Select Illuminators**

Brings up a dialog that allows selecting which illuminators that are linked in to this program are to be activated (or deactivated). Deselected illuminators will remain linked with the program in whatever activation state they are already in.

#### Move Up, Move Down

Rearranges the order of the programs. This is purely cosmetic.

### **Remove Program**

Removes the program from this activation set. No changes to the activations of the program will be made by this activation set.

#### Context Menu for an Activation Set

Right clicking an activation set name in the Activation Sets section brings up a context menu:




Figure 4-45. Context Menu on an Activation Set

### **Apply Activation Set**

Applies all the activations (or deactivations) of all the illuminators in all the programs that are in this activation set.

### **Select Programs**

Brings up a dialog that allows you to choose which programs are in this activation set. By default, all programs are selected.

#### **Copy Activation Set**

Brings up a dialog asking for the name of a new activation set, and creates a copy of this activation set with that name.

#### **Make Default Activation Set**

Designates a single activation set as the default activation set. It immediately applies it. Then, whenever a program gets relinked, this activation set is immediately applied to it.

Whenever a change is made to a setting in the default activation set, that change is immediately applied to that illuminator in that program. This means if you apply a different activation set, then modify the default activation set, the current activations will be a mixture of the two activation sets.

The Wizard window (or page) will modify the default activation set. If there isn't one, it will create one called Wizard.

The default activation set is displayed in a bold font.



Figure 4-46. Default Activation Set in Bold

### **Forget Default Activation Set**

Removes the default activation set designation. It does not change the current activations, but whenever a program is relinked in the future, it will default to having no illuminators activated.

Create Default Script (NightTrace in File Mode), Create Default Script (NightTrace in Stream Mode), Create Default Script (Launch Programs)

Creates scripts based on the programs and settings in an activation set. See "New Script from Activation Set (NightTrace in File Mode)" on page 4-61 and "New Script from Activation Set (NightTrace in Stream Mode), New Script from Activation Set (Launch Programs)" on page 4-62 for details on these actions.

### Move Up, Move Down

Changes the order of the activation sets. This is purely cosmetic.

### **Rename Activation Set**

Prompts you for a new name for an activation set.

#### **Remove Activation Set**

Deletes an activation set from the session. No changes are made to the current activations.

# **Scripts**

The fifth and final step in the workflow is to run your instrumented programs and Night-Trace. The Scripts section of nlight allows you to set up scripts for automating this process. Right click on Scripts to get a context menu for creating a script:




Figure 4-47. Scripts Context Menu

## **New Script**

Selecting New Script prompts for a name for the script. The script has some settings for controlling how it is invoked. When nlight invokes a script, it places it in a file called .nlight\_script\_n in the current working directory. By default, output from the script is directed to the Console window (or page). If it is necessary to interact with the script, you can run it under an X Terminal, Gnome Terminal, KDE Terminal, or invoke it by a custom method.




Figure 4-48. Run Script in Terminal Session

When Custom is selected, the script is invoked by the Custom Terminal Session Command. By default, this is an **xterm** command for illustration purposes. The Custom Terminal Session Command can be used to invoke the script any arbitrary way or to pass an option to the script:



Figure 4-49. Invoking a Script on the Console While Passing an Option

Double click on Script or select Edit Script from its context menu to bring up an editor dialog for editing the script.

## New Script from Activation Set (NightTrace in File Mode)

As a convenience, <code>nlight</code> can use the information in an activation set to create a first draft of a script. <code>nlight</code> prompts you for an activation set and then scans the "main" illuminators for trace files and creates commands to start a user daemon for each one, run each of the programs in succession, stop the daemons, and invoke NightTrace. As a shortcut, you can also right click on an activation set and select <code>Create Default Script</code> (NightTrace in File Mode) from the context menu (see "Create Default Script (NightTrace in File Mode), Create Default Script (NightTrace in Stream Mode), Create Default Script (Launch Programs)" on page 4-59). You can then edit the script to add options to the commands, control the order your programs are run, etc:

```
# Start NightTrace user daemons
ntraceud --numbufs=16 --buflen=65536 trace_file

# Run programs
./myappAI

# Halt NightTrace user daemons
ntraceud -q trace_file

# Invoke NightTrace
ntrace myappAI &

# Wait a few seconds for messages from ntrace to go to console
sleep 3
```

Figure 4-50. Default Script created for an Activation Set (NightTrace in File Mode)

## New Script from Activation Set (NightTrace in Stream Mode), New Script from Activation Set (Launch Programs)

If you want to use NightTrace in its streaming mode, you can create a pair of scripts: one to launch NightTrace with the appropriate daemons, and one to launch your instrumented programs. The New Script from Activation Set (NightTrace in Stream Mode) and New Script from Activation Set (Launch Programs) will prompt you for an activation set and create a first draft of the scripts for doing this. As a short cut, you can also right click on an activation set and select the corresponding Create Default Script context menu item (see "Create Default Script (NightTrace in File Mode), Create Default Script (NightTrace in Stream Mode), Create Default Script (Launch Programs)" on page 4-59).




Figure 4-51. Activation Set for an Elaborate Script Example

# Console

The Console window (or page) captures output from external commands and scripts. For each command invoked, the console includes a heading with a time stamp, a description of the action, and the command being invoked. Command output follows and then finally the status returned by the command. Scripts can have their output directed to a different terminal session.

The status is green if zero, and red if non-zero. You will also get a warning dialog for any non-zero status that is returned. Scripts might not return an error status but still have error messages.



Figure 4-52. Non-zero Status Warning

```
2008-Jan-18 Fri 16:08:55 EST

Compiling "a.out"

Running: gec -o a.out var.c

Status=0

2008-Jan-18 Fri 16:08:55 EST

Compiling "b.out"

Running: make b.out

make: ***

No rule to make target `b.out'

. Stop.

Status=2
```

Figure 4-53. Console Output

# **Predefined Illuminators**

## **Detail Levels**

Except for main, all predefined illuminators have the three default detail levels: 1, 2, and 3. The table below details what information is recorded on the events that **nlight** generates for function entry and return events.

Table 4-1. Values Recorded As Arguments to Illumination Events

	1	2	3
return address (entry events)	X	X	X
frame pointer (entry events)		X	X
byte limit on aggregate size (all events)	16	16	16
parameters (entry events)		X	X
indirect through pointer parameters (entry events)			X
return values (return events)	X	X	X
indirect through pointer return values (return events)			X
errno (return events)			X

## main

The main illuminator is special. It does not record any events. Linking with and activating it causes trace\_begin() to be called before main() is called. This is necessary if the traced program does not do its own trace\_begin() call.

If a program does its own trace\_begin() call, do not use this illuminator. In this situation, nlight and NightTrace will not know automatically what user trace daemon is needed by the instrumented program, so generated scripts will have to be edited to include the appropriate daemon and trace file.

# glibc

The glibc illuminator illuminates functions from the system C library. The thousands of functions are partitioned into dozens of named groups for convenience when customizing the glibc illuminator (see "Groups" on page 4-90). Use the Editor window (or page) by editing the illuminator, select the Report menu item from the context menu from the Create, Customize, and Build Illuminators section of the session manger, or use the following command to see a list of all groups and their functions:

#### nlight --report=glibc

# pthread

The pthread illuminator illuminates functions from the system pthread library. The functions are partitioned into two named groups for convenience when customizing the pthread illuminator:

- glibc functions that are redundant with functions in the C library; and
- pthread the functions implementing threads.

## ccur\_rt

The ccur\_rt illuminator illuminates functions from the ccur\_rt library. This illuminator will be present only on systems with the ccur\_rt library installed. The numerous functions are partitioned into several named groups for convenience when customizing the ccur\_rt illuminator. Use the Editor window (or page), use the Report context menu item, or use the following command to see a list of all groups and their functions:

nlight --report=ccur\_rt

### cuda

The cuda illuminator illuminates functions from the CUDA libraries. NVIDIA provides a CUDA API which allows an NVIDIA GPU to execute user-specified code. This illuminator will be present only on systems with the cuda driver installed. The numerous functions are partitioned into several named groups for convenience when customizing the cuda illuminator. Use the Editor window (or page), use the Report context menu item, or use the following command to see a list of all groups and their functions:

nlight --report=cuda

# **Illuminator Files**

The following files are created in the *illuminator* directory:

config.xml

The file that holds all the settings and customizations for an illuminator. An illuminator that has not yet been built will contain only this file.

next event.txt

The next event number after the last one assigned. Its purpose is to assist in creating multiple wrapper libraries that use contiguous ranges of events.

#### NOTE

When building multiple illuminators using the graphical interface of nlight, nlight will automatically adjust event ranges so that they do not overlap (assuming the illuminators otherwise have default event range specifications).

illuminator.h

Header file that #defines a name for each event for use in calling the NightTrace analysis API. The names are of the form:

```
TRACE_EVENT_illuminator_ENTER_function and TRACE_EVENT_illuminator_RETURN_function.
```

When a function has been aliased to have multiple names (usually a strongly and a weakly defined name), only a single event pair is allocated for it. The function name used to build the event name is the shortest alias (then lexically earliest if there are two or more shortest aliases). Each alias will get its own wrapper function, but they will each record the same entry and return event IDs.

illuminator.map

NightTrace event map naming the events. The names are of the form:

ENTER\_function and RETURN\_function.

### $illuminator\_level.fmt$

NightTrace format table called illumination. There is one for each detail level so NightTrace knows what details were recorded in the trace file.

### $illuminator\_level.o$

Object file that gets copied into the user program by **nlight --illuminate** to control the level of detail recorded by each function in the wrapper library.

### illuminator\_level.list

The list of functions to wrap or not wrap for each detail level. It is used by the **nlight** --illuminate command.

#### illuminator.o

Relocatable object file containing all the "wrapper" functions.

#### illuminator.vararg

NightTrace table called vararg\_functions indexed by entry event number. The indexed entry will be "true" if the corresponding function is a "vararg" function (and thus doesn't generate a return event) or "false" otherwise.

# nlight Command Line Mode

Illuminators can be created, manipulated, used, activated, and deactivated by using **nlight** in command-line mode rather that running the tool in GUI mode.

# **Commands for Manipulating an Illuminator**

## nlight --create

Usage:

```
$ nlight --create=illuminator [options] [object files]
```

Creates a directory called *illuminator* (with periods changed to underscores) and places in it a **config.xml** file that reflects the options and object files specified on the remainder of the command line. If *illuminator* already exists, it will be modified to include the additional *options* and *object files* that are specified.

The following options may be specified:

```
--aggregate_limit=limit
--config=config.xml
--do_nodebug
--dont_nodebug
--event_ids=N-[M]
--install=path
--iunderscores
--iregex=regex
--istd
--xunderscores
--xregex=regex
--xstd
```

The *object files* that may be specified are those containing the functions to be illuminated. They may be a whole program, archives, shared objects, individual object files, or debug-info files. If the DWARF debug information has been placed in a separate debug-info file, it must be listed immediately after its corresponding object file.

```
--aggregate_limit=limit
```

Limits the recording of aggregate values to *limit* bytes. Aggregates might get recorded with an event if a function's parameter or return value is a C/C++ struct type, for example. Only the first *limit* bytes of the aggregate are recorded.

This option may also be set in a *config.xml* file:

```
<defaults><options aggregate_limit=limit/></defaults>
(See "aggregate_limit=limit" on page 4-105).
```

The limit must be at least 16 bytes. The default limit is 16 bytes.

#### --config=config.xml

Reads configuration from an XML file. More than one instance of this option may be specified to merge several such files together. Options specified on the command line after the **--config** option will override options set in the *config.xml* file. One use of this might be to generate a customized glibc illuminator.

This would initialize myglibc/config.xml with /usr/lib/Night-Trace/illuminators/glibc/config.xml, but change the aggregate limit from 16 to 64.

#### --do\_nodebug, --dont\_nodebug

Creates or blocks creation of trace events for functions that have no DWARF debug information. The default is to not create such trace events. Only entry events are generated for functions without debug information. An alternative to **--do\_nodebug** is to use a *config.xml* file to provide a signature for the function (See "declare" on page 4-101).

This option may also be set in a *config.xml* file:

```
<defaults><options nodebug={yes/no}></defaults>
(See "nodebug={yes|no}" on page 4-107).
```

#### --event ids=N-[M]

Specifies the range of NightTrace event IDs to use for the function entry and return events. If the range is exceeded, a warning is generated.

This option may also be set in a *config.xml* file:

```
<defaults><options event_ids=N-[M]></defaults>
(See "event_ids="N-[M]"" on page 4-107).
```

The defaults for *N* and *M* are 10,000,000 and 29,999,999 respectively. The highest possible event ID is 29,999,999.

If the upper bound is 29,999,999 and the illuminator is built through the graphical interface, **nlight** will change the lower bound to be a value in the range 10,000,000 through 29,999,999 so that the illuminator's event range will not overlap other illuminators in the session that also have their upper bound set to 29,999,999.

#### --install=path

Specifies an installed location for an illuminator, in contrast to the location where it is actually built. This path is recorded in the object files for **ntrace** to find the

event map and format tables (see "Using NightTrace with Illuminators" on page 4-75).

Includes or excludes functions from getting entry and return events based on the functions' names. Multiple instances of these options may be specified. The last one specified that matches a function's name determines whether that function is included or excluded. Excluded functions are not included in the **--populate** output.

#### --iunderscores, --xunderscores

Includes or excludes functions whose names start with an underscore character. All aliases of a function and the fully qualified C++ name (if applicable) must begin with an underscore in order to match these options (in contrast to **--iregex=\_.\*** or **--xregex=\_.\***). A fully qualified C++ name matches if the function name or name of any containing classes start with an underscore.

The rationale for this is that functions and class names that begin with underscores are typically vendor implementation routines that are of less interest. But it is also common practice to create a strongly defined function that starts with an underscore, then weakly define aliases to that function that do not. These functions, like many in Glibc (see NOTE), are likely to be interesting, and so aren't matched by these options.

#### **NOTE**

Many functions in Glibc for which all aliases begin with an underscore do not follow standard function call conventions, and so should never be traced via Application Illumination.

These options may also be specified in a *config.xml* file:

<defaults><options underscores={yes|no}/></defaults>

(See "underscores={yes|no}" on page 4-107).

The default is --xunderscores.

### --iregex=regex, --xregex=regex

Includes or excludes functions whose names match a POSIX regular expression (see regex(7)). A function name matches the regular expression if any alias or fully qualified C++ name (if applicable) matches it. The regular expression must match the whole name (an implicit ^ and \$ is placed before and after the regular expression respectively).

These options may also be specified in a *config.xml* file:

are excluded.

To include only functions matching a particular *regex*, first exclude all functions:

```
--xregex=.* --iregex=regex
```

```
--istd, --xstd
```

Includes or excludes C++ functions in the std namespace.

These options may also be specified in a *config.xml* file:

```
<defaults><option std={yes/no}/></defaults>
(See "std={yes|no}" on page 4-108).
```

The default is to exclude C++ functions in the std namespace. Such functions are often inlined and so tracing them usually doesn't provide a lot of useful information.

## nlight --populate

Usage:

```
$ nlight --populate=illuminator [options] [object files]
```

Creates or updates (like --create) the *illuminator*'s config.xml file to add the *options* and *object files* specified, then populates the config.xml file with a list of all the functions found on the *object files* that it will generate trace points for and all the global variables it can record as arguments to return events. This can be a great convenience when you want to create a number of function-specific customizations by editing the config.xml file. If such customizations are made, they will be retained if you run the nlight --populate command again, which you will likely want to do anytime you add or remove functions or change the function's signatures that you are illuminating.

## nlight --build

Usage:

```
$ nlight --build=illuminator [options] [object files]
```

Creates or updates (like --create) the *illuminator*'s config.xml file to reflect the *options* and *object files* specified, then builds the "wrapper" functions, event map, format tables, etc. You will want to do this any time you change the types or function signatures that Application Illumination uses to create trace points.

By default, three detail levels are created for the illuminator: 1, 2, and 3. You may edit the **config.xml** file to modify these detail levels or to create custom detail levels.

## nlight --report

Usage:

```
$ nlight --report=illuminator
```

Generates a report about an *illuminator* on functions, function groups, global variables, etc. For example:

```
$ nlight --report=pthread
The following global variables were found:
The following subroutines had no debug information or
<declare>:
   pread64
   pwrite64
   lseek64
  pread
  pread64
  pwrite
  pwrite64
The following subroutines were excluded because of their
names:
   __errno_location
   __h_errno_location
   __libc_allocate_rtsig
   _pthread_cleanup_pop
  _pthread_cleanup_pop_restore
  _pthread_cleanup_push
   pthread cleanup push defer
The following subroutines are in group "glibc":
  _IO_flockfile
   _IO_ftrylockfile
   _IO_funlockfile
  wait
  waitpid
   write
The following subroutines are in group "pthread":
```

```
__pthread_atfork
   __pthread_getspecific
  pthread testcancel
  pthread timedjoin np
  pthread_tryjoin_np
  pthread yield
  sem_close
  sem destroy
  sem getvalue
  sem init
  sem_open
  sem_post
  sem_timedwait
  sem_trywait
  sem unlink
  sem wait
The following subroutines are in no group:
```

# **Commands for Linking with Illuminators**

Once built, an illuminator's "wrapper" functions must be linked into your program with the **-Wl,--emit-relocs** and either **-lntrace** or **-lntrace\_thr** options. The **nlight** program with the below options can be used between back-quotes to conveniently generate all the options to reference the needed object files and options. When an illuminator is specified with a relative path, the program will search for it first relative to the current directory, and then relative to **/usr/lib/NightTrace/illuminators**. Alternatively, an absolute path to the illuminator directory may be given.

When an illuminator is first linked into your program, it is inert. It does not intercept any function calls or interfere with your program's performance at all until it is activated with the **nlight** --illuminate command (see "Command for Activating and Deactivating Illuminators" on page 4-74).

# nlight --gcc

Usage:

```
$ gcc ... 'nlight --gcc [-t] illuminator_list'
```

Generates options suitable for **gcc** to link in a list (separated by whitespace) of illuminators. The **-t** option specifies the use of the threaded **ntrace** library.

This generates the following options:

- illuminator\_path/illuminator.o (for each illuminator)
- -Wl,--emit-relocs
- -lntrace/ thr/

## nlight -- g77

Generates options suitable for **g77**. See "nlight --gcc" on page 4-73.

## nlight --cf77

Generates options suitable for **cf77**. See "nlight --gcc" on page 4-73.

## nlight --ada

Generates options suitable for **a.link**. See "nlight --gcc" on page 4-73.

This generates the following options:

- -ld illuminator\_path/illuminator.o (for each illuminator)
- --emit-relocs
- -so=ntrace/ thr/

# **Command for Activating and Deactivating Illuminators**

Once the illuminators are linked into a program, they can be activated by using the **nlight** --illuminate command. This command scans the user program for calls to the functions to be traced, and redirects them to the "wrapper" functions in the illuminator that record the entry event, call the real function, record the return event, and return.

Usage:

program

Specifies the program you linked with illuminators. **nlight** --illuminate may be run on the program multiple times to turn on and off various illuminators and to change their detail levels.

!

Deactivates the illuminator the "!" is prefixed to. When deactivated, an illuminator has no run-time overhead.

```
main[,options]
```

Specifies the main illuminator and its options. This illuminator is special. It "wraps" only the main() routine, and records no events. Instead, it performs a trace\_begin() call (see "trace\_begin, Trace.begin" on page 2-7). Rather than

specifying a detail level, you may specify a comma-separated list of options to the trace\_begin() call:

#### • TRACE\_FILE=filename

Specifies the name of the file that will hold the trace events. The default is **trace\_file**.

#### • NUM\_BUFFERS=count

Specifies the number of buffers used for recording trace events. The default is 8.

#### BUFFER\_LENGTH=size

Specifies the length in bytes of each buffer used for recording trace events. The default is 32768.

#### illuminator

Specifies the name of the illuminator. This can be an absolute or relative path to the directory containing the illuminator's files. Relative paths will be searched for relative to the current directory and then relative to /usr/lib/NightTrace/illuminators. The following illuminators are provided in /usr/lib/NightTrace/illuminators:

- main
- glibc
- pthread
- ccur\_rt

The following illuminators are provided in the directory /usr/lib/Night-Trace/illuminators2 on systems where CUDA is available:

• cuda

level

Specify the level of detail to be recorded by the illuminator's events. The default is 2. By default, illuminators have detail levels 1, 2, and 3. These levels may be customized, or custom details may be created, for any illuminator.

# **Using NightTrace with Illuminators**

Illuminators have a NightTrace event map and, for each detail level, a NightTrace format table, within them. The absolute path to these files are embedded in programs that have the illuminator linked in. If the main illuminator is used, the (possibly relative) path to the trace file is also embedded in the program. You may specify a program on the ntrace command line, and NightTrace will extract these embedded paths and use them.

Usage:

## \$ ntrace a.outAI

Note that because the path to the trace file may be a relative path, the **ntrace** command should be run with the current working directory being the same as when *a.outAI* was run.

# **Customizing an Illuminator with the Editor**

The Editor is invoked by selecting the Edit context menu item on an illuminator in the Illuminators section of the session manager window (or page), by double clicking on that same illuminator, or by specifying an illuminator on the **nlight** command line. The editor can be in its own window or in a page in the session manager, depending on the Show Editor in Page setting in the View menu.

The Editor presents the configuration of an illuminator in a tree structure much like the session manager.




Figure 4-54. Editor Page

#### **Buttons**

The row of buttons above the settings tree allow loading and saving of the **config.xml** files that define the customizations of an illuminator and toggle the search bar.

#### Open...

Launches a standard file selection dialog which allows you to specify an illuminator's **config.xml** file to edit.

If changes have been made to the current illuminator but have not yet been saved, **nlight** will ask you if you wish to save the current illuminator before proceeding.

#### Save

Saves the current illuminator to a **config.xml** file quickly.

You are not prompted for the filename where the illuminator is to be saved. It is automatically saved to the same file it was opened from or previous saved to.

#### Save As...

Launches a standard file selection dialog which allows you to specify the filename where the illuminator's **config.xml** file will be saved.

#### Search

Toggles displaying the search bar at the bottom of the Editor window (or page).

## **Search Editor**

The Search Editor menu item in the View menu or the Search button turns on the search bar in the Editor window (or page). All of the items in the editor's trees also include Search in their context menus.





Figure 4-55. The Search Bar



Specifies the text or regular expression to search for. If a Search context menu is used, it is initialized with a regular expression that will match the value of the item that was right clicked on exactly.



Searches for the next or previous instance of the search string or regular expression.



Opens up a pull down menu that allows you to specify search options. The label on the button reflects the settings of these search options.

Capitalization and Punctuation indicate case and regular expression settings.

#### ΑII

Capitalized: matches case.

#### all

All lower case: matches ignoring case.

#### AII\*

Capitalized with an asterisk: matches regular expression.

The word indicates the type of value to search for. When using the Search context menu item on a setting with a particular type, the type setting will be set to that type, regular expression.

## All, all, All\*

Searches all text in the tree structure, including values that are multi-line blocks of text.

#### Group, group, Group\*

Searches only group names.

#### Function, function, Function\*

Searches only function names

#### Level, level, Level\*

Searches only detail level names.

#### Text, text, Text\*

Searches only multi-line text block values.

#### Variable, variable, Variable\*

Searches only variable names.

# **Options**

The options section contains settings that are not specific to any detail level, group, or function.




Figure 4-56. Options

#### **Event IDs**

Specifies the range of event\_ids to be mapped to entry and return events. (See "event\_ids="N-[M]"" on page 4-107). If the upper bound of the specified range is 29,999,999, nlight will take over assigning the lower bound to the range 10,000,000 through 29,999,999 such that the assigned event IDs won't overlap other managed illuminator's ranges in the session.

# Limit on Size of Aggregates Recorded

Limits the number of bytes of an aggregate that may be recorded with an event. The limit must be at least 16 bytes. (See "aggregate\_limit="limit"" on page 4-107).

## **Include Functions without Dwarf Debug Info**

Specifies whether functions that have no debug information are to be illuminated or not. Return events are not generated for functions without debug information. (See "node-bug={yes|no}" on page 4-107).

## Regular Expressions

Specifies whether function names that match regular expressions are to be illuminated or not. Multiple expressions may be specified. Each regular expression either specifies functions to include in the illuminated functions list or specifies functions to exclude. If more than one regular expression matches a function name, the last one to match overrides the previous ones. Right click on Regular Expressions to bring up the context menu of regular expressions that may be added to the list.

Include Functions Beginning with Underscore
Exclude Functions Beginning with Underscore
Include Functions in Standard Namespace
Exclude Functions in Standard Namespace
Include Functions Matching POSIX Regular Expression
Exclude Functions Matching POSIX Regular Expression
Search

Figure 4-57. Regular Expressions Context Menu

# Include Functions Beginning with Underscore, Exclude Functions Beginning with Underscore

Includes or excludes functions whose names start with an underscore character. All aliases of a function and the fully qualified C++ name (if applicable) must begin with an underscore in order to match these options (in contrast to **--iregex=\_.\*** or **--xregex=\_.\***). A fully qualified C++ name matches if the function name or name of any containing classes start with an underscore.

The rationale for this is that functions and class names that begin with underscores are typically vendor implementation routines that are of less interest. But it is also common practice to create a strongly defined function that starts with an underscore, then weakly define aliases to that function that do not. These functions, like many in Glibc (see NOTE), are likely to be interesting, and so aren't matched by these options.

#### NOTE

Many functions in Glibc for which all aliases begin with an underscore do not follow standard function call conventions, and so should never be traced via Application Illumination. The default is to exclude functions beginning with underscore.

```
(See "underscores={yes|no}" on page 4-107).
```

# Include Functions in Standard Namespace, Exclude Functions in Standard Namespace

Includes or excludes C++ functions in the std namespace.

The default is to exclude C++ functions in the std namespace. Such functions are often inlined and so tracing them usually doesn't provide a lot of useful information.

```
(See "std={yes|no}" on page 4-108).
```

# Include Functions Matching POSIX Regular Expression, Exclude Functions Matching POSIX Regular Expression

Includes or excludes functions whose names match a POSIX regular expression (see regex(7)). A function name matches the regular expression if any alias or fully qualified C++ name (if applicable) matches it. The regular expression must match the whole name (an implicit ^ and \$ is placed before and after the regular expression respectively).

```
main,
.*\.internal_io.ada, and
.*\.internal_io\.ada\.\..*
```

are excluded.

To include only functions matching a particular *regex*, first exclude all functions:

```
--xregex=.* --iregex=regex
(See "iregex="regex", xregex="regex"" on page 4-108).
```

The context menu on an individual regular expression allows you to change their order (order is important!) or remove a regular expression from the list.




Figure 4-58. Regular Expression Context Menu

## **Object Filenames**

Specifies *object files* that contain the functions to be illuminated. They may be a whole program, archives, shared objects, individual object files, or debug-info files. If the DWARF debug information has been placed in a separate debug-info file, it must be listed immediately after its corresponding object file.

Right click on Object Filenames to get the context menu. Browse for Object Files brings up a standard file dialog for selecting object files. Multiple object files may be selected using control and shift click.



Figure 4-59. Object Filenames Context Menu

The context menu on an individual object file allows you to change their order (this is important only for debug-info files), edit the path to the object file, or remove it from the list.

The Object Filenames list is normally filled in when the session manager creates the illuminator.

(See "filename="filename"" on page 4-108).

## **Detail Levels**

Named detail levels control what functions are illuminated and what details are recorded with those illuminated functions' entry and return events. By default there are three detail levels, 1, 2, and 3. You may delete these and/or add more. Their names are not limited to numbers, but may be any string that can be part of a filename.




Figure 4-60. Detail Levels

There are numerous settings that can be made for each detail level. If a setting has the default value, it is displayed in gray. The default Limit on Size of Aggregates Recorded is inherited from the Limit on Size of Aggregates Recorded setting in Options. The Regular Expressions list is empty by default.

The default value for the other settings depends on the name of the detail level as detailed by the table below. To return a setting to the default setting right click on it and select Clear Setting from the context menu.

(See "level" on page 4-104).

Table 4-2. Detail Levels Settings Defaults

Attribute	1	2	3	Custom
Record Caller on Entry	yes	yes	yes	no
Record Frame Pointer on Entry	no	yes	yes	no
Record Arguments on Entry	no	yes	yes	no
Record Indirect through Arguments on Entry	no	no	yes	no
Record Return Values on Return	yes	yes	yes	no
Record Indirect through Return Values on Return	no	no	yes	no
Record Global Variables on Return	no	no	yes	no
Record errno on Return	no	no	yes	no
Exclude All Functions	no	no	no	no

In the table above, the Custom column is indicating the default setting for the attribute when a custom detail level is initially created. You can of course change the setting when you edit the custom detail level.

#### **Record Caller on Entry**

Records the return address on entry events. (See "caller={yes|no}" on page 4-105).

#### **Record Frame Pointer on Entry**

Records the caller's frame pointer on entry events. (See "frame= $\{yes|no\}$ " on page 4-105).

### Limit on Size of Aggregates Recorded

Sets a size limit (in bytes) on aggregate values recorded with entry and return events. The aggregate value recorded is truncated beyond the limit. (See "aggregate\_limit=limit" on page 4-105).

#### **Record Arguments on Entry**

Records a function's arguments on entry events. If the argument is an aggregate type (class, structure, union, or array), only a limited number of bytes will be recorded. This limit is set by the Limit on Size of Aggregates Recorded setting. (See "args={yes|no}" on page 4-105).

#### **Record Indirect through Arguments on Entry**

Records the value pointed to by a function's pointer arguments on entry events. If the argument is a pointer to an aggregate type (class, structure, union, or array), only a limited number of bytes will be recorded. This limit is set by the Limit on Size of Aggregates Recorded setting. (See "addr\_args={yes|no}" on page 4-106).

#### Record Return Values on Return

Records a function's return value and out arguments on return events. If the value is an aggregate type (class, structure, union, or array), only a limited number of bytes will be recorded. This limit is set by the Limit on Size of Aggregates Recorded setting. (See "return\_val={yes|no}" on page 4-106).

## Record Indirect through Return Values on Return

Records the value pointed to by a function's pointer return value and pointer out arguments on return events. If the value is an aggregate type (class, structure, union, or array), only a limited number of bytes will be recorded. This limit is set by the Limit on Size of Aggregates Recorded setting. (See "addr\_ret={yes|no}" on page 4-106).

#### **Record Global Variables on Return**

Records select global variables and indirection through select global variables on return events. If the value is an aggregate type (class, structure, union, or array), only a limited number of bytes will be recorded. This limit is set by the Limit on Size of Aggregates Recorded setting. The list of variables is empty by default. See "Variables to Record" on page 4-88, "Select Variables to Record, Add Variable to Record" on page 4-93, "Select Variables to Record Add Variable to Record" on page 4-96, "variables={yes|no}" on page 4-106).

#### Record errno on Return

Records the value of errno on return events. (See "errno={yes|no}" on page 4-106).

#### **Exclude All Functions**

Excludes all functions from having entry and return events recorded for them at this detail level. This can be convenient for restricting a detail level to a small set of functions by then overriding this setting for individual groups or functions. (See "exclude={yes|no}" on page 4-106).

#### **Regular Expressions**

Excludes or includes select functions from having entry and return events recorded from them. The same regular expressions may be used here as in the Options section (see "Regular Expressions" on page 4-82). Functions cannot be included here that were excluded in the Options sections. The inclusion regular expressions are for putting back functions that were excluded by previous regular expressions. For example, you could exclude ".\*", then include "c\_.\*" to restrict this detail level to just those functions starting with "c\_". But if the Options section had excluded functions matching "c\_a.\*", they would not be included. (See "under-

scores={yes|no}" on page 4-107, "std={yes|no}" on page 4-108,
"iregex="regex", xregex="regex" on page 4-108).

## Variables to Record

Detail level 3 (by default) and any detail level with the Record Global Variables on Return setting turned on will record any global variables or indirection through global variables that are listed in this section on function return events. The function must have the global variable declared in its DWARF debugging information. No error is generated for functions that don't have the global variable in their DWARF, they just don't record the variable in their return events.

Right click on Variables to Record and select Add Variable or Select Variables to Record to add variables or indirection through variables to this list. (See "variable" on page 4-108).




Figure 4-61. Variables to Record

#### **Add Variable**

Brings up a dialog to allow you to type in a variable name. If the variable name is preceded by an asterisk ("\*"), then the value pointed to by the variable, if it is a pointer, is recorded instead. If the variable isn't a pointer and indirection is requested, no value is recorded.




Figure 4-62. Add Variable Dialog

#### **Select Variables to Record**

Brings up a dialog with a list of variables and their types that were discovered by populating the illuminator (see "Populate" on page 4-47). Pointer variables will be in the list twice: once for themselves and once for indirection through them. Select or deselect the variables desired by clicking in the check box next to them.




Figure 4-63. Select Variables to Record Dialog

To remove a variable from this list, use the Select Variables to Record dialog to deselect them, or right click on the variable to be removed and select the Remove Variable context menu item. This context menu may also be used to rearrange the variables in the list.




Figure 4-64. Variable Name Context Menu

# **Groups**

Functions may be placed in named groups. This is convenient for applying customizations. Perhaps, for example, you want more details on the functions in the group iconv. You could create a copy of detail level 1 called iconv\_details, and then customize that detail level to include more details for functions in the iconv group. (See "group" on page 4-103).

# **Create a Group**

To create a group, right click on **Groups** and select **New Group** from the context menu that pops up. A dialog will pop up asking for a name for the group.



Figure 4-65. Groups Context Menu

# **Customize a Group**

Right click on the group name and select an item from the context menu that pops up.




Figure 4-66. Group Name Context Menu

#### **Select Detail Levels to Customize**

This allows you to customize a detail level for a particular group. A dialog pops up allowing you to select or deselect which detail levels you want to customize.




Figure 4-67. Select Detail Level to Customize Dialog

An additional branch is added to the group's tree for each customized detail level. The values for each detail level setting are gray when they are inherited from the Detail Levels section. The Exclude This Group setting overrides the Exclude All Functions setting in the Detail Levels section. To create a custom detail level that only records events for one group's functions, set Exclude All Functions in the Detail Levels section to yes, then override that for a particular group by setting Exclude This Group to no.



Figure 4-68. A Customized Custom Detail Level for a Group

### Select Variables to Record, Add Variable to Record

These allow you to record additional global variables for return events of just this group's functions for detail levels that have Record Global Variables on Return true. The same dialogs are brought up to select variables as in the Variables to Record section (see "Variables to Record" on page 4-88).




Figure 4-69. A Group with Additional Variables to Record

#### **Rename Group**

This pops up a dialog that prompts for a new name for the group.

#### **Delete Group**

This deletes a group.

## **Selecting Members of a Group**

To select which functions are in a group, right click on the Functions branch under a group name and select the Select Functions in Group context menu item.



Figure 4-70. Member Functions Context Menu

This brings up a dialog with a list of all functions defined in the Functions section to select or deselect from.




Figure 4-71. Select Functions Dialog

Functions may also be added to a group from the Functions section (see "Adding a Function to a Group" on page 4-98).

## **Functions**

The Function section allows customization of individual functions. A function does not have to be listed here to be illuminated (although it does need to be here to be a member of a group). (See "function" on page 4-102).

## Adding a Function

Functions are usually added to this section by using the populate command in the session manager (see "Populate" on page 4-47) or **nlight --populate** on a command line (see "nlight --populate" on page 4-71). Functions may also be added by right clicking on Functions and selecting Add a Function from the context menu that pops up. A dialog will pop up asking for the function name.



Figure 4-72. Functions Context Menu

## **Customizing a Function**

To customize a function, right click on the function name and choose an item from the context menu that pops up.




Figure 4-73. Function Context Menu

#### Select Detail Levels to Customize

This allows you to customize a detail level for a particular function. It works just like customizing a detail level for a particular group (see "Select Detail Levels to Customize" on page 4-92).

#### **Exclude This Function from All Levels**

This allows you to prevent this function from being illuminated for all detail levels. Another way to do this would be to use a regular expression to exclude the function in the Options section.

To remove the exclusion, right click on Exclude This Function From All Detail Levels and select Remove Exclusion from the context menu that pops up.

(See "exclude" on page 4-102).




Figure 4-74. Remove Exclusion Context Menu Item

# Select Variables to Record Add Variable to Record

These allow you to record additional global variables for just the return event of this function for detail levels that have Record Global Variables on Return true. The same dialogs are brought up to select variables as in the Variables to Record section (see "Variables to Record" on page 4-88). Settings in gray are inherited from the Groups section (see "Select Variables to Record, Add Variable to Record" on page 4-93). If a function is a member of more than one group, the first group in the list that provides an explicit setting is the effective value.

Insert File Scope Code
Insert Pre-Entry Event Code
Insert Post-Return Event Code
Replace Real Function Call Code

These are advanced items for inserting assembly code fragments in the function "wrapper" code that records the entry and return events. To edit the code that is to be inserted, double click on the appropriate Handcoded item or right click on it and select Edit from the context menu that pops up. This brings up a text editor dialog. See "wrapper\_file\_scope" on page 4-109, "wrapper\_post" on page 4-109,

"wrapper\_pre" on page 4-109, "wrapper\_real" on page 4-110 for more detailed documentation on these code fragments.




Figure 4-75. Edit Handcoded Dialog

### **Provide C Declaration**

Provides a C language declaration for functions that do not have DWARF debug information (perhaps the function was written in assembly, for example). This setting is ignored if the function has DWARF debug information. The declaration may be preceded by #includes and type definitions. The declaration itself should not include an extern, nor be terminated by a semi-colon. (See "declare" on page 4-101).

```
#include <sys/types.h>
#include <sys/socket.h>
int accept(int s, struct sockaddr *addr, socklen_t *addrlen)

OK Cancel
```

Figure 4-76. Edit Declaration Dialog

#### **Rename This Function**

Pops up a dialog that prompts for a new name for the function.

#### **Delete This Function**

Deletes a function from the Functions section. This does not stop the function from being illuminated, it only removes the customizations for the function and the function's group memberships.

## Adding a Function to a Group

To add a function to a named group of functions that is defined in the Groups section, right click on the Groups branch under a function name and select the Select Groups context menu item.




Figure 4-77. Member of Groups Context Menu

This brings up a dialog with a list of all groups defined in the **Groups** section to select or deselect from.



Figure 4-78. Select Groups Dialog

Functions may also be added to a group from the **Groups** section (see "Selecting Members of a Group" on page 4-94).

# Customizing an Illuminator by Editing the config.xml File

The **config.xml** file in the illuminator directory may be edited to customize the illuminator. This section provides a brief dictionary for the supported XML elements. Each element is documented in alphabetical order and is headed with a brief synopsis that shows the context in which it appears, as well as other elements in may contain.

## comments

Comments (<!-- comment -->) may be placed amongst the XML using standard XML comment syntax. Elements that enclose text (such as <declare>, <wrapper> and <wrapper\_\*> may not have comments embedded in the text. Comments are lost when a config.xml file is repopulated with the nlight --populate command. There is no guarantee on the order of the elements, so there is no way to know exactly where to place the comments in the repopulated file. The three-way comparison tool, diff3(1), may be used to help reinsert them into the approximate correct place.

# config

```
<config>
   /<defaults>
      /<level .../> .../
      ///> .../> .../
      [<variable name=[*]variable_name/> ...]
   </defaults> ...]
   [<variable name=variable_name</pre>
               [type=type_name ptr={yes/no}]/> ...]
   /<group name=group name>
      [<variable name=[*]variable_name/> ...]
   </group> ...]
   [<function name=function_name>
      /<exclude/>/
      /<level ... /> .../
      [<group name=group_name/> ...]
      [<wrapper>wrapper function</wrapper>]
      [<wrapper_file_scope>some code</wrapper_file_scope>]
      [<wrapper_pre>some code</wrapper_pre>]
      [<wrapper_real>call to real function</wrapper_real>]
      /<wrapper post>some code</wrapper post>/
      [<declare>declaration</declare>]
      /<variable name=[*]variable name/> ...]
   </function> ...]
</config>
```

Encloses the entire file. It may contain four types of elements: <defaults> (see page 4-101), <variable> (see page 4-108), <group> (see page 4-103), and <function> (see page 4-102).

### declare

```
<function ...>
     <declare>declaration</declare>
</function>
```

Provides a C language declaration for functions (see "function" on page 4-102) that do not have DWARF debug information (perhaps the function was written in assembly, for example). This element is ignored if the function has DWARF debug information. The declaration may be preceded by #includes and type definitions. The declaration itself should not include an extern, nor be terminated by a semi-colon. Here is an example:

```
<declare>
   #include &lt;sys/types.h&gt;
   pid_t getpgid(pid_t pid)
</declare</pre>
```

Certain characters are special in XML and must be replaced with "character entities":

**Table 4-3. Character Entities** 

## defaults

```
<config>
   <defaults>
      /<level name=level name</pre>
               [caller={yes/no}]
               [frame={yes/no}]
               [aggregate limit=limit]
               [args={yes/no}]
               [addr_args={yes/no}]
               [return_val={yes/no}]
               [addr_ret={yes/no}]
               [variables={yes/no}]
               [errno={yes/no}]
               [exclude={yes/no}]>
       [<options [underscores={yes/no}]</pre>
                      [std={yes/no}]
                      [xregex=regex]
                      [iregex=regex]/> ...]
       </level> .../
       [<options .../> ...]
```

```
[<variable name=[*]variable_name/> ...]
  </defaults>
</config>
```

Defines the defaults for all functions and groups (see "config" on page 4-100). It may contain zero or more <level> elements (see "level" on page 4-104) to customize the detail levels 1, 2, or 3, or to define a user-named custom detail level. It may contain zero or more <options> elements (see "options" on page 4-107) to specify values for certain command line options.

Finally, it may contain zero or more <variable> elements (see "variable" on page 4-108) to specify global variables to be recorded with the return event for any function whose DWARF defines the global variables when the detail level includes variables.

### exclude

```
<function ...>
     <exclude/>
</function>
```

Excludes a function (see "function" on page 4-102) from all detail levels without having to list separate <level> (see "level" on page 4-104) elements. If both the <exclude/> element and an exclude attribute (see "exclude={yes|no}" on page 4-106) for a specific <level> are specified in a <function> element, the exclude attribute takes precedence. Thus:

```
<function name=hello>
    <exclude/>
    <level=3 exclude=no>
</function>
```

will exclude hello() from all detail levels except 3.

## **function**

```
<config>
    <function name=function_name>
        [<exclude/>]
        [<level ... /> ...]
        [<group name=group_name/> ...]
        [<wrapper>wrapper function</wrapper>]
        [<wrapper_file_scope>some code</wrapper_file_scope>]
        [<wrapper_pre>some code</wrapper_pre>]
        [<wrapper_real>call to real function</wrapper_real>]
        [<wrapper_post>some code</wrapper_post>]
        [<declare>declaration</declare>]
        [<variable name=[*]variable_name/> ...]
        </function>
</config>
```

Defines settings for a specific function (see "config" on page 4-100). It may contain:

- zero or more <level> elements (see "level" on page 4-104) to override
  the defaults for the detail levels for function name;
- zero or more <group> elements (see "group" on page 4-103) to designate function name as a member of a group of functions;
- an optional <wrapper> element (see "wrapper" on page 4-109) to provide a hand written "wrapper" function;
- optional <wrapper\_\*> elements (see "wrapper\_file\_scope" on page 4-109, "wrapper\_post" on page 4-109, "wrapper\_pre" on page 4-109, and "wrapper\_real" on page 4-110) to provide some code to insert into or replace parts of the machine generated "wrapper" function;
- an optional <declare> element (see "declare" on page 4-101) to provide the declaration of the function being "wrapped";
- zero or more <variable> elements (see "variable" on page 4-108) to specify global variables to be recorded with return events if the function's DWARF defines the global variables when the detail level includes variables.

## group

Defines settings for a named group of functions (see "config" on page 4-100). It may contain zero or more <level> elements (see "level" on page 4-104) to specify settings for particular detail levels for the named group of functions. The named levels must be one of the three predefined levels, or a user-named custom level defined in a defaults element.

It may also contain zero or more <variable> elements (see "variable" on page 4-108) to specify global variables to be recorded with return events for all functions in the group whose DWARF defines the global variables when the detail level includes variables.

```
<function ...>
    <group name=group_name/>
</function>
```

Designates in a <function> element (see "function" on page 4-102) that the subject function is a member of *group\_name*. In this context it may not contain any <level> or <variable> elements.

#### level

```
<defaults>
   <level name=level name</pre>
          /caller={yes/no}/
          /frame={yes/no}/
          [aggregate_limit=limit]
          [args={yes/no}]
          [addr_args={yes/no}]
          [return_val={yes/no}]
          /addr ret={yes/no}/
          [variables={yes/no}]
          [errno={yes/no}]
          [exclude={yes/no}]>
      [<options [underscores={yes/no}]
                 [std={yes/no}]
                 [xregex=regex]
                 [iregex=regex]/>]
   </level>
</defaults>
```

Modifies the default settings (see "defaults" on page 4-101) for predefined detail levels or defines a custom detail level. The attributes and elements control whether a function is traced, and what details are recorded with the trace events if it is.

<options> elements (see "options" on page 4-107) corresponding to --x\* and --i\*
command line options may also be specified in a <level> element when it appears in a
<defaults> element. These may not be used to include any functions that were
excluded at the command line level or by the corresponding <options> element within
a <defaults> element, but may be used to restrict a level to a smaller subset for a specific detail level. One way of creating a new level that excludes all functions but one is:

The effective value of each attribute for a given function and detail level is determined by searching for a definition of the attribute in the following places in the following order:

- a <level> element in the function's <function> element;
- a <level> element in each of the function's group memberships, in the order the <group> elements were listed;
- a <level> element in the <defaults> element;
- the system defaults.

The system defaults for the attributes are:

Table 4-4. System Defaults

Attribute	Level 1	Level 2	Level 3	Custom Levels
caller	yes	yes	yes	no
frame	no	yes	yes	no
aggregate_limit	16	16	16	16
args	no	yes	yes	no
addr_args	no	no	yes	no
return_val	yes	yes	yes	no
addr_ret	no	no	yes	no
variables	no	no	yes	no
errno	no	no	yes	no
exclude	no	no	no	no

The details that can be recorded are partitioned into several named classes. To turn on one of those classes, specify *classname*=yes as an attribute to the <level> element. For example, to create a custom detail level to record only the function arguments, you would code the following element in a <defaults> element:

<level name="argsonly" args=yes/>

To turn off an attribute specify attribute=no.

caller={yes/no}

The return address in the caller is recorded on entry events.

frame={yes/no}

The address of the frame of the caller is recorded on entry events.

aggregate\_limit=limit

A limit is set on the number of bytes of an aggregate that can be recorded with an entry or return event. The limit must be at least 16 bytes.

args={yes/no}

The arguments passed to the traced function are recorded on entry events, and out arguments are recorded on return events.

```
addr_args={yes/no}
```

The variables pointed to by arguments that are pointers are recorded on entry events. The variables pointed to by out arguments that are pointers are recorded on return events. When these are aggregates (strings, arrays, structures, or unions), the number of bytes that may be recorded is limited by the aggregate\_limit setting.

```
return_val={yes/no}
```

The return value of the function (if it has one) is recorded on return events.

```
addr_ret={yes/no}
```

The variable pointed to by the return value, if it is a pointer, is recorded on return events. When this is an aggregate (string, array, structure, or union), the number of bytes that may be recorded is limited by the aggregate\_limit setting.

```
variables={yes/no}
```

Variables or indirection through variables specified with <variable> elements (see "variable" on page 4-108) in <defaults>, <group>, and <function> elements are recorded on return events.

errno={yes/no}

The value of errno is recorded on return events.

```
exclude={yes/no}
```

Functions are entirely excluded from being recorded. Normally this would be set to yes only on individual functions or groups of functions. Or, one could set it to yes in <defaults>, then override that on individual functions or groups of functions in order to only include those functions. For example, the following creates a new detail level that excludes all but one function:

```
<defaults>
     <level name=0 exclude=yes/>
</defaults>
<function name=pthread_create>
     <level name=0 exclude=no/>
</function>
```

See also "exclude" on page 4-102 for a shorthand way to exclude a function from all detail levels.

# options

Specifies values for several command line options (see "defaults" on page 4-101, "nlight --create" on page 4-68). Options specified after a **--config** option on the command line will override those set in the *config.xml* file.

Specifies level-specific overrides for command line options that exclude or include functions by their name (see "level" on page 4-104, "--i\*, --x\*" on page 4-70).

```
event_ids="N-[M]"
```

Specifies the range of event\_ids to be mapped to entry and return events (see "--event\_ids=N-[M]" on page 4-69).

```
aggregate_limit="limit"
```

Limits the number of bytes of an aggregate that may be recorded with an event (see "--aggregate\_limit=limit" on page 4-68). The limit must be at least 16 bytes.

nodebug={yes/no}

Specifies whether function names that have no debug information are to be included or excluded respectively (see "--do\_nodebug, --dont\_nodebug" on page 4-69).

```
underscores={yes/no}
```

Specifies whether function names that start with an underscore are to be included or excluded respectively (see "--iunderscores, --xunderscores" on page 4-70). This may also be specified for a particular level (see "level" on page 4-104).

```
std={yes/no}
```

Specifies whether function names in the C++ std namespace are to be included or excluded respectively (see "--istd, --xstd" on page 4-71). This may also be specified for a particular level (see "level" on page 4-104).

```
iregex="regex", xregex="regex"
```

Specifies whether function names that match the POSIX regular expression are to be included or excluded respectively (see "--iregex=regex, --xregex=regex" on page 4-70). This may also be specified for a particular level (see "level" on page 4-104).

To specify multiple instances of these attributes, you must use separate <options> elements since XML syntax does not allow duplicate attribute names.

```
filename="filename"
```

Specifies an object file, shared object file, debug-info file, archive, or program to read DWARF from to generate "wrapper" functions. These filenames may also be specified as arguments to the **nlight** --create command (see "nlight --create" on page 4-68).

To specify more than one filename, you must use multiple <options> elements since XML syntax does not allow duplicate attribute names.

## variable

Defines a a global variable (see "config" on page 4-100). **illuminator** does not actually use this element. It is populated by the **nlight --populate** command (see "nlight --populate" on page 4-71). You may wish to consult this list (or **nlight --report** output, see "nlight --report" on page 4-72) to get the exact correct spelling of certain variable names in name-mangling languages. The fully qualified name is reconstructed from the mangled name, and may include elements that are implicit in the original source.

Names a variable (with optional indirection), when it appears in a <defaults>, <group>, or <function> element (see "defaults" on page 4-101, "group" on page 4-103, "function" on page 4-102), that will be recorded on return events at detail levels that have the variables=yes attribute set (see "variables={yes|no}" on page 4-106). Depending on which element it appears in, it may apply to all functions, all functions in a group, or a particular function (for <defaults>, <group>, or <function> elements respectively). The function's DWARF must include a definition of the variable in question. No error message is generated if it is absent from the DWARF.

## wrapper

```
<function ...>
     <wrapper>assembly "wrapper" function</wrapper>
</function>
```

Specifies a hand coded "wrapper" function for a specific function (see "function" on page 4-102). The text between the opening and closing tags is copied verbatim into the "wrapper" function assembly language source file. It may not be used with the other <wrapper\_\*> elements.

# wrapper\_file\_scope

```
<function ...>
    <wrapper_file_scope>some code</wrapper_file_scope>
</function>
```

Specifies assembly language code to be inserted in "file scope" just before the "wrapper" function (see "function" on page 4-102). It may not be used with a <

# wrapper\_post

```
<function ...>
    <wrapper_post>some assembly code</wrapper_post>
</function>
```

Specifies assembly language code to insert into a generated "wrapper" function after the return event is recorded but just before actually returning (see "function" on page 4-102). One use might be to insert some debug code into the application. It may not be used with a <wrapper> element.

# wrapper\_pre

```
<function ...>
    <wrapper_pre>some assembly code</wrapper_pre>
</function>
```

Specifies assembly language code to insert into a generated "wrapper" function before the entry event is recorded (see "function" on page 4-102). One use might be to test for a situation where you don't want an event to be recorded. It may not be used with a <wrapper> element.

# wrapper\_real

```
<function ...>
    <wrapper_real>assembly code call to real function</wrapper_real>
</function>
```

Specifies assembly language code to call the real function in place of the default code in a generated "wrapper" function (see "function" on page 4-102). It may not be used with a <wrapper> element.

Here's an example of intercepting a function called through a pointer parameter in pthread\_create() in order to call trace\_register\_thread() in the newly created thread:

```
<function name=pthread_create>
  <wrapper_file_scope>
       # Set up a function that gets called by the new
       # thread instead of start_routine. This function
       # gets an arg that informs it of the original
       # function and its arg.
       .type prestart_routine,@function
prestart_routine:
       pushq %rdi;
                        # save the arg while I do a call
       call trace_register_thread
       movq (%rsp), %rax # get the arg back
       movq 8(%rax),%rdi # get the original arg
       movq (%rax),%rll  # get the original start_routine
       call *%rll # call it
       pushq %rax
                         # save return value
       movq 8(%rsp),%rdi # free myarg
       call free
       popq %rax;
       addq $8,%rsp
       ret
       .size prestart_routine,.-prestart_routine
  </wrapper_file_scope>
  <wrapper_real>
       # allocate arg for the interceptor routine (thread safe)
       movq $16,%rdi
       call malloc
       # store the original start_routine
       # and arg into the new arg
       movq -24(%rbp),%r11
                                      # start_routine
       movq %r11,(%rax)
                                      # arg
       movq -32(%rbp),%r11
       movq %r11,8(%rax)
        # set up parameters to the interceptor routine
       movq -8(%rbp),%rdi
                                      # newthread
       movq -16(%rbp),%rsi
                                       # attr
       lea prestart_routine(%rip),%rdx # interceptor start
                                       # routine
       movq %rax, %rcx
                                       # myarg
        # call the real function passing my interceptor routine
       call __real_pthread_create
  </wrapper_real>
</finction>
```

Note that to call the real function from a "wrapper" you call \_\_real\_function, otherwise, the call to function would be diverted to \_\_wrap\_function and become an infinite recursion.

The NightTrace function trace\_register\_thread() is obsolete in the latest NightTrace release, but is retained in this example because it makes such a good illustration of doing something complex with inserting code in an illuminator.

# **Examples**

Appendix F includes several examples with step-by-step instructions for using Application Illumination in a variety of scenarios.

See "NightTrace Application Illumination Examples" on page F-1.

# **Performance Tuning**

The NightTrace default configuration is often sufficient for most tracing needs, however, situations with exceptionally high trace event rates or those requiring precise control over disk activity may require adjustment. This chapter discusses the following:

- "Preventing Trace Event Loss" on page 5-1
- "Conserving Disk Space" on page 5-3
- "Conserving Memory and Accelerating ntrace" on page 5-3

# **Preventing Trace Event Loss**

By default, NightTrace copies <u>all</u> user trace events from the shared memory buffer to the trace event file. This means that normally NightTrace neither discards nor loses trace events as long as it can copy the shared memory buffers to the output device faster than the application can fill up all remaining shared memory buffers.

NightTrace reports lost trace events in several ways:

- The --info options to ntraceud and ntracekd describe the number of lost events
- The Daemon Control area in ntrace displays event loss counts
- NightTrace display pages include a visual indicator on the ruler, a capital L
  character, indicating where event loss started to occur
- An internal trace point, NT\_LOST\_DATA, is included in the trace data output at the point where trace events began to be lost

## **NOTE**

Events that are overwritten in file-wrap and buffer-wrap modes are not considered lost events and are not reported.

# **Daemon Scheduling Adjustment**

The scheduling policy, priority, and CPU bias of daemons can be adjusted using the following methods:

- Invoke **ntraceud** with the **--priority=***P*, **--policy=***P*, and **--processor=***C* command line options to select scheduling priority, policy and CPU binding.
- Select the scheduling policy, scheduling priority and CPU bias from the Runtime tab of the Daemon Definition dialog in the ntrace tool.

# **Increasing Trace Buffer Size**

The number of trace buffers and the size of trace buffers can be adjusted using the following methods:

- Specify larger values using the --numbufs and --buflen options to ntraceud. The default values for these options are 8 and 32768, respectively.
- Specify larger values for the ntc\_num\_buffers and ntc\_buffer\_length fields
  in the ntconfig\_t configuration record passed to trace\_begin. The
  default values for these fields are 8 and 32768, respectively. Note that
  these configuration values will be ignored if the corresponding user daemon has already started and the value of ntc\_daemon\_preferred is set to
  TRUE.
- Specify larger values for Number of Buffers and Buffer Size in the User Trace tab of the Daemon Definition dialog in the ntrace tool. The default values for these settings are 8 and 32768, respectively.
- Specify larger values for Number of Trace Buffers and Trace Buffer Size using the Other tab of the Daemon Definition dialog in the ntrace tool. The default values for these settings are 4 and 50000, respectively.

When increasing user trace buffer sizes, your request may be rejected if the total trace buffer shared memory size exceeds system limitations. You can increase the system shared memory limits by adjusting the *kernel.shmmax* and *kernel.shmall* variables using the **systct1(8)** command.

For user trace buffers, the number of buffers and buffer length must be individually a power of two. These values are automatically increased to the next highest power of two if this is not the case.

Since daemons are notified immediately when a single trace buffer fills, adding additional buffers is sometimes as effective as increasing the size of buffers. The applications continue to log trace events to the next shared memory buffer while the daemon flushes the filled buffer.

# **Programmatic Flushing**

For applications which log trace events, the trace\_flush API routine can be used to cause the associated user daemon to wake up and flush all filled buffers.

Modifying the sizes and number of trace buffers as described in the previous section is usually more effective than relying on trace\_flush, since the daemon automatically wakes and empties buffers as individual buffers are filled.

# **Conserving Disk Space**

If disk space is an important consideration and you are most interested in the latest events that are logged, use of file-wrap and buffer-wrap modes is helpful.

In buffer-wrap mode, no disk activity occurs until the daemon is terminated or an explicit flush is requested. When all trace buffers are filled, the oldest events are overwritten by the newest events.

In file-wrap mode, a file size maximum is imposed and the oldest events are overwritten by the newest events when the maximum size is reached.

Both of these options can be useful when desiring to obtain trace data from a situation which rarely appears.

For example, the following commands might be used to capture user trace data for an extended period of time (even hours or days) until your application detects a specific situation:

```
> ntraceud --filewrap=10M user-data
> ./a.out
```

#### > ntraceud --quit user-data

# **Conserving Memory and Accelerating ntrace**

**ntrace** can be a memory-intensive tool. By default, when **ntrace** starts up, it loads <u>all</u> trace event information into memory; therefore, the more trace events in your trace event file(s), the more memory **ntrace** uses. When you move the scroll bar on a display page to change the displayed interval, **ntrace** processes all trace events between the last interval and this one; if there are many trace events, the display update (or search) may be slow. To conserve memory and accelerate **ntrace**:

- Log only trace events you are really interested in.
- Disable uninteresting events via the --disable option to ntraceud or via the Events tab of the Daemon Definition dialog in the ntrace tool.
- Invoke ntrace only with the trace event files that are essential to your analysis.
- Once ntrace is launched, select a data region of interest and discard all
  other events to reduce the working set size by selecting the Discard
  Events... option from the Events menu of a display page.

• Operate the daemons in file-wrap or buffer-wrap modes to reduce data set size in favor of keeping the most recent events.

# Invoking NightTrace

NightTrace is invoked using ntrace which is normally installed in /usr/bin.

The full command syntax for **ntrace** is:

Depending on the options and arguments specified to ntrace, NightTrace:

- loads all trace event information into memory
- checks the syntax of specifications in each file argument
- processes each file argument
- loads any display pages and their objects into memory
- presents any timeline panels (see "Timeline Panels" on page 11-1)
- displays the NightTrace Main Window (see "The NightTrace Main Window" on page 7-1)

# **Command-line Options**

The command-line options to **ntrace** are:

```
-h
--help
```

Displays **ntrace** invocation syntax and a list of all command line options to standard output.

```
--help-summary
```

Displays help specific to the **--summary** option to standard output.

See "Summary Criteria" on page 6-5 for more information.

#### -v

#### --version

Displays the current version of NightTrace to standard output and exits.

## -1

## --listing

Displays a chronological listing of all trace events and their arguments from all supplied trace-event data files to standard output and exits.

The output includes the following information about a trace event:

- · relative timestamp
- · trace event ID
- any trace event argument(s)
- the process identifier (PID), process name, or thread name
- the system node name (when data sets from multiple systems are present)

The timestamp for the first trace event is zero seconds (0s). All other timestamps are relative to the first one.

If you supply an event map file on the invocation line, NightTrace displays symbolic trace event names instead of numeric trace event IDs, and displays trace event arguments in the format you specify in the file, rather than the hexadecimal default format. For more information on event map files, see "Event Map Files" on page 6-9.

#### --stats

Displays simple overall statistics about the trace-event data files to standard output and exits.

The statistics are grouped by trace event file, with cumulative statistics for all trace event files.

The statistics include:

- the number of trace event files
- · their names
- the number of trace events logged
- the number of trace events lost

For example, the following command:

### ntraceud /tmp/data

collects trace data from any user applications which are logging the data to /tmp/data. (see "Capturing User Events with ntraceud" on page 3-1).

Issuing the command:

```
ntrace --stats /tmp/data
```

results in the output similar to the following (assuming user application were actually logging data):

```
Read 1 trace event segment timestamped with Intel TSC.

(1) User trace event log file: /tmp/data.
2268 trace events saved.
0 trace events lost.
2.9707482s time span, from 0.0000000s to 2.9707482s.

2268 total events read from disk.
2268 total events saved in memory.
0 total trace events lost.
2.9707482s total time span saved in memory.
```

Detailed summary information about a trace data set is available via the **--summary** option.

```
-s val
--start={ offset | time{ s | u } | percent% }
```

Excludes from analysis trace events before the specified trace-event offset, relative time in seconds  $(\mathbf{s})$  or microseconds  $(\mathbf{u})$ , or percent of total trace events.

The specified values can be:

offset

Load trace events after the specified trace event offset.

```
time\{ s | u \}
```

Load trace events after the specified relative time in seconds  $(\mathbf{s})$  or microseconds  $(\mathbf{u})$ .

percent%

Load trace events after the specified percent of total trace events. The % is required.

If you invoke NightTrace with several **--start** options, NightTrace pays attention only to the last one.

```
-e val
--end={ offset | time{ s | u } | percent% }
```

Excludes from analysis trace events after the specified trace-event offset, relative time in seconds  $(\mathbf{s})$  or microseconds  $(\mathbf{u})$ , or percent of total trace events.

The specified values can be:

offset

Load trace events before the specified trace event offset.

#### $time\{ s | u \}$

Load trace events before the specified relative time in seconds  $(\mathbf{s})$  or microseconds  $(\mathbf{u})$ .

#### percent%

Load trace events before the specified percent of total trace events. The % is required.

If you invoke NightTrace with several **--end** options, NightTrace pays attention only to the last one.

#### -x

#### --notimelines

Starts NightTrace but does not include any timeline panels.

#### -u

#### --use-session

Automatically loads the last session used in a previous invocation of NightTrace. All files associated with the previous session are automatically loaded.

## --summary=criteria

Provides a textual summary of specified trace events using the supplied *criteria*. Summary results are sent to standard output.

See "Summary Criteria" on page 6-5 for details regarding valid criteria.

#### --import=a.out

## a.out

These options specify the executable file containing daemon definitions and the location of format tables and event description files. This information is embedded in executable files when they contain instrumented code generated by the Night-Trace illuminator tool.

A daemon definition is created with the number of buffers, buffer length, and trace key file information extracted from the file. If the executable file does not include such information, ntrace queries the user for the name of the trace key file, and uses default values for other daemon settings.

NightTrace loads all event description and format table files gleaned from the executable.

Specifying **a.out** as a standalone argument processes executable files in the same manner as those specified with **--import**. In addition, NightTrace loads the user trace data file as specified by information embedded by the built-in "main" illuminator if it was included in the program. NightTrace also records the pathname of the specified file and associates it with any references to the base name of the file in lookup\_pc() references during the NightTrace session. For example:

ntrace /tmp/a.out

References to "a.out" in lookup\_pc() expressions in the session will use /tmp/a.out as the path to the file from which PC descriptions (routine, file and line number) are read.

#### --verbose

In addition to the cumulative statitistics normally output, this option provides detailed information about each occurrence of the item being summarized.

file ...

You can invoke NightTrace with arguments such as trace event files, event map files, page configuration files, session configuration files, or trace data segments.

See "Command-line Arguments" on page 6-8 for a description of these types of files.

By default, when NightTrace starts up, it reads and loads <u>all</u> trace events from all trace event files into memory. The **--process**, **--start**, and **--end** options let you prevent the loading (but not the reading) of certain trace events.

For example, the following invocation displays only those trace events logged 0.5 seconds or more after the start of the data set.

ntrace --start=0.5s /tmp/data

## **Summary Criteria**

The **--summary** option is supplied with criteria for command-line usage without ever using the GUI to perform summaries.

### **NOTE**

The **--verbose** option provides detailed information about each occurance of the item being summarized in addition to the cumulative statitistics normally output.

This criteria consists of a comma-separated list of any of the following:

crit

This allows previously-defined profiles to be referenced when doing command line summaries.

To use previously-defined profiles when executing a summary from the command line, specify the desired profile name (*crit*) on the command line along with the NightTrace session configuration file which contains that profile

#### ev:event

Summarizes the number of occurrences of the specified *event*.

#### f:func

Summarizes all function entry events for the specified function *func*. This option is only useful if you have loaded Application Illumination data. See "Application Illumination" on page 4-1 for more infomation.

#### fr:func

Summarizes all function return events for the specified function *func*. This option is only useful if you have loaded Application Illumination data. See "Application Illumination" on page 4-1 for more infomation.

#### fe:func

Summarizes all function entry and return events for the specified function *func*. This option is only useful if you have loaded Application Illumination data. See "Application Illumination" on page 4-1 for more infomation.

#### fs:func

Summarizes all function call states for the specified function *func*. This option is only useful if you have loaded Application Illumination data. See "Application Illumination" on page 4-1 for more infomation.

#### fs:\*

Summarizes all function calls statistics for all functions. This option is only useful if you have loaded Application Illumination data. See "Application Illumination" on page 4-1 for more infomation.

## p:process

Summarizes all events associated with the specified process.

## t:thread

Summarizes all events associated with the specified thread.

### skip:on

Suppresses summarization for all subsequent criteria in the list (or until a **skip:off** criteria is seen) if there are no summarization matches for the criteria.

## skip:off

Reactivates summarization for all subsequent criteria in the list (or until a **skip:on** criteria is seen) if there are no summarization matches for the criteria.

#### st:start-end

Summarizes all occurrences of the state defined by the starting event *start* and terminated by the ending event *end*.

These may be combined together along with tagged criteria from the Summarize NightTrace Events dialog in a comma-separated list.

Consider the following example:

```
ntrace --summary=ev:5,crit_0 event_file my_session
```

Using the trace event file **event\_file** as the trace data source (see "Trace Event Files" on page 6-9), NightTrace will:

- 1. summarize the number of occurrences of user events with a *trace event ID* of 5 as well as information about the gaps between the events (min, max, avg)
- perform a summary using the profile defined by crit\_0 in the my\_session session file (see "Session Configuration Files" on page 6-21)

## **NOTE**

In order to use a summary criteria tag on the command line, the NightTrace session configuration file in which it was defined must be specified on the command line as well (see "Session Configuration Files" on page 6-21).

The following criteria may be specified <u>alone</u> (not part of a comma-separated list):

```
evt[:proc]
```

Summarize the number of occurrences of all events named in event map files. User events which are not named in event map files are not shown. If \*:proc\* is provided, only those events associated with proc\* are summarized.

proc

Summarize the number of events for each process.

# **Command-line Arguments**

You can supply filenames as arguments to the **ntrace** command when invoking Night-Trace. These files may contain trace event data, display page layouts, additional configuration information, or information related to a previously-saved session.

These arguments can be:

• trace event files

Trace event files are captured by a user trace daemon and contain sequences of trace events logged by your application.

See "Trace Event Files" on page 6-9 for more information.

• event map files

Event map files map short mnemonic trace event names to numeric trace event IDs and associate data types with trace event arguments. These ASCII files are created by the user.

See "Event Map Files" on page 6-9 for more information.

session configuration files

Session configuration files define a list of daemon sessions and their individual configurations. In addition, session configuration files contain definitions of profiles and search and summary configurations from previous uses of the session. Also, session configuration files contain a list of any files the user associated with the session, such as event map files and trace data files.

See "Session Configuration Files" on page 6-21 for more information.

• trace data segments

Trace data segments are conglomerations of all trace data saved in a much more efficient format than raw trace event files providing for faster initialization at startup. These files are created using the Save Trace Segments... menu choice of the File menu on the NightTrace Main Window.

See "Trace Data Segments" on page 6-22 for more information.

program file

Application Illumination embeds in executable object files paths to various support files that **ntrace** can extract:

- event map files defining names for the events generated for function entry and return points;
- configuration files containing format tables to neatly format the events and their arguments generated for function entry and return points;

a trace event file if the main illuminator is used (this file may be recorded using a relative path; if this is the case, ntrace must be invoked with the same current working directory that the program file was executed with).

See "Application Illumination" on page 4-1 for more information.

## **Trace Event Files**

Trace event files are created by user trace daemons. They consist of header information and individual trace events and their arguments as logged by user applications or the operating system. NightTrace detects trace event files as specified on the command line and does the required initialization processing so that the trace events contained in the files are available for display.

To load a trace event file, either:

- specify the trace event file as an argument to the **ntrace** command when you invoke NightTrace, or
- select the Open Files... menu option from the File menu of the Night-Trace main window and select the trace event file from the file selection dialog

## **Event Map Files**

NightTrace does not require you to use event map files. However, using these files can improve the readability of your NightTrace displays.

An *event map file* allows you to associate meaningful names with the more cryptic trace event ID numbers. It also allows you to associate additional information with a trace event including the number of arguments and the argument conversion specifications or display formats. Although NightTrace does not require you to use event map files, labels and display formats can make graphical NightTrace displays and textual summary information much more readable.

To load an existing event map file, perform any of the following:

- specify the event map file as an argument to the ntrace command when you invoke NightTrace
- select the Open Files... menu item from the File menu on the Night-Trace Main Window

You can create an event map file with a text editor before you invoke NightTrace.

There is one trace event name mapping per line. White space separates each field except the conversion specifications; commas separate the conversion specifications. NightTrace ignores blank lines and treats text following a # as comments.

The syntax for the trace event mappings in the event map file follows:

```
event: ID "event_name" [ nargs [ conv_spec, ... ] ]
```

Fields in this file are:

event:

The keyword that begins all trace event name mappings.

ID

A valid integer in the range reserved for user trace events (0-4095, inclusive). Each time you call a NightTrace trace event logging routine, you must supply a trace event ID.

event\_name

A character string to be associated with *event\_ID*. Trace event names must begin with a letter and consist solely of alphanumeric characters and underscores. Keep trace event names short; otherwise, NightTrace may be unable to display them in the limited window space available.

The following words are reserved in NightTrace and should not be used in uppercase or lowercase as trace event names:

- NONE
- ALL
- ALLUSER
- TRUE
- FALSE
- CALC

#### TIP

Consider giving your trace events uppercase names in event map files and giving any corresponding profile referring to those events the same name in lowercase. For more information about profiles of events, see "Profile References" on page 15-181.

If your application logs a trace event with one or more numeric arguments, by default NightTrace displays these arguments in decimal integer format. To override this default, provide a count of argument values and one argument conversion specification or display format per argument.

nargs

The number of arguments associated with a particular trace event. If *nargs* is too small and you invoke NightTrace with the event map file and the **--listing** option, NightTrace shows only *nargs* arguments for the trace event.

```
conv_spec
```

A conversion specification or display format for a trace event argument. NightTrace uses conversion specification(s) to display the trace event's argument(s) in the designated format(s). There must be one conversion specification per argument. Valid conversion specifications for displays include the following:

```
%d
    signed decimal integer (default)
%o
    unsigned octal integer
%x
    unsigned hexadecimal integer
%1f
    signed double precision, decimal floating point
```

For more information on these conversion specifications, see  ${\tt printf(3)}$ .

The following line is an example of an entry in an event map file:

```
event: 5 "Error" 2 %x %lf
```

NightTrace displays trace event 5 and labels the trace event "Error". Trace event 5 also has two (2) arguments. NightTrace displays the first argument in unsigned hexadecimal integer (%x) format and the second argument in signed double precision decimal floating point (%lf) format. (You may override these conversion specifications when you configure display objects.)

For more information on event map files, see "Pre-Defined Strings Tables" on page 6-15.

## **Table Files**

A *table file* contains information used to obtain verbose descriptions of events or arguments associated with events..

A table file is an ASCII file containing such definitions as:

- string table definitions (see "String Tables" on page 6-13)
- format table definitions (see "Format Tables" on page 6-17)

### **NOTE**

Any tables found in page configuration files are imported into the session; when the session is saved, these tables are saved with the session. Tables are no longer saved as part of the page configuration files.

#### NOTE

If you define a string table or format table more than once in a configuration file, NightTrace merges the two tables; if there are duplicate entries, values come from the last definition.

To load an existing table file, either:

- specify the configuration file as an argument to the **ntrace** command when you invoke NightTrace
- Select the Open Files... menu option from the NightTrace menu of the NightTrace Main window and select the configuration file from the file selection dialog

## **Tables**

The table file may contain two types of tables, both of which can improve the readability of your NightTrace displays:

- string tables (see "String Tables" on page 6-13)
- format tables (see "Format Tables" on page 6-17)

A table lets you associate meaningful character strings with integer values such as trace event arguments. These character strings may appear in NightTrace displays.

The following table names are reserved in NightTrace and should not be redefined in uppercase or lowercase:

- event
- pid

- tid
- boolean
- name\_pid
- name\_tid
- node\_name
- pid\_nodename
- tid\_nodename
- vector
- syscall
- device
- vector\_nodename
- syscall *nodename*
- device\_nodename
- vararg\_functions

The results are undefined if you supply your own version of these tables.

#### **NOTE**

The only way to put tables into your configuration file is by text editing the file before you invoke NightTrace. To avoid any forward-reference problems, define all string tables before any format tables.

For more information on pre-defined tables, see "Pre-Defined Strings Tables" on page 6-15.

If you define a string table or format table more than once in a configuration file, Night-Trace merges the two tables; if there are duplicate entries, values come from the last definition.

## **String Tables**

You can log a trace event with one or more numeric arguments. Sometimes these arguments can take on a nearly fixed set of values. A *string table* associates an integer value with a character string. Labeling numeric values with text can make the values easier to interpret.

The syntax for a string table is:

```
string_table ( table_name ) = {
  item = int_const, "str_const" ;
  ...
```

```
[ default_item = "str_const" ; ]
};
```

Include all special characters from the syntax except the ellipsis (...) and square brackets ([]).

The fields in a string table definition are:

```
string_table
```

The keyword that starts the definition of all string tables.

```
table_name
```

The unique, user-defined name of this table. This name describes the relationship of the numeric values in this string table.

An *item line* associates an integer value with a character string. This line extends from the keyword item through the ending semicolon. You may define any number of item lines in a single string table. The fields in an item line are:

item

The keyword that begins all item lines.

int\_const

An integer constant that is unique within *table\_name*. It may be decimal, octal, or hexadecimal. Decimal values have no special prefix. Octal values begin with a zero (0). Hexadecimal values begin with 0x.

str\_const

A character string to be associated with *int\_const*. Keep this string short; otherwise, NightTrace may be unable to display it in the limited window space available. Use a \n for a newline, not a carriage return in the middle of the string.

The optional *default item line* associates all other integer values (those not explicitly referenced) with a single string.

### TIP

If your table needs only one entry, you may omit the item line and supply only the default item line. A get\_string() call with this table name as the first parameter needs no second parameter.

NightTrace returns a string of the item number in decimal if:

- there is no default item line, and the specified item is not found
- the string table is not found (The first time NightTrace cannot find a particular string table, NightTrace flags it as an error.)

The following lines provide an example of a string table in a configuration file.

```
string_table (curr_state) = {
  item = 3, "Processing Data";
  item = 1, "Initializing";
  item = 99, "Terminating";
  default_item = "Other";
};
```

In this example, your application logs a trace event with a numeric argument that identifies the current state (curr\_state). This argument has three significant values (3, 1, and 99). When curr\_state has the value 3, the NightTrace display shows the string "Processing Data." When it has the value 1, the display shows "Initializing." When it has the value 99, the display shows "Terminating." For all other numeric values, the display shows "Other."

For more information on string tables and the get\_string() function, see page 15-172.

## **Pre-Defined Strings Tables**

The following string tables are pre-defined in NightTrace:

event

pid

The event string table is a dynamically generated table which contains all trace event names.

This table is indexed by an event code or an event code name. Examples of using this table are:

```
get_string(event, 4306)
get_item(event, "IRQ_EXIT")
```

A dynamically generated string table internal to NightTrace. In user tracing, it associates global process ID numbers with process names of the processes being traced.

## NOTE

When analyzing trace event files from multiple systems, process identifiers are not guaranteed to be unique across nodes. Therefore, accessing the pid table may result in an incorrect process name being returned for a particular process ID. To get the correct process name for a process ID, the pid table for the node on which the process identifier occurs should be used instead. The pid table is maintained for backwards compatibility.

This table is indexed by a process identifier or a process name. Examples of using this table are:

```
get_string(pid, pid())
get_item(pid, "ntraceud")
```

tid

A dynamically generated string table internal to NightTrace. In user tracing, it associates NightTrace thread ID numbers with thread names.

This table is indexed by a thread identifier or a thread name. Examples of using this table are:

```
get_string(tid, tid())
get item(tid, "cleanup thread")
```

boolean

A string table which associates 0 with false and all other values with true.

```
name pid
```

A dynamically generated string table internal to NightTrace. It maps all known node ID numbers (which are internally assigned by NightTrace) to the name of the node's process ID table).

This table is indexed by a node identifier or a node name. Examples of using this table are:

```
get_string(name_pid, node_id())
get_item(name_pid, "system123")
```

Consider the following example:

```
get_string(get_string(name_pid,node_id()),pid)
```

The nested call to <code>get\_string(name\_pid,node\_id())</code> returns the name of the process ID table on the system where this trace point was logged. We then index that table with the current process ID (since processes IDs are guaranteed to be unique when analyzing mutipile trace event files obtained from multiple systems) to obtain the name of the current process.

## **NOTE**

The predefined process\_name() function is equivalent to the expression above - and much simpler to write! (See "process\_name()" on page 15-54 for more information.)

```
name_tid
```

A dynamically generated string table internal to NightTrace. It maps all known node ID numbers (which are internally assigned by NightTrace) to the name of the node's thread ID table).

This table is indexed by a node identifier or a node name. Examples of using this table are:

```
get_string(name_tid, 1)
get_item(name_tid, "charon")
```

node\_name

A dynamically generated string table internal to NightTrace. It associates node ID numbers (which are internally assigned by NightTrace) with node names.

This table is indexed by a node identifier or a node name. Examples of using this table are:

```
get_string(node_name, node_id())
get_item(node_name, "gandalf")
```

vararg functions

This table is generated by **nlight** (see "Application Illumination" on page 4-1). It identifies functions that have variable numbers of arguments.

The table is indexed by the trace ID value of the function's ENTRY\_ event and returns the string "true" for functions have have variable numbers of arguments and "false" otherwise. Vararg functions do not have any RETURN\_ events associated with them (see "Limitations" on page 4-5 for more information).

You can use pre-defined string tables anywhere that string tables are appropriate. Use the get\_string() function to look up values in string tables.

#### **Format Tables**

Like string tables, *format tables* let you associate an integer value with a character string; however, in contrast to a string table string, a format table string may be dynamically formatted and generated. Labeling numeric values with text can make the values easier to interpret.

The syntax for a format table is:

```
format_table ( table_name ) = {
    [ index_type = "event"; ]
    item = int_const, "format_string" [ , "value1" ] ...;
    ...
    [ default_item = "format_string" [ , "value1" ] ...; ]
};
```

Include all special characters from the syntax except the ellipses (...) and square brackets ([]).

The fields in a format table are:

```
format_table
```

The keyword that begins the definition of all format tables.

table\_name

The unique, user-defined name of this table. This name describes the relationship of the numeric values in this format table.

An *index\_type* of "*event*" may be specified to direct **ntrace** to use this table to format events and their arguments. More than one table may have the *event* index\_type.

An *item line* associates a single integer value with a character string. This line extends from the keyword item through the ending semicolon. You may have any number of item lines in a single format table.

The fields in an item line are:

item

The keyword that begins all item lines.

int\_const

An integer constant that is unique within *table\_name*. This value may be decimal, octal, or hexadecimal. Decimal values have no special prefix. Octal values begin with a zero (0). Hexadecimal values begin with 0x.

format\_string

A character string to be associated with *int\_const*. Keep this string short; otherwise, NightTrace may be unable to display it in the limited window space available. Use a \n for a newline, not a carriage return in the middle of the string.

The string contains zero or more conversion specifications or display formats. Valid conversion specifications for displays include the following:

%i

Signed integer

%u

Unsigned decimal integer

%d

Signed decimal integer

%0

Unsigned octal integer

٧х

Unsigned hexadecimal integer

%lf

Signed double precision, decimal floating point

%е

Signed decimal floating point, exponential notation

%C

Single character

```
%s
Character string
%%
Percent sign
```

Newline

For more information on these conversion specifications, see printf(3).

format\_string may contain any number of conversion specifications. There is a one-to-one correspondence between conversion specifications and quoted values. A particular conversion specification-quoted value pair must match in both data type and position. For example, if format\_string contains a %s and a %d, the first quoted value must be of type string and the second one must be of type integer. If the number or data type of the quoted value(s) do not match format\_string, the results are not defined.

value1

A value associated with the first conversion specification in *format\_string*. The value may be a constant string (literal) expression or a NightTrace expression. A string literal expression must be enclosed in double quotes. An expression may be a get\_string() call (see page 15-172). For more information on expressions, see "Using Expressions" on page 15-1.

The optional default\_item line associates all other integer values with a single format item. NightTrace flags it as an error if an expression evaluates to a value that is not on an item line and you omit the default item line.

#### TIP

If your table needs only one entry, you may omit the item line and supply only the default item line. A get\_format() call with this table name as the first parameter needs no second parameter.

The following lines provide an example of a string table and format table in a configuration file.

In this example, the first numeric argument associated with a trace event represents the current state (curr\_state), and the event\_info format table represents information associated with the trace event IDs. When trace event 186 occurs, a get\_format(event\_info,186) makes NightTrace display:

```
Search for the next time we process data
```

When trace event 25 occurs, NightTrace replaces the conversion specification (%s) with the result of the get\_string() call. If arg1() has the value 1, then NightTrace displays:

```
The current state is Initializing
```

When trace event 999 occurs, NightTrace replaces the first conversion specification (%s) with the result of the get\_string() call and replaces the second conversion specification (%d) with the integer result of the numeric expression offset(). If arg(1) has the value 99 and offset() has the value 10, then NightTrace displays:

```
Current state is Terminating, current trace event is 10
```

For all other trace events, NightTrace displays "Other".

For more information on get\_string(), see "get\_string()" on page 15-172.

For more information on format tables and the get\_format() function, see "get\_format()" on page 15-176.

For more information about arg1(), see "arg()" on page 15-22.

For more information about offset(), see "offset()" on page 15-50.

## **Session Configuration Files**

A session configuration file defines a NightTrace session.

### NOTE

NightTrace remembers the last session loaded or saved on a per-user basis. To simplify restarting NightTrace at another time to analyze the same data, the usage of the **--use-session** (**-u**) command line option (see "-u --use-session" on page 6-4) is strongly encouraged to invoke NightTrace with the last session loaded or saved.

A session configuration may include:

· daemon definitions

See "Edit Daemon Definition" on page 8-8 for more information.

• display page configurations

See "Table Files" on page 6-12 for more information.

- string tables
  - event names specified for user event IDs
  - any user-defined string tables
  - any modifications to default NightTrace string tables, or string tables embedded in trace data files
- profiles of conditions and states

See "Using Expressions" on page 15-1 for more information.

named tags

See "Tags List Panel" on page 14-1 for more information.

- previously-executed searches
- previously-executed summaries
- references to saved trace data segment files

See "Trace Data Segments" on page 6-22 for more information.

• references to user trace files generated by **ntraceud** (see "The ntraceud Daemon" on page 3-1), or a user daemon defined in the GUI (see "Daemons Panel" on page 8-1)

Session configuration files can be generated by the following menu items in the File menu of the NightTrace Main Window:

Upon exiting when there are unsaved changes to the session, the user is given the chance to save the changes before NightTrace exits.

The user may load the session on a subsequent invocation of NightTrace by either:

- specifying the session configuration filename on the command-line when invoking **ntrace** (see "Invoking NightTrace" on page 6-1)
- using the Load Session dialog to open the session configuration file from the NightTrace Main Window

# **Trace Data Segments**

Trace data segments are conglomerations of all trace data saved in a much more efficient format than raw trace event files providing for faster initialization at startup.

Trace data segments are saved using the Save Trace Data button on the Trace Segments panel (see "Trace Segments Panel" on page 9-1 for more information).

# The NightTrace Main Window

The NightTrace GUI is invoked using **ntrace** (see "Invoking NightTrace" on page 6-1). By default, the NightTrace main window is presented as shown in the figure below.




Figure 7-1. NightTrace Main Window

The NightTrace main window consists of the following components:

- Menu Bar
- Toolbars
- Pages and Panels

## Menu Bar

The menu bar provides access to session configuration services, additional tools, and help. The menu bar provides the following menus:

- File
- View
- Daemons
- Search
- Summary
- Profiles
- Timelines
- Tools
- Help

Each menu is described in the sections that follow.

## File

Accelerator: Alt+F

The File menu contains session-related items such as initiating a new *session*, saving the current session, and opening a previously-saved session or data file.

A session includes daemon configurations, trace data sets, configuration options, display pages, and user-defined profiles.




Figure 7-2. File Menu

The following paragraphs describe the options on the File menu in more detail.

#### **New Session**

Mnemonic: N

Creates a new session.

If an existing session is open, it is first closed by this operation.

If changes have been made to the current session but have not yet been saved, Night-Trace will ask you if you wish to save the current session before proceeding.

#### Load Session...

Mnemonic: L

This option launches a standard file selection dialog which allows you to specify a previously-saved session file. Filenames displayed in the file selection dialog are relative to the host system.

If changes have been made to the current session but have not yet been saved, Night-Trace will ask you if you wish to save the current session before proceeding.

## **NOTE**

NightTrace will automatically load the last session used when invoked with the **-u** option. See "Invoking NightTrace" on page 6-1 for more information.

#### Save Session

Mnemonic: S
Accelerator: Ctrl+S

Save Session saves the current session to a session configuration file.

Save Session allows for quickly saving a session. The user is not prompted for the filenames where the session, trace data, or display pages are to be saved. These are automatically saved in appropriately named files in the current working directory.

If the current session has not been saved to a file in the past, the session is automatically saved to a new session configuration file. The new filename appears in the window title.

If the current session was loaded from or previously saved to a session configuration file, the session is saved to that file.

Trace data that has been *touched* is saved by Save Session. Touched trace data includes trace data modified by discarding events. In addition, trace data from a trace data segment file where one or more segments have been saved to another trace data segment file or closed is saved.

If the trace data was loaded from a previously saved trace data segment file, the data is saved to that file. If the trace data has never been saved to a trace data segment file, the data is automatically saved to a newly created trace data segment file

If the display pages were loaded from a previously saved display page file, the page is saved to that file.

If the display page has never been saved to a display page file, the page is automatically saved to a newly created display page file.

#### Save Session As...

Mnemonic: A

This option launches a standard file selection dialog which allows you to specify the a filename where the session will be saved. Filenames displayed in the file selection dialog are relative to the host system.

### **Save Session Copy**

Mnemonic: C

Save Session Copy saves the current session to a newly created session configuration file (see "Session Configuration Files" on page 6-21 for a complete description of the contents of a session).

In addition, all trace data and display pages are saved to new file names using a common session file name prefix.

Save Session Copy allows for quickly saving one or more copies of a session at certain stages. The user is not prompted for the filenames where the session, trace

data, or display pages are to be saved. These are saved in appropriately named files in the current working directory.

#### Preferences...

Mnemonic: F

This option launches the Preferences Dialog which allows you to specify preferences for NightTrace, including font selection.

Saved user preferences are applied to all NightTrace invocations for the user. Preferences are saved in the user's home directory and have a broader application than session configuration files.

See "Preferences Dialog" on page 7-41 for more information.

## Open Files...

Mnemonic: O

Accelerator: Ctrl+O

Presents the user with a standard file selection dialog so that they may select a trace event file, event map file, or configuration file to load.

The trace event file can be a user trace data file. See "Trace Event Files" on page 6-9 for more information.

An event map file provides ASCII names for specific trace event values. See "Event Map Files" on page 6-9 for more information.

Configuration files contain string and format tables as well as display page definitions. See "Table Files" on page 6-12 for more information.

## **Close All Trace Data**

Mnemonic: D

Accelerator: Alt+W

Closes the trace data segments currently selected in the Trace Segments area. The events associated with the closed segments are immediately removed from the current data set being analyzed.

Data segments that were not associated with a trace file and that have not yet been saved will be lost when closed.

## **Exit**

Mnemonic: X

Accelerator: Ctrl+Q

Closes the session and exits NightTrace completely.

If changes have been made to the current configuration but have not yet been saved, NightTrace will ask you if you wish to save the session before proceeding.

## **Exit Immediately**

Mnemonic: I

Accelerator: Alt+Q

Closes the session and exits NightTrace without prompting to save changes that have been made. Any changes will be lost.

## **View**

Accelerator: Alt+V

The View menu allows you to add, rename, or delete pages and controls which panels in pages are visible.




Figure 7-3. View Menu

## **Add Page**

Mnemonic: A
Accelerator: Ctrl+A

This option adds a new page to the right of the last page in the main window.

## Rename Current Page...

Mnemonic: R

This option launches a dialog that allows you to change the name of the current page. The current page is the page which is currently being displayed in the main window.

This option is also available from the context menu which appears when you right-click on a page's tab.

## **Delete Current Page**

Mnemonic: D

This option deletes the current page and all panels it contains. The current page is the page which is currently being displayed in the main window.

This option is also available from the context menu which appears when you right-click on a pages's tab.

## **Toolbars**

Mnemonic: B



## Figure 7-4. Toolbars Menu

This menu allows you to hide or show individual Toolbars on the main window. You can also hide or show toolbars using the context menu that appears when you right-click a toolbar.

#### **Events**

This checkbox controls whether the Events panel is displayed. See "Events Panel" on page 10-1 for information its operation.

#### **Daemons**

This checkbox controls whether the Daemons panel is displayed. See "Daemons Panel" on page 8-1 for information on its operation.

## **Trace Segments**

This checkbox controls whether Trace Segments panel is displayed. See "Trace Segments Panel" on page 9-1 for information on its operation.

## **Event Descriptions**

This checkbox controls whether the Event Descriptions panel is displayed. See "Event Descriptions Panel" on page 13-1 for information on its operation.

## **Tags List**

This checkbox controls whether the Tags List panel is displayed. See "Tags List Panel" on page 14-1 for information on its operation.

#### **Timelines and Panels**

When timelines or other panels are added, an entry for each is added to the View menu. These entries are checkboxes which toggle the visibility of the panel in the current page.

# **Daemons**

Accelerator: Alt+D

The Daemons menu provides functionality for configuring new and existing daemon definitions, as well as attaching to and detaching from running daemons.




Figure 7-5. Daemons Menu

This menu is identical to the context menu shown when right-clicking inside the Daemons panel, as described in "Daemons Panel" on page 8-1.

# Search

Accelerator: Alt+R

The Search menu contains search-related items such as opening the Profile Definition panel to define search criteria, executing a forward or backward search with the most recent search criteria, or modifying search options.

Text Search	Ctrl+T
Change <u>S</u> earch Profile	Ctrl+F
Search Backward	Ctrl+B
Search Forward	Ctrl+G
Search Backward within Timeline Interval	Alt+B
Search Forward within Timeline Interval	Alt+G
Goto Next Tag     Got	]
Goto Previous Tag	[
⇒ Go Back to Previous Interval	Ctrl+V
<u>☞ G</u> oto	Ctrl+I
© Goto <u>First Event</u>	Alt+Left
Goto Last Event	Alt+Right
🕱 Ask Before Wrapping for Search	
<u>Z</u> oom to Search Match	

Figure 7-6. Search Menu

## **Text Search**

This option launches the Search Events for Text dialog which allows you to specify textual search criteria for searching the contents of an Events panel. See "Text Search" on page 10-3 for a description of this dialog and its actions.

# Change Search Profile...

Mnemonic: S

Accelerator: Ctrl+F

Displays the Profiles dialog allowing you to define the search criteria and to execute a search for an event or condition in a Timeline panel. See "Profiles Dialog" on page 12-2 for more information.

#### **Search Forward**

Mnemonic: R

Accelerator: Ctrl+G

Executes a forward search using the last profile defined or selected. If no profiles have been defined, a forward search for the next event is executed.

# Search Backward

Mnemonic: K

Accelerator: Ctrl+B

Executes a backward search using the last profile defined or selected. If no profiles have been defined, a backward search for the previous event is executed.

#### Search Forward withinTimeline Interval

Accelerator: Alt+G

Executes a forward search using the last profile defined or selected. If no profiles have been defined, a forward search for the next event is executed. The search is bounded by the events in the current timeline interval.

#### Search Backward within Timeline Interval

Accelerator: Alt+B

Executes a backward search using the last profile defined or selected. If no profiles have been defined, a backward search for the previous event is executed. The search is bounded by the events in the current timeline interval.

# Goto Next Tag Goto Previous Tag

Mnemonics: ] and [

These options search forward or backward, respectively, to the next or previous tagged event or time in the data set.

## Go Back to Previous Interval

Accelerator: Ctrl+V

This option toggles the current timeline between its current position and its last position. Using this option or accelerator, you can easily revert back to a location in the data set after executing a search or clicking elsewhere in a timeline or ruler.

#### Goto...

Mnemonic: G
Accelerator: Ctrl+l

This option launches the Change Interval dialog which allows you to change the current time and boundaries of the current interval.





Figure 7-7. Change Interval Dialog

The Change Interval dialog is launched from the Goto... option of the Search menu. It is also launched whenever you click on any of the values in the interval value boxes in the lower-left corner of a timeline,



as shown in the picture above (highlighted with a reddish background).

The dialog allows you to enter values as event offsets or times. Values entered in floating-point notation are interpreted as times, as are values with a trailing S character (meaning seconds). Integer values without a trailing S character are interpreted as event offsets.

In most situations, you should change at most one or two of the values in the dialog, and let NightTrace adjust the unmodified values for you when you press OK; in order to accommodate your specifications.

For example, if you simply change the Interval End setting to a larger number, NightTrace will expand the Interval Span (and change the Current timeline value if necessary) when you press OK.

The dialog was designed for quick access and use. For example, to change the current timeline to time 3.5s, you could use the following 6 keystrokes when a timeline panel has focus (the keystrokes are separated by whitespace for clarity below):

Ctrl+I 3 . 5 s Enter

When the dialog is launched via the menu or accelerator sequence, the Current time value is fully selected so that it will be replaced immediately with whatever characters you type. The OK button has the activation focus, so that hitting the Enter key activates the OK button.

When the dialog is launched by clicking on one of the actual values that define the interval in the lower-left corner of a timeline (see picture above), the value that you clicked on is fully selected in the dialog, ready for immediate substitution.

#### **Goto First Event**

Mnemonic: F

Accelerator: Alt+LeftArrow

This option searches to the first event in the data set.

#### **Goto Last Event**

Mnemonic: L

Accelerator: Alt+Right

This option searches to the last event in the data set.

## Ask Before Wrapping for Search

When checked, this causes a dialog to pop up when either end of the data set is reached during a search operation; it allows you to continue searching at the other end or to cancel the search.

#### **Zoom to Search Match**

When checked and a search criteria is found, the timeline is zoomed to include the number of events specified by the Limit Number of Events Displayed... option of the Timelines menu.

# Summary

Accelerator: Alt+U

The Summary menu provides for defining profiles for summaries, executing summaries, and controlling summary options.




Figure 7-8. Summary Menu

# Change Summary Profile...

Mnemonic: U

Accelerator: Ctrl+U

This option opens the Profiles dialog allowing you to select a profile to summarize or define a new profile to summarize. See "Profiles" on page 12-1 for more information.

## **Summarize**

Mnemonic: Z

Accelerator: Ctrl+Z

This option executes a summary on the current profile. If no profiles have been defined, a summary of all events is executed. For each summary of a specific profile, a new page is created to hold the summary results, including any required data graphs as directed by the Graph State Durations... or Graph State Gaps... options of the Summary menu.

#### **Summarize within Timeline Interval**

Mnemonic: I

Accelerator: Alt+Z

This option is identical to the Summarize option except that the list of events to summary is constrained by those in the current timeline interval.

## **Summarize Functions**

Mnemonic: F

This option executes a summary on Application Illumination data to summarize the occurrences of all function calls and returns associated with such data. It presents the data in a table in a panel which shows you the number of calls and the minimum, maximum, and average duration times.

This menu option requires that you have used **nlight** to instrument code with such trace events. See "Application Illumination" on page 4-1 for more information.

The following figure illustrates such a summary:




Figure 7-9. Summarize Function Results

The table headings are mostly self explanatory, except for the Active column. This value indicates whether the call was still active and the end of the trace data set (or interval if summarizing only part of the data set).

Right-clicking on a row in the table launches the following context menu:




Figure 7-10. Summary Functions Table Context Menu

Selecting Launch detailed summary of calls for this function generates a table with each row representing a single call for the currently selected function, as shown in the following figure:




Figure 7-11. Function Call Details Table

Both tables are sortable; click on the heading of interest to sort. Click again to change the sort direction.

Both tables have context menus that allow you to set the current timeline to a value associated with the selected row, and to save the table in textual format to a file.

## **Summarize Functions within Timeline Interval**

Mnemonic: U

This option is identical to the Summarize Functions option except that the list of events to summary is constrained by those in the current timeline interval.

## **Graph State Durations...**

Mnemonic: D

This option displays the Graph State Durations dialog which allows you to select whether you want a data graph generated when summarizing the current profile. The data graph shows the individual durations of each instance of the state as defined by the profile, plotted vertically.

The dialog also allows you to specify a standard deviation value which instructs the summary action to graph values that fall outside the specified domain as the maximum defined by that domain.

# Graph State Gaps...

Mnemonic: G

This option is identical to the **Graph State Durations** option except that it controls the graphing of the gaps between instances of states as defined by the current profile.

Prevents the current timeline from being moved, but the summary results are still displayed in page text areas.

# **Profiles**

Accelerator: Alt+P

The Profiles menu manipulates the list of profiles shown in the Profile Status List area of the Profiles dialog.

A profile is a set of criteria either defining a state with beginning and end conditions, or simply a condition. Profiles are used for searches, summaries, and graphs.




Figure 7-12. Profiles Menu

## New Profile...

Mnemonic: N

Accelerator: Ctrl+P

This option shows the Profiles dialog to allow you to create a new profile. See "Profiles Dialog" on page 12-2 for more information on using profiles.

# **Delete**

Mnemonic: D

This menu choice deletes all profiles currently selected in the Profile Status List area of the Profiles dialog.

## Move Up Move Down

Accelerator: Ctrl+UpArrow and Ctrl+DownArrow

These options move the currently selected profiles in the Profile Status List in the Profiles dialog towards the beginning or end of the list, respectively.

## **Export to API Source...**

This option opens the Export Profiles to NightTrace API Source File dialog to automatically generate source code defining and referencing profiles, for use with applications using the <u>NightTrace Analysis API</u> (see "Using the NightTrace Analysis API" on page 16-1).

## **String Tables**

This option expands to a sub-menu which allows you to select an existing string table for modification, or to create a new string table.

### **Format Tables**

This option expands to a sub-menu which allows you to select an existing format table for modification, or to create a new format table.

# **Export Profiles to NightTrace API Source File**

The Export Profiles to NightTrace API Source File dialog is presented when the Export to API Source... menu item is selected from the Profiles menu.




Figure 7-13. Export Profiles Dialog

This dialogs generates C source code using the NightTrace Analysis API to define and install listener callback functions for the profiles selected from the Profile Status List area of the Profiles dialog when the dialog was launched.

## Define main() function

When checked, this option generates source code for a main C program which creates an instance of the Analysis API and installs all definitions and callbacks selected in this dialog.

#### Define callback functions

When checked, this option generates stub routines for all callback functions that are defined by this dialog. The stub routines are empty unless the Include default printf() output in callbacks option is checked. If this option is not checked, the function profiles are still generated, but no definitions are generated.

## Default printf()'s in callbacks

When checked, this option generates source code to print information about instances of the selected profiles in the callback function definitions.

## Report analysis API errors

When checked, this function will report all errors from API calls to stderr; otherwise, errors are ignored.

#### Read trace data from stdin

This option controls the initial API calls which either open a pre-existing data file or read data from stdin in streaming mode.

#### State start callbacks

When checked, a callback profile is generated and registered with the API for the start event of the selected state profiles.

## State end callbacks

When checked, a callback profile is generated and registered with the API for the end event of the selected state profiles.

#### State active callbacks

When checked, a callback profile is generated and registered with the API for any event that occurs when selected state profiles are active.

#### State inactive callbacks

When checked, a callback profile is generated and registered with the API for any event that occurs when selected state profiles are inactive.

#### **Trace Data File**

When Read trace data from stdin is not checked, this text field defined the data file from which pre-existing data will be read.

#### **Profiles Source**

This text area defines the name of the source file for all source code generated except for callback definitions.

## **Callbacks Source**

This text area defines the name of the source file for all source code that define callback routines.

By default, the dialog is set to create a fully functional program that you can compile and link using a command similar to the following:

```
cc export_analysis_0.c -lntrace_analysis
```

You could subsequently feed live NightTrace data to the program using an invocation similar to the following:

```
ntraceud --stream /tmp/key-file | ./a.out
```

See "Using the NightTrace Analysis API" on page 16-1 for more information.

# **Timelines**

Accelerator: Alt+M

The Timelines menu allows to create new timeline panels and provides controls for moving and changing timeline intervals.




Figure 7-14. Timelines Menu

The Timelines menu in the main window menu bar is essentially identical to the context menu available from all Timeline panels, with the addition of the New submenu which allows you to create new timelines.

This section will describe the New sub-menu.

## New

Mnemonic: N

#### **Custom Kernel Timeline...**

Mnemonic: K

Presents the Build Custom Kernel Page dialog to quickly build a customized kernel page based on choices of nodes, CPUs, and graphs. When loading kernel trace events in NightTrace, default kernel display pages are displayed for each node where trace data originated. These pages show each CPU for each node, as well as a fixed number of graphs and data boxes per CPU.

However, there may be cases where the default display page for kernel data is not desirable:

- on multi-CPU nodes, the vertical height of the default kernel page may be too large
- when shielding a CPU, or running a process with a CPU bias, it may be desirable to see only data for that CPU
- one or more of the default graphs per CPU may not be of interest




Figure 7-15. Create Custom Kernel Timeline Dialog

The checkboxes allow you to select which event and state graphs you wish to build for which CPUs.

The checkboxes allow you to select which event and state graphs you wish to build for which CPUs.

The Options area of the dialog provides additional tailoring choices, especially useful when you have 8 or more CPUs to view.

The Zoom Factor specifies the percentage of the default kernel timeline geometry that should be used in creating the new page. For most monitors, a kernel timeline for 8 CPUs doesn't fit vertically in the visible area of the display (although the timeline does have a scroll bar so you can scroll to see all CPUs). Selecting a percentage less than 100% may be useful in such a situation.

The Zoom to fill panel checkbox tells NightTrace to automatically calculate the Zoom Factor so that all the CPUs will fit in the available vertical space of screen. NightTrace calculates the available space based on the current size of the NightTrace main window. For best results, increase the size of the NightTrace main window (or maximize the window to fill the entire screen) before creating the custom timeline.

The Zoom to fill panel checkbox disables and overrides the Zoom Factor setting, because it automatically calculates the setting when creating the timeline.

The Widescreen checkbox splits the kernel timeline in half, creating two columns of CPUs. You can select the Widescreen option as well as a zoom option.

#### Per Process Kernel Timeline...

Mnemonic: P

Presents a list of processes in the current kernel data set which allows you to quickly build a customized kernel timeline that is filtered to display specific processes.

#### **NOTE**

Support for kernel tracing is only available under some operating system distributions. See "Kernel Dependencies" on page B-1 for more information.

# **Empty Timeline**

Mnemonic: T

This menu choice opens a new timeline so that the user may configure it from scratch. The grid must be populated with display objects before trace information can be analyzed or graphically examined. See "Timeline Panels" on page 11-1.

## **Default User Timeline**

Mnemonic: U

This menu choice opens the default user timeline which is automatically pre-configured to show all user events and specific descriptions of the event ID and the first argument of each event.

The default user timeline includes a row that includes events for each registered thread in the application, as well as a row that includes events for all threads.




Figure 7-16. Default User Timeline

Mnemonic: A

#### Default Al Timeline...

Mnemonic: I

This menu choice opens the default Application Illumination timeline. This is essentially a single-thread version of the default timeline, but with bigger hover and descriptive areas, as Application Illumination event descriptions tend to be verbose.

See "Application Illumination" on page 4-1 for more information.

#### **CUDA**

Mnemonic: C

This menu choice opens a sub-menu with the following choices.

Default CUDA AI Timeline:

Mnemonic: A

A CUDA AI timeline is much like a normal AI timeline, except that information is included that relates to use of the NVIDIA CUDA API and the execution of CUDA kernels. See "Default CUDA AI Timeline" on page 11-22 for a complete description.

## Default CUDA GPU Timeline:

Mnemonic: G

This presents a timeline that focuses on trace events that were logged from code executed by an NVIDIA GPU. See "Default CUDA GPU Timeline" on page 11-23 for a complete description.

## Limit Number of Events Displayed...

This option launches a simple dialog which allows you to set a display limit, in units of events. This limit is consulted when doing search operations and when using the Zoom In to Limit action.

#### Zoom

Mnemonic: Z



Figure 7-17. Zoom sub-menu of Timelines Menu

## Zoom In

Mnemonic: I
Accelerator: =

Change the current interval such that fewer events are displayed, but with more detail.

The amount the interval changes is dependent on whether or not you have selected events in a timeline.

If you use the mouse to click-and-drag to select events in a timeline, then the Zoom In action will change the interval to include only the events you have selected.

Otherwise, a Zoom In action will change the interval by the Zoom Factor.

#### Zoom In to Limit

Mnemonic: L

Accelerator: Alt+Down, Alt+=

Change the current interval by zooming in to the smallest interval as defined by the Limit Number of Events Displayed... menu setting described above.

The Alt+Down accelerator is affected by the Zooming Control preferences. Depending on your preference setting, Alt+Down may actually zoom fully out. See "Zooming Controls" on page 7-42 for more information.

#### **Zoom Out**

Mnemonic: O Accelerator: -

Change the current interval such that more events are displayed, but with less detail. The change in interval is controlled by the Zoom Factor.

#### **Show All Events**

Mnemonic: A

Accelerator: Alt+Up

Change the current interval by zooming all the way out such that the interval contains the entire data set. When fully zoomed out, the display isn't useful for detailed analysis, but it is useful for identifying areas of significant activity, etc.

The Alt+Up accelerator is affected by the Zooming Control preferences. Depending on your preference setting, Alt+Up may actually zoom fully in. See "Zooming Controls" on page 7-42 for more information.

#### Set Zoom Factor...

Mnemonic: F

This menu option launches a simple dialog which allows you to change the Zoom Factor. The Zoom Factor is a floating point number which represents the change in interval when incremental zoom actions are taken.

Thus a zoom factor of 2.0 will cause roughly twice as long an interval to be displayed after a single zoom out action, and 1/2 as long an interval to be displayed after a zoom in action.

Changing the Zoom Factor preference in the Preferences dialog will change this setting. See "Zooming Controls" on page 7-42 for more information.

#### **Shift Left**

Mnemonic: L

Accelerator: Ctrl+Left

Shift the current interval "left", so that the interval now includes earlier times. The amount the interval changes is controlled by the Interval Shift setting, which you can set via the Shift Percentage... menu option.

By default, the Interval Shift setting is 25%, so that when you shift an interval left (or right), the new interval still includes 75% of the time covered by the previous interval. This can be helpful when you want to maintain some context while traversing the data set.

## **Shift Right**

Mnemonic: R

Accelerator: Ctrl+Right

Shift the current interval "right", so that the interval now includes later times. The amount the interval changes is controlled by the Interval Shift setting, which you can set via the Shift Percentage... menu option.

By default, the Interval Shift setting is 25%, so that when you shift an interval right (or left), the new interval still includes 75% of the time covered by the previous interval. This can be helpful when you want to maintain some context while traversing the data set.

## Shift Percentage...

Mnemonic: P

This option launches a simple dialog which allows you to change the Interval Shift value. The Interval Shift is a percentage that controls how much the interval changes when you do Shift Left or Shift Right interval options (as described above).

Setting the percentage to 25% will maintain 75% of the current interval's timespan in the new interval. This is useful when you want to maintain some context from the previous view while traversing the data set.

Setting the percentage to 100% will present an entirely new timespan for the next interval (contiguous with the previous interval).

#### **Center Current Timeline**

Mnemonic: C
Accelerator: =

This option adjusts the interval such that the current timeline is centered in the interval.

This option has no effect if there are insufficient events outside the current interval to accommodate the current Interval Span setting. In such circumstances, you should Zoom In sufficiently before selecting this option.

#### Discard Selected...

Mnemonic S

This option discards all events from the data set that are currently selected in the timeline (selection is done using click-and-drag operations with the mouse).

A verification dialog is presented before the events are discarded.

This option is most useful when you have a very large data set and want to concentrate on a small portion of the data and use selection to identify events you want to delete.

In such circumstances, it may be useful to save a copy of your session using the Save Session Copy... option from the File menu before discarding events. The Save Session Copy... option creates a copy of all your session information as well as all the current trace data; thus you can easily revert back to the original data set subsequently.

#### Discard Unselected...

Mnemonic: U

This option discards all events from the data set that are <u>not</u> currently selected in the timeline (selection is done using click-and-drag operations with the mouse).

A verification dialog is presented before the events are discarded.

This option is most useful when you have a very large data set and want to concentrate on a small portion of the data.

In such circumstances, it may be useful to save a copy of your session using the Save Session Copy... option from the File menu before discarding events. The Save Session Copy... option creates a copy of all your session information as well as all the current trace data; thus you can easily revert back to the original data set subsequently.

## **Distinguish Process Name By PID**

Mnemonic: D

This option causes the process names shown in timelines to be distinguished from other processes by appending the Process ID to the name.

# **Edit Current Event Description...**

Mnemonic: E

Accelerator: Ctrl+D

This option launches the Edit Event Description dialog which allows you to define or change the name of an event and its description. See "Edit Current Event Description..." on page 10-4 for a description of that dialog.

# **Tools**

Mnemonic: Alt+L



Figure 7-18. Tools Menu

The following describe the options on the Tools menu:

## **NightProbe Monitor**

Mnemonic: P

Opens the NightProbe Data Monitoring tool. NightProbe is a real-time graphical tool for monitoring, recording, and altering program data within one or more executing programs without significant intrusion. NightProbe can be used in a development environment as a tool for debugging or in a production environment for data capture or to create a "control panel" for program input and output.

## NightSim Scheduler

Mnemonic: S

Opens the NightSim Application Scheduler. NightSim is a tool for scheduling and monitoring real-time applications which require predictable, repetitive process execution. With NightSim, application builders can control and dynamically adjust the periodic execution of multiple coordinated processes, their priorities, and their CPU assignments.

# NightTrace Illuminator

Mnemonic: T

Opens the NightTrace Application Illumination tool, which automatically instruments user application code with trace points that log the entry and exit of functions, with their arguments and return values.

# NightTune Tuner

Mnemonic: U

Opens the NightTune Tuner. NightTune is a graphical tool for analyzing the status of the system in terms of processes, interrupts, context switches, interrupt CPU affinity, processor shielding and hyper-threading control as well as network and disk activity. NightTune can adjust the scheduling attributes of individual or groups of processes, including priority, policy, and CPU affinity.

For systems that support CPU shielding, NightTune provides a handy interface for controlling shielding, including downing sibling hyper-threaded CPUs to avoid interference.

# NightView Debugger

Mnemonic: V

Opens the NightView Source-Level Debugger. NightView is a graphical source-level debugging and monitoring tool specifically designed for real-time applications and multi-threaded applications. NightView can monitor, debug, and patch multiple real-time processes running on multiple processors with minimal intrusion.

# Help

Mnemonic: Alt+H




Figure 7-19. Help Menu

The following describe the options on the Help menu:

#### On Context

Mnemonic: C

Gives context-sensitive help on the various menu options, dialogs, or other parts of the user interface.

Help for a particular item is obtained by first choosing this menu option, then clicking the mouse pointer on the object for which help is desired (the mouse pointer will become a floating question mark when the On Context menu item is selected). The cursor turns to the a circle with a backslash when the item under the cursor has no help description associated with it.

In addition, context-sensitive help may be obtained for the currently highlighted option by pressing the F1 key. NightStar's online help system, will open with the appropriate topic displayed.

## NightTrace User's Guide

Mnemonic: G

Opens the online version of the NightTraceLX User's Guide in the online help viewer.

# NightStar LX Tutorial

Mnemonic: T

Opens the online version of the NightStar LX Tutorial in the online help viewer.

## **License Report**

Mnemonic: T

Opens a license dialog which indicates the current license server and the number of licenses available on the system.

#### On Version

Mnemonic: V

Displays a short description of the current version of NightTrace.

## Check for Updates...

Mnemonic: U

Launches NUU (Network Update Utility) enabling you to update your system with the latest NightStar software. This requires network access to Concurrent's Updates web site. Updates require a login and user ID issued by Concurrent. Refer to <a href="http://redhawk.ccur.com/updates">http://redhawk.ccur.com/updates</a> for complete information. Note that this option is not available on Ubuntu/Debian distributions, in which case **synaptic** should be used to check for NightStar updates.

# **Toolbars**

NightTrace includes four toolbars which can be dragged and placed on any corner or side of the main window. These include:

- the File Toolbar
- the Search Toolbar
- the <u>Daemons</u> Toolbar
- the Panels Toolbar

#### File Toolbar



This toolbar consists of two icons.

## **Open Files**

When pressed, this icon invokes the action associated with the Open Files.... option of the File menu.

#### Save Session

When pressed, this icon invokes the action associated with the Save Session option of the File menu. This icon is disabled if no changes have been made to the current session since it was last loaded or saved.

#### Search Toolbar



This toolbar consists of seven icons.

#### Search Backward

When pressed, this icon searches backward in the data set from the current timeline for the nearest occurrence of the profile selected in the Profile Status List in the Profiles dialog. If no profile is selected, it searches backward for the nearest event.

#### **Search Forward**

When pressed, this icon searches forward in the data set from the current timeline for the nearest occurrence of the profile selected in the Profile Status List in the Profiles dialog. If no profile is selected, it searches forward for the nearest event.

#### Go Back To Previous Interval

When pressed, this icon invokes the Go Back to Previous Interval option of the Search menu, allowing you to switch back and forth between the current timeline and the last value of the current timeline.

# Goto

When pressed, this icon invokes the Goto... option of the Search menu, allowing you to type in an event offset or time of interest.

#### **Goto First Event**

When pressed, this icon changes the current timeline to be the first event in the data set.

# Goto Last Event

When pressed, this icon changes the current timeline to be the last event in the data set.

#### Zoom In

When pressed, this icon causes the time interval to be reduced by the zoom factor set using the Set Zoom Factor... option of the Zoom submenu of the Timelines menu.

#### **Zoom Out**

When pressed, this icon causes the time interval to be increased by the zoom factor set using the Set Zoom Factor... option of the Zoom submenu of the Timelines menu.

### **Summarize**

When pressed, this icon invokes the Summarize option of the Summary menu which operates on the profile currently selected in the Profile Status List in the Profiles dialog. If no profile is currently selected, a summary of all events is executed.

#### **Daemons Toolbar**



This toolbar consists of four icons.

#### Launch

When pressed, this icon launches all daemons currently selected in the Daemons panel.

#### Resume

When pressed, this icon resumes all daemons currently selected in the Daemons panel.

## **Pause**

When pressed, this icon pauses all daemons currently selected in the Daemons panel.

#### Halt

When pressed, this icon halts all daemons currently selected in the Daemons panel.

#### **Panels Toolbar**



This toolbar consists of six icons, representing each of the available panel types in NightTrace. When pressed, the icon toggles the visibility of the corresponding panel in the current page.

#### **Profiles Toolbar**



This toolbar consists of two icons that represent the Profiles Status List and Profile Definition areas of the Profiles dialog. When pressed, the dialog appears and the focus is set in the appropriate area.

# **Pages**

The remaining area of the main window is reserved for various tabbed pages which can contain any of the seven panel types available within NightTrace.

Each page has a tab which contains the page title. When clicked or right-clicked, the page is raised to the top and becomes the current page.

Each tab has a context menu which allows you to manipulate the page position and title.



Figure 7-20. Tab Context Menu

# **Delete Current Page**

Mnemonic: D

This option deletes the current page.

## **Rename Current Page**

Mnemonic: R

This option launches a dialog which allows you to rename the current page.



Figure 7-21. Rename Page Dialog

If the page title contains an ampersand character (&), it causes the next character to be underlined, provides a keyboard shortcut for that page, and the ampersand becomes invisible in the title that is shown for the page. In the example above, the keyboard shortcut for this page will be Alt+4 and the displayed title will become Page 4. Activating the shortcut for a page causes it to be raised to the top and it becomes the current page. Care should be taken when choosing shortcuts for pages so they do not conflict with other shortcuts. If you desire to have an ampersand displayed in the actual page title (as opposed to defining a shortcut), use two ampersand characters, back to back in the Rename Page dialog.

## **Move Current Page**

Mnemonic: M

This option launches a dialog which allows you to reposition the current page among other pages. This option will be disabled unless at least two viewing pages exist.




Figure 7-22. Move Page Dialog

# **Panels**

NightTrace provides flexibility in configuring the graphical user interface to suit your needs through the use of resizable and movable panels.

Consider the following page which contains a Timline panel and an Event List panel:




Figure 7-23. Page with Events and Timeline Panels

Panels are moved by left-clicking the title bar, dragging them to a new location, and then releasing the mouse button. Depending on the location of the panel when the mouse button is released, the panel will either remain detached or will be inserted into the page again.

To detach the panel from the page without inserting it, click the left-most control box in the upper right-hand corner of the panel.




Figure 7-24. Panel Detaches from Page

The Timeline panel detaches from the page and becomes free floating. If moved outside the boundaries of the main window and released, the panel will remain detached from the main window. However, even in detached mode, if the main window is iconified, the detached panel will be iconified with it.

To insert a panel into the page at a new location, drag the panel using the left mouse button on its title bar and move it until it approaches a boundary of the page. NightTrace will respond by creating space indicating where the panel will be inserted.




Figure 7-25. Panel Movement in Progress


The figure above shows space being created above the Events panel as the Timeline panel is dragged towards the upper boundary of the page.

#### **IMPORTANT**

When attempting to move panels inside of a page, if an empty space does not appear where you desire it, try increasing the size of the main window, decreasing the size of the undocked panel, and moving an alternative edge of the undocked panel near where you want to place it.

Panels can be resized by left-clicking on the separator between the panels and dragging it to the desired size.

Another feature of the graphical user interface is the use of tabbed panels. Tabbed panels allow you to maximize your GUI real estate by placing two or more panels in the same location by stacking them on top of each other. You can then raise a panel to the top by clicking on its tab.



To create a tabbed panel, move a panel to the lower horizontal edge of another panel and release.

Figure 7-26. Panels as Tabs


In the figure above, the Timeline panel has been inserted as a tab with the Events panel, conserving space.

## **IMPORTANT**

To move a panel above another panel, move the desired panel to the top boundary of the other panel. If you move a panel to the bottom boundary of another panel, it will become a tabbed panel instead.

The orientation and size of panels within pages is saved as part of a NightTrace session.

# **Preferences Dialog**



The Preferences Dialog is launched via the Preferences... option of the File menu.

Figure 7-27. Preferences Dialog -- General Tab

Preference settings are <u>not</u> saved with session files. They live in a separate file in your home directory: ~/.NightTrace\_prefs.

When you change a preference with this dialog, the change is only applied to the current NightTrace invocation, unless you press the Save button. This allows you to experiment with preference changes without having to commit to them permanently.

# **General Preferences**

The General tab controls preferences for tool tips, timestamp display, zooming controls, tag panel effects, and other miscellaneous behavior.

# **Hover Popups**

These preferences control whether tool tips are displayed when you hover the mouse cursor over items in Event and Timeline panels.

A tool tip is a small notation that appears near the mouse cursor which provides additional information about items near the cursor than what is typically displayed in the panel. This information is normally useful, but some users are distracted by this behavior.

## **Timestamps**

By default, timestamps are displayed as fractional numbers in seconds, with 9 trailing digits so that you can see detail down to the nanosecond. Selecting the Use underscores in timestamp fractions preference causes timestamps to be displayed with underscores in the fractional portion between the digits that separate milliseconds, microseconds, and nanoseconds. This makes it easier to determine relative times between events.

For example:

2.023 121 767 .vs. 2.023121767

# **Zooming Controls**

The traditional controls for zooming in NightTrace are at odds with popular applications; depending on your point of view, the traditional actions make perfect sense to you, or surprise you.

You can select how the Up and Down keys and the mouse wheel affect zooming, using these preferences.

You can also set the default zoom factor which is used for any single zoom in or out action.

# **Tags**

By default, when you select a tag in the tags list panel, the current time changes on all timelines and events panel to the time associated with the selected tag. Clear the Change "Current Time" when selecting a tag in the Tags List panel checkbox to prevent this behavior.

Similarly, by default, when selecting a tag not only does the current time change, but the time interval is restored to the value it had when the tag was created. Clear the Restore time interval span when selecting a tag in the Tags List panel checkbox to prevent this behavior. Of course this preference is meaningless if the current timeline isn't moved when selecting a tag.

#### Miscellaneous

By default, relative pathnames are used in session files. This is handy if you wish to save a session and then send the relevant files to another person for their analysis. If you wish full pathnames to be used, clear the Use relative notation for pathnames in session files checkbox.

# **Timeline Preferences**




Figure 7-28. Preferences Dialog -- Timelines Tab

This tab allows you to define default colors for timelines.

If you want the preferences to apply to existing timelines, be sure to check the Apply to existing timelines box at the bottom of the dialog. Otherwise, the colors are only consulted when you create a new timeline. Once created, you can manually override individual colors using the context menu in a timeline.

#### **Backgrounds**

Here you can set the background color of grids, columns, rulers, locators, data boxes, state graphs, data graphs, and labels. You can also choose to use a graphic image as the background for a timeline grid.

To change colors, type in the hexadecimal RGB code or press the colored bar to the right of the relevant field and select a color from a standard color selection dialog.

## **Kernel and Ada Tasking Timelines**

These areas allow you to define the color used for categories of events and states. The color will be used as the state color and data graph color for such graphs as well as for any text describing instances of these items in labels.

## Restore all color settings to their default values

This button is provided in case your experimentation takes a wrong turn and you end up nauseated. Pressing the button returns all the values to their NightTrace-default state.

# **Font Preferences**

NightTrace uses multiple fonts to present text in the most effective manner throughout the various display areas of the tool.

Variable-width fonts are most commonly used; these fonts most closely resemble how people write or print words.

Fixed-width fonts require that all characters and numbers have the same width (visual footprint). Fixed-width fonts are of benefit when source code is being displayed or manipulated or when columns of numbers are viewed.

NightTrace further divides the use of fonts into the following categories; default, panel, and timeline.

Default fonts are used for text associated with operational description and control, including: menus, buttons, selection devices, labels, tool tips, status bar messages, and generally descriptive verbiage.

Panel fonts are used in NightTrace panels, which display the data of highest importance.

Timeline fonts are used in Event Timelines. Timeline fonts are separated from panel fonts in NightTrace because it may be advantageous to use a small font in timelines where space may be at a premium, especially for kernel display pages on systems with more than a few CPUs.

Fonts are selected by querying font preferences from the following sources until a preference is found:

- Your NightTrace preference
- Your NightStar-wide preference
- The system's NightTrace preference
- The system's NightStar-wide preference
- NightTrace's ultimate default




Figure 7-29. Preferences Dialog -- Fonts Tab

This page is divided into three sections.

## **Global NightStar Fonts**

The Change... button in this area launches the NightStar Global Fonts dialog which allows you to set your Nightstar-wide preferences, your preferences for another specific NightStar tool, or the system's tool or NightStar-wide preferences.

#### Note:

Setting a NightStar preference for the system typically requires root access.

Changes saved in the NightStar Global Fonts dialog are always saved to disk and apply to the current and subsequent NightTrace invocations.

### My NightTrace Fonts

This area allows you to set or clear your user's preferences for NightTrace.

Selection of the checkboxes for the individual font categories control whether or not your preferences are to be consulted. Clearing a checkbox effectively removes your user preference for that category. Setting a checkbox allows you to select specific fonts within the category.

Changes to any of the settings in this area, including individual fonts or category checkboxes, are immediately reflected in the Effective NightTrace Fonts area at the bottom of the page so you can see the ultimate effect a change will have.

To change a specific font, ensure that the corresponding category's checkbox is checked and then press the Change... button. This will launch a standard font selection dialog. When you select a font from the dialog and press OK, the name of the font family is displayed to the left of the Change... button and is displayed in the selected font as well.

## **Effective NightTrace Fonts**

This area shows you the effective fonts that will be used based on your user settings and consultation of global settings which aren't shown in the page.

The values in this area immediately change to reflect the effective font whenever any change is made within the page.

Your changes in the My NightTrace Fonts area are applied to the current invocation of NightTrace when you press the OK button. However, your changes are not saved to disk and will not affect subsequent invocations of NightTrace unless you press the Save button

Separation of Apply and Save operations make it easy to experiment with fonts in the current invocation without affecting long-term usage.

#### Note:

Changes to font preferences in the NightStar Global Fonts dialog are always saved to disk and apply to the current and subsequent NightTrace invocations; i.e. there is no way to experiment with a global font preference without affecting subsequent NightTrace invocations.

The buttons at the bottom of the page control the application of your changes.

## OK

Applies any changes made directly in the Font Preferences page to the current invocation of NightTrace and closes the dialog. The changes will not be saved to disk or affect subsequent NightTrace invocations unless you return to the Preferences... dialog and press Save.

#### Reset

Discards any changes you have made directly to the Font Preferences page since the dialog was launched and resets the dialog accordingly.

#### Note:

Changes made in the NightTrace Global Fonts dialog cannot be discarded via the Reset button.

#### Save

Applies the preferences from the dialog to the current invocation of NightTrace, saves the preferences to disk thereby affecting subsequent NightTrace invocations, and closes the dialog.

## Cancel

Cancels any pending changes and closes the dialog.

## Help

Opens the help system to display this section.

# **NightStar Global Fonts Dialog**

The NightStar Global Fonts dialog allows you to set your Nightstar-wide preferences, your preferences for another specific NightStar tool, or the system's tool or Night-Star-wide preferences.




Figure 7-30. NightStar Global Fonts Dialog

Keep in mind that fonts are selected by querying font preferences from the following sources until a preference is found:

- Your NightTrace preference
- Your NightStar-wide preference
- The system's NightTrace preference
- The system's NightStar-wide preference

#### • NightTrace's ultimate default

This dialog has two control areas which define the scope of font preference application.

## Changes Fonts For...

By default, the dialog is set up to apply font preferences to your user account. Select the Entire System button if you wish to set the system's preferences.

#### Note:

Changing font preference for the system typically requires root access.

### Apply Fonts To...

This area additionally controls the scope of font preference application. You can change a preference for a specific NightStar tool or change the NightStar-wide preference.

If you wish to change the font for more than one tool from this dialog, but not change the NightStar-wide preference, select the first tool of interest, make your preference change in the areas below, and then press the Save button. Then select the second tool of interest and repeat.

## Set Default Fonts Set Panel Fonts Set Timeline Fonts

These areas contain the variable and fixed-width font preferences for each of the font categories, identified by the label next to each checkbox.

To remove the preferences in a category, clear its checkbox.

To change a specific font, ensure that the category's checkbox is checked and then press the Change... button. This will launch a standard font selection dialog. When you select a font from the dialog and press OK, the name of the font family is displayed to the left of the Change... button and is displayed in the selected font as well.

The buttons at the bottom of the page control the application of your changes.

#### Save & Close

Saves any changes made in this dialog to disk, thus affecting subsequent tool invocations, and closes the dialog.

These changes may affect the effective font preferences for the current invocation of NightTrace. When the dialog is closed, the fonts shown in the Effective NightTrace Fonts section of the Preferences dialog are updated. If you apply the changes in that dialog, they will take effect in the current invocation of NightTrace.

#### Save

Applies the preferences from the dialog to the current invocation of NightTrace, saves the preferences to disk thereby affecting subsequent NightTrace invocations.

These changes may affect the effective font preferences for the current invocation of NightTrace. When this dialog is subsequently closed, the fonts shown in the Effective NightTrace Fonts section of the Preferences dialog are updated. If you apply the changes in that dialog, they will take effect in the current invocation of NightTrace.

## Cancel

Cancels any unsaved changes and closes the dialog.

## Help

Opens the help system to display this section.

# **Advanced Preferences**




Figure 7-31. Preferences Dialog -- Advanced Tab

This tab shows advanced preferences.

#### **Trace Data File Cache**

NightTrace has the ability to start tracing daemons on remote systems. When tracing to a file, the file is created on the remote system. After tracing is complete, you can press the Display button on the Daemons panel to load the file into the current NightTtrace session.

If the file is remote, NightTrace consults these preferences to determine the appropriate action.

If the Cache Mode is off, no action will be taken, other than a dialog indicating that your preference prevents NightTrace from downloading the file.

If the Cache Mode is on, then NightTrace will consult the Cache Directory to see if the file already has been downloaded and that the file on the remote system has a matching timestamp. If the file needs to be downloaded NightTrace will do so and place it the specified Cache Directory. Consulting the cache before downloading may seem unusual, but it is helpful when viewing a file which has already been downloaded in a previous session.

If the Cache Mode is temporary, the actions are identical to the on case, except that the file will be deleted when you exit NightView.

Pressing the Delete Cache... button deletes the contents of the Cache Directory.

The Daemons panel provides for the creation and control of user daemons which are used to collect data from user applications and the operating system, respectively.

It is often more convenient to use the Daemons panel to launch and run daemons as opposed to relying solely on the ntraceud command line invocation as described in "Capturing User Events with ntraceud" on page 3-1.

Additionally, the Daemons panel aids in locating user applications that are attempting to log trace data yet have no trace daemons currently associated with them. You can also gain control of a previously-executed command line daemon by using the Attach feature of the Daemons panel.




Figure 8-1. Daemons Panel

All daemons defined in the current session are shown as individual rows in the panel.

Using the buttons at the bottom of the panel, you can control the execution of the daemons as well as bring data into NightTrace Timeline panels for immediate viewing.

# **Context Menu**

The panel's context menu provides a super-set of the activities controlled by the buttons at the bottom of the panel, including the ability to create and edit daemon definitions.




Figure 8-2. Daemons Panel Context Menu

## New Kernel Daemon...

Mnemonic: K

Opens the Edit Daemon Definition dialog (see "Edit Daemon Definition" on page 8-8) allowing the user to configure a new kernel daemon definition.

#### **NOTE**

Support for kernel tracing is only available on some operating system distributions. See "Kernel Dependencies" on page B-1 for more information.

#### New User Daemon...

Mnemonic: U

Opens the Edit Daemon Definition dialog (see "Edit Daemon Definition" on page 8-8) allowing the user to configure a new user daemon definition.

#### Import...

Mnemonic: I

Presents a dialog which lists all user applications on the target system that are attempting to log trace data but that do not currently have user daemons associated with them.




Figure 8-3. Import Daemon Definitions Dialog

Each application that has called trace\_begin(), but that does not yet have a daemon, is listed in a row in the table.

The table includes the Process ID, Program name, User, and the name of the Key File as passed to trace\_begin().

To import any daemon configuration information specified by the user application (the second parameter to trace\_begin()), click the row of interest and press the Import Selected button.

This causes a daemon definition to be automatically created and the Edit Daemon Definition dialog is launched so you can make any required adjustments, as described in "Edit Daemon Definition" on page 8-8.

#### Attach...

Mnemonic: A

Allows the user to query any target system for user application trace daemons and displays the results in a dialog.




Figure 8-4. Attach to Running Daemons Dialog

The user may then attach to the desired daemon and control it, by selecting a daemon from the list and pressing the Attach to Selected button.

A daemon definition is created for the daemon and it is added to the list of daemons in the panel.

## Properties...

Mnemonic: O

Opens the Edit Daemon Definition dialog (see "Edit Daemon Definition" on page 8-8) allowing the user to configure the currently selected daemon.

### **Delete**

Mnemonic: D

Deletes the daemon definition currently selected in the panel.

### Launch

Mnemonic: L

Starts execution of the daemon(s) currently selected in the panel.

#### **NOTE**

Starting a daemon does not imply that the daemon begins to collect events.

Launch operations are time consuming and involve possibly connecting to a target system, user authentication, etc. Once the daemon is launched, it is more efficient to utilize the Pause and Resume operations which require less time and resources.

#### Resume

Mnemonic: R

Resumes execution of the daemon(s) currently selected in the panel. Once resumed, incoming events are placed into the daemon buffer for subsequent processing by the daemon.

#### **Pause**

Mnemonic: P

Pauses the execution of the daemon(s) currently selected in the panel.

## **NOTE**

When a daemon is paused, incoming trace events are discarded without notice.

### Flush

Mnemonic: F

Flushes trace events from the buffers associated with the daemon(s) currently selected in the panel to either the NightTrace display buffer or to the output file.

#### Halt

Mnemonic: H

Stops execution of the daemon(s) currently selected in the panel.

#### Detach

Relinquishes control of the running daemon(s) currently selected in the panel. Daemons writing to a file will continue to execute and will continue to write events to a file. If the file has no size limit associated with it, it could consume large amounts of disk space.

You cannot detach from a daemon which is streaming events directly to NightTrace, however you can detach to daemons streaming to a user application. The streaming will continue when detached.

#### Refresh Rate...

Mnemonic: S

Provides a dialog which controls the refresh interval of statistics for active daemons as shown in the panel.

# Triggers...

Mnemonic: T

This option launches the Edit Triggers dialog.

Triggers allow you to set a condition which is continually evaluated as streaming data is sent to NightTrace. When the condition evaluates to true, NightTrace will stop all executing daemons under its control. Daemons with triggers must be streaming data into NightTrace -- daemons writing to files are not eligible for triggers.

See "Triggers" on page 8-16 for more information.

#### Streaming Memory Usage Control...

Mnemonic: M

This option launches the Streaming Memory Usage Control dialog.

For streaming daemons, the Streaming Memory Usage Control <u>limit</u> defines the maximum amount of memory that NightTrace should use to hold streaming data.

See "Streaming Memory Usage Control" on page 8-18 for more information.

## **Display Fields**

The Display Fields submenu provides checkboxes for each of the column headers that can be displayed in the panel. When checked, the column is present; otherwise the column is hidden.

# **Control Buttons**

At the bottom of the panel there are a series of buttons that operate on daemons that are currently selected in the panel.

Most of the buttons execute obvious actions, as described in detail in the panel's Context Menu. The descriptions below provide a brief summary of those actions as well as detailed descriptions of actions not available in the Context Menu.

#### Launch

Launches the currently selected daemons. See "Launch" on page 8-4 for more information.

### Resume

Resumes the currently selected daemons. See "Resume" on page 8-5 for more information.

#### **Pause**

Pauses the currently selected daemons. See "Pause" on page 8-5 for more information.

#### Halt

Halts the currently selected daemons. See "Halt" on page 8-5 for more information.

#### Flush

Flushes the internal buffers of the currently selected daemons, forcing the data to be sent to the output device (file or stream attached to NightTrace). See "Flush" on page 8-5 for more information.

## **Display**

This option is equivalent to flush except in the case of a daemon writing to a file. Once such a daemon is stopped, pressing Display will load the contents of the file containing the trace data.

## Triggers...

This button launches the Edit Triggers dialog.

Triggers allow you to set a condition which is continually evaluated as streaming data is sent to NightTrace. When the condition evaluates to true, NightTrace will stop all executing daemons under its control. Daemons with triggers must be streaming data into NightTrace -- daemons writing to files are not eligible for triggers.

See "Triggers" on page 8-16 for more information.

#### **Enable Events**

Launches a dialog which allows you to enable or disable events while the daemon is executing.

#### **Delete**

Deletes the currently selected daemons; daemons cannot be deleted until halted.

# **Edit Daemon Definition**

The Edit Daemon Definition dialog allows the user to create and modify the various aspects of a daemon configuration.




Figure 8-5. Edit Daemon Definition Dialog

The Edit Daemon Definition dialog is divided into a number of areas that contain specific information about the current configuration, including:

- "General Settings" on page 8-9
- Trace File, Stream, and Consumer Output Settings (see "General Settings" on page 8-9)
- "Trace Buffer Settings" on page 8-11
- "Trace Daemon Runtime Settings" on page 8-14
- "Enabled Events" on page 8-15

# **General Settings**

The General area of the dialog contains information such as the name of the daemon configuration, the target system on which the daemon will run, the user name, and the output method.

#### Name

This field is automatically populated with the name user\_daemonfor each new daemon definition. A..x notation is appended when required, starting at 1, in order to keep the daemon names unique within a NightTrace session.

The Name is merely a label to aid the user in identifying specific daemons with a session. It has no external meaning and is unrelated to the NightTrace API. The user may change this to a name of their choosing.

## **Target**

The system on which this trace daemon will run.

#### **RCIM Clock**

When checked, the RCIM tick clock will be used to timestamp data. By default, the system's architecture clock is used as a timing source. Use of the RCIM tick clock is advantageous when multiple systems are being traced at the same time and their RCIM clocks are synchronized through an RCIM cable.

#### User

The name of the user on the specified target system responsible for running this daemon.

## **Output**

These radio buttons define the output method.

### **File**

When selected, all trace data is written directly to a disk file. You cannot analyze the data until the daemon has stopped collecting data and you load it into NightTrace using the Display button in the Daemons panel or the Open Files... option of the File menu in the main window.

Use of the File method requires you to enter information in the Trace File Settings group area which appears immediately below the General Settings area when this method is selected. For user daemons, this must be the pathname the user application specified to the trace\_begin, Trace.begin() call to initiate tracing.

If you check the File Wrap checkbox, the file size will be limited by the value in the Size Limit (bytes) field. When the limit is reached, the oldest trace data is overwritten with newer trace data.

#### Stream

When selected, all trace data is streamed directly into the current NightTrace session for immediate analysis. You can analyze trace data as it is collected or save it to a file for subsequent analysis.

You can adjust the Stream Buffer Size (byte) value in the Stream Settings group area which appears immediately below the General Settings group area when this mode is selected. You may wish to increase the size of the internal buffer NightTrace uses to pass data between the daemon and the analysis modules of NightTrace. If this buffer is too small, NightTrace iteratively pauses and resumes the daemon to catch up with processing (in which case you will see P and R markers in timeline rulers indicating the Pause and Resume operations). Normally, the default value is sufficient for most data rates.

This buffer is only used during the transfer of data blocks between the daemon and the analysis modules. It is unrelated to the Streaming Memory Usage Control limit, which sets a boundary for the amount of memory used to hold <u>all</u> trace data for all active streams. See "Streaming Memory Usage Control" on page 8-18 for more information.

#### Consumer

When selected, all trace data is streamed directly into a user application of your choice. It is assumed that the user application is written using the "NightTrace Analysis Application Programming Interface" on page 16-1.

You must specify the command that launches your application in the Consumer Application field which appears in the Consumer Application Settings group area immediately below the General Settings area when this mode is selected. You may specify arguments in the field as well.

When launched, the stdin file descriptor associated with your program is associated with the stream of trace data being generated by the daemon.

# **Key File**

This is required for user daemons. This field does not appear for user daemons that specify File output, in which case the filename is specified in the Trace File field as described under File above.

This must be the pathname the user application specified to the trace\_begin, Trace.begin() call to initiate tracing.

# **Trace Buffer Settings**

The contents of the Trace Buffer Settings area differ depending on whether the daemon is a user or kernel daemon.

#### **User Daemons**

## **Buffer Wrap**

When checked, events remain in memory and are not written to the output device until an explicit flush operation is executed. When all buffers are full, the oldest trace events are overwritten with new trace events.

Bufferwrap can be extremely useful in the following situations:

- When an event of interest occurs very infrequently and the trace data of interest is that only leading up to the event.
- When even the activity of writing events from memory to the output device can adversely affect system or application conditions.
- When the trace data rate is so intense that capturing all events overloads the network or NightTrace. Using bufferwrap and examining snapshots using the Flush button can still be useful in these situations.

### **Default Page Policy**

When checked, the default page-locking policy is in effect. The default policy is to leave pages in their default state (which would normally be unlocked unless the user application has taken some action outside of the NightTrace API, such as mlock(2)).

#### **Lock Critical Pages**

When checked, pages in use by the NightTrace API, as well as the shared memory pages associated with daemon buffers and control structures, will be locked in memory.

## **NOTE**

Locking pages requires the user application to run as root or to have privileged capabilities. See pam\_capability(3) for more information on granting privileged access to non-root users.

## **Inherit Settings**

When checked, the daemon will defer to any configuration settings the user application may have specified on the trace\_begin, Trace.begin() call, if the user application has already started.

When unchecked and the user application has already started, any critical configuration mismatches (e.g. use of an alternative clock, ability to lock pages, etc.) will cause the daemon invocation to fail with an appropriate diagnostic.

## **Number Buffers**

This setting controls the number of shared memory buffers in use between the user application and the daemon. This number, combined with the setting for Buffer Size, defines the total number of raw events that can be held in memory. In default operating mode (i.e. not buffer-wrap), when a single buffer fills, the user application automatically informs the NightTrace daemon and the daemon wakes up and copies the buffer to the output device.

Reducing the number of buffers reduces the number of wakeup events the user application needs to make to the daemon (although these are very short and efficient). However, reducing the number of buffers to a value less than 8 can cause loss of data when trace data rates are high.

The value specified is automatically rounded up to a power of two if it is not already a power of two.

A *raw event* is the amount of storage required to hold an event without arguments. Events with arguments require two or more raw events to hold their data.

#### **Buffer Size**

This setting controls the number of raw events that an individual buffer can hold. This setting, combined with the setting for the number of buffers, defines the total number of raw events that can be held in memory.

Increasing the Buffer Size setting is recommended if you have high trace data rates or are losing trace events.

A *raw event* is the amount of storage required to hold an event without arguments. Events with arguments require two or more raw events to hold their data.

## **Shared Mem Perms**

This area allows you to set the permissions to be applied on the shared memory buffer which is used to hold events logged by the user application before they are written to the output device by the user daemon.

#### **Kernel Daemons**

#### **Buffer Wrap**

When checked, events remain in memory and are not written to the output device until an explicit flush operation is executed. When all buffers are full, the oldest trace events are overwritten with new trace events.

Bufferwrap can be extremely useful in the following situations:

- When an event of interest occurs very infrequently and the trace data of interest is that only leading up to the event.
- When even the activity of writing events from memory to the output device can adversely affect system or application conditions.
- When the trace data rate is so intense that capturing all events overloads the network or NightTrace. Using bufferwrap and examining snapshots using the Flush button can still be useful in these situations.

### **Specify Non-Default Number Buffers**

This setting controls the number of kernel memory buffers in use between the kernel and the daemon. This number, combined with the setting for Specify Non-Default Buffer Size, defines the total number of bytes that can be held in memory. In default operating mode (i.e. not buffer-wrap), when a single buffer fills, the kernel automatically informs the NightTrace daemon and the daemon wakes up and copies the buffer to the output device.

Reducing the number of buffers to a value less than 8 can cause loss of data when trace data rates are high.

The value specified is automatically rounded up to a power of two if it is not already a power of two.

## Specify Non-Default Buffer Size

This setting controls the number of bytes that an individual buffer can hold. This setting, combined with the setting for the number of buffers, defines the total number of bytes that can be held in memory.

Increasing the setting is recommended if you have high trace data rates or are losing trace events.

#### **Trace CPUs**

This setting defines the list of CPUs which should be traced.

The list can either be the word all, or a comma-separated list of CPU numbers or ranges of CPU numbers; for example: 0, 2-3.

To the right of the text field a description of the resultant CPU mask is shown. Some system interfaces require CPU affinity to be specified as a mask, with each bit in the mask representing a CPU. The mask is shown to remind you that the numbers you enter into the text field here are logical CPU <u>numbers</u>, not hexadecimal characters in a CPU mask.

If you enter something invalid into the text field, the description to the right changes to the word invalid, shown in red. Ultimately, syntactically-invalid CPU lists are automatically replaced with a list indicating all.

#### NOTE

Support for kernel tracing is only available on some operating system distributions. See "Kernel Dependencies" on page B-1 for more information.

# **Trace Daemon Runtime Settings**

The Trace Daemon Runtime Settings area allows the user to specify the scheduling policy, CPU bias, and memory binding policies for the daemon.

## **Policy**

POSIX defines three types of policies that control the way a process is scheduled by the operating system. They are SCHED\_FIFO (FIFO), SCHED\_RR (Round Robin), and SCHED\_OTHER (Other). Each of these scheduling policies is associated with one of the System V scheduler classes.

#### **FIFO**

The FIFO (first-in-first-out) policy (SCHED\_FIFO) is associated with the fixed-priority class in which critical processes can run in predetermined sequence. Fixed priorities never change except when a user requests a change.

This policy is almost identical to the Round Robin (SCHED\_RR) policy. The only difference is that a process scheduled under the FIFO policy does not have an associated *time quantum*. As a result, as long as a process scheduled under the FIFO policy is the highest priority process scheduled on a particular CPU, it will continue to execute until it voluntarily blocks.

#### **Round Robin**

The Round Robin policy (SCHED\_RR), like the FIFO policy, is associated with the fixed-priority class in which critical processes can run in predetermined sequence. Fixed priorities never change except when a user requests a change.

A process that is scheduled under this policy (as opposed to the FIFO policy) has an associated time quantum.

## Other (Interactive)

The Time-Sharing policy (SCHED\_OTHER) is associated with the time-sharing class, changing priorities dynamically and assigning time slices of different lengths to processes in order to provide good response time to interactive processes and good throughput to CPU-bound processes.

## **Priority**

The Priority is relative to the selected Scheduling Policy and the range of allowable values is dependent on the operating system.

On most Linux systems, the priority values for the FIFO class include 1..99, where 99 is the most urgent user priority available on the system.

It is recommended that a reasonable urgent priority is specified when using the FIFO scheduling policy to prevent event loss.

#### **CPU List**

NightTrace daemon process execution will be constrained to the CPUs listed here.

By default, the list is all, which means the daemon process can run on any CPU on the target system which isn't shielded from process execution (consult the **shield(1)** man page for more information on shielding).

The list can either be the word all, or a comma-separated list of CPU numbers or ranges of CPU numbers; for example: 0, 2-3.

To the right of the text field a description of the resultant CPU mask is shown. Some system interfaces require CPU affinity to be specified as a mask, with each bit in the mask representing a CPU. The mask is shown to remind you that the numbers you enter into the text field here are logical CPU <u>numbers</u>, not hexadecimal characters in a CPU mask.

If you enter something invalid into the text field, the description to the right changes to the word invalid, shown in red. Ultimately, syntactically-invalid CPU lists are automatically replaced with a list indicating all.

## **Enabled Events**

The Enabled Events area allows you to specify which trace event types will be handled by the daemon.

You may also change this list dynamically while the daemon is executing by pressing the Enable Events button in the panel.

## **User Tracing**

By default, all user trace events are enabled.

## **Kernel Tracing**

For kernel trace daemons, the default set of enabled events is highly recommended. You may wish to enable additional events that you may have added to the kernel, a kernel module, or through a kernel event logged through an **ioctl(2)** call.

You should not disable kernel events that are enabled by default unless you are an expert in kernel tracing, as it may have an adverse affect on the default kernel display pages generated by NightTrace.

#### NOTE

Support for kernel tracing is only available on some operating system distributions. See "Kernel Dependencies" on page B-1 for more information.

# **Triggers**

Triggers are conditions that are evaluated as NightTrace analyzes trace events from streaming daemons. (A streaming daemon is one that sends trace data directly to the **ntrace** tool for immediate processing, as opposed to a daemon that sends such data to a file for subsequent processing).

When a trigger condition is evaluated to true, all streaming daemons are automatically halted and the Current Timeline is set to the event which caused the trigger.

Triggers are useful when you are trying to capture data associated with an event that may occur very rarely.

You may need to capture user and kernel data over a long period of time before the event actually occurs.


With the trigger capability, you can set your conditions, launch your daemons, and then walk away from NightTrace and let it run and capture data until triggered.

When capturing kernel data, or even user data, huge amounts of data may be collected over a fairly short period of time. NightTrace limits the amount of memory it will use to hold streaming trace data via a user-specified setting.

When the memory limit is reached, NightTrace will either halt current daemons or discard the oldest trace events in order to stay under the specified memory limit.

# **Edit Triggers Dialog**

The Edit Triggers dialog is activated by the Triggers... option in the Daemons menu and the Daemons Panel context menu, as well as by the Triggers... button in the Daemons panel.



### Figure 8-6. Edit Triggers Dialog

Trigger conditions are specified using NightTrace profiles (see "Profiles" on page 12-1).

# **Enable Triggers**

When checked, triggers are enabled, and NightTrace will continually process streaming trace data to evaluate the trigger conditions.

## Trigger if All/Any conditions are true

This option list indicates whether All conditions must be true before daemons will be halted, or if only one (Any) of the conditions must be true.

#### Add

Pressing the Add button launches a dialog which allows you to select an existing profile and optionally apply a count criteria to it.




Figure 8-7. Add Triggers Entry Dialog

#### **Edit**

Pressing the Edit button launches a dialog which allows you to change the selected profile and count criteria.

### Remove

Pressing the Remove button removes all selected profiles from the list.

## Change Setting...

The warning text and the Change Setting... button will only appear if the current Streaming Memory Usage Control action is set to stop daemons when the memory limit for streaming events is exceeded.

This may cause your daemons to be halted before the trigger condition of interest has occurred. Typically, when using triggers, you will want to change the Streaming Memory Usage Control action such that the oldest trace events are discarded when the memory limit is exceeded.

Pressing the Change Setting... button launches a dialog which allows you to change the memory limit and set the associated action. See "Streaming Memory Usage Control Dialog" on page 8-19

# **Streaming Memory Usage Control**

When daemons stream trace data directly to NightTrace for immediate analysis, the trace events are kept in memory. You can set the limit for the total amount of memory to be

used to hold streamed events. You can also instruct NightTrace as to which action to take when the limit is reached; halt streaming daemons or discard the oldest trace events.

# **Streaming Memory Usage Control Dialog**




Figure 8-8. Streaming Memory Usage Control Dialog

## **Memory Usage**

Enter the maximum amount of memory, in megabytes, that NightTrace should use to hold streaming trace data. When the limit is reached, the Action criteria defines what action NightTrace will take.

## **Action**

Select the desired action for NightTrace to take when the amount of memory required to hold streaming trace data exceeds the maximum limit set above.

If you have enabled Triggers (See "Triggers" on page 8-16), then you will most likely want to set the action to Delete oldest trace data at limit. Otherwise, the daemons may be shut down before your triggering condition actually occurs.

# **Trace Segments Panel**

The Trace Segments panel describes individual trace data segments that are loaded into the current NightTrace session.

# **Trace Segments Table**




Figure 9-1. Trace Segments Panel

A trace data segment represents data collected from a single user daemon.

## **Type**

This column provides an icon which indicates whether the daemon is a user daemon or kernel daemon (U or K), and whether it is a streaming daemon (a horizontal line through the letter).

### **NOTE**

Kernel tracing is on support under certain operating system distributions. See "Kernel Dependencies" on page B-1 for more information.

# **Trace Segment**

This column provides the name of the segment which is used merely for identification purposes within a NightTrace session.

## **Target**

This column indicates the target system name where the data was collected.

## Logged

This column provides a count of the actual number of events present in the data set. This number almost always differs from the statistics shown in the Daemons panel. The event counts in that panel are raw events. Processed events often consume more than one raw event.

#### Lost

This column displays a count of the number of raw events that have been lost between the logging agent (user application) and the daemon.

Event loss can occur for a variety of reasons. See "Preventing Trace Event Loss" on page 5-1 for more information.

When events are lost, an L character appears on trace display Timelines indicating the time at which the loss was recorded.

## **Duration**

This column displays the duration of the data segment.

#### **Unsaved**

This column displays an icon indicating the data segment has not yet been saved to disk. This occurs when streaming trace data into NightTrace.

# **Context Menu**

The Trace Segment panel's context menu is shown below:



Figure 9-2. Trace Segment Panel Context Menu

## Open Trace File...

This option launches a standard file browser that allows you to select a NightTrace data file to be loaded into the current session.

# Save Trace Data...

This option saves all the selected data segments to a NightTrace segment file which can be reloaded in subsequent NightTrace sessions. While the segment file is saved as a single entity, the distinction of the individual data segments is not lost when reloading.

## Properties...

This option displays information about the trace segment, including the system name and type, the clock source, and general timing information.




Figure 9-3. Trace Data Segment Properties Description Dialog


The Raw Header... button displays low-level information which is primary intended for use by NightTrace developers.

#### **Close Trace Data**

This option deletes the selected data segments from the current session. All events associated with them are discarded. If the events were streamed into NightTrace and have not yet been saved, a dialog will give you the opportunity to save them before closing them.

# **Display Fields**

This option displays a sub-menu which allows you to customize which columns are visible in the Trace Segments panel.



# **Control Buttons**

The buttons at the bottom of the panel provide save and close operations on the selected trace segments, as described in "Save Trace Data..." on page 9-3 and "Close Trace Data" on page 9-3.

The Events panel provides a textual table describing all trace events in all trace segments in chronological order.

# **Textual Event Tables**




Figure 10-1. Events Panel

The current timeline is displayed in the panel as the selected event. By selecting a new event in the panel, the current timeline is changed. Thus the Events panel is synchronized with all Timeline panels.

The Events panel table consists of the following columns:

#### Offset

This column displays the ordinal event offset number within the combined trace data set for the session. The first event in chronological time order has offset zero, the second offset one, and so on.

This is the same value as would be returned by the NightTrace offset() function.

#### Node

This column displays the name of the system where the event was logged. This column is hidden by default if there is trace data from only one system.

#### **Event**

This column displays the event ID as a numeric value, or using the corresponding event name, if one exists. Event IDs maybe assigned event names by using the Edit Current Event Description... option of the Event panel context menu, or using the Event Descriptions Panel panel.

#### **CPU**

When kernel trace data is present, this column displays the CPU where the event was logged. If user trace data is also present, NightTrace can provide the same information for user trace points, since it tracks the CPU upon which each process executes from the kernel data (user trace data does not, in and of itself, include the CPU number). This information cannot always be calculated (e.g. data loss), in which case a value of ?? is displayed.

This column is hidden by default when no kernel trace data is present.

#### **Process**

This column displays the process name that logged the trace event. If a process name is not available, the process ID is used.

#### **Thread**

This column displays the thread name or thread ID associated with the trace event. Kernel trace events normally do not have thread names associated with them, unless the user trace data segment is loaded with the kernel trace data and individual threads within the user application were named with a call to trace\_set\_thread\_name. See "trace\_set\_thread\_name, Trace.setThread-Name" on page 2-24.

#### **Time**

This column displays the time of the event, in seconds, relative to the first event in the combined data set.

## Tag

This column displays an event's tag name, if present. Events of interest can be tagged by double-clicking any cell in the row of an event. You can also create a tag by double-clicking an event in a Timeline panel or double-clicking in a ruler in a Timeline panel

Tags allow you to quickly locate events of interest. Tag names are saved as part of a NightTrace session so you can refer to them subsequently. You can annotate a tag with descriptive text using the Tags List Panel or using the context-menu of a tag in a ruler in a Timeline panel (see "Timeline Panels" on page 11-1 for more information).

## Description

This column displays an event's description. By default, kernel event descriptions are already associated with all kernel event IDs. For events without descriptions, the values of any arguments are displayed.

You can customize an event's description using the Event Descriptions Panel or by invoking the Edit Current Event Description... option of the Events panel's context menu.

## **Context Menu**

The Events panel context menu is shown below.




Figure 10-2. Events Panel Context Menu

#### **Text Search**

Accelerator: Ctrl+T

This option launches a search dialog which allows you to locate user-specified text within the Events panel. See "Event Panel Search Dialog" on page 10-6 for more information.

#### Search Forward

Mnemonic: R
Accelerator: Ctrl+G

Executes a forward search on the previously defined text search. If no such text search has been defined, it searches for the immediately following event.

#### **IMPORTANT**

When the focus is in an Events panel, Ctrl+G execute a textual search of that panel. However, when the focus is in a Timeline panel, Ctrl+G executes a profile search as defined by the currently selected profile.

#### Search Backward

Mnemonic: K

Accelerator: Ctrl+B

Executes a backward search on the previously defined text search. If no such text search has been defined, it searches for the immediately preceding event.

#### **IMPORTANT**

When the focus is in an Events panel, Ctrl+B execute a textual search of that panel. However, when the focus is in a Timeline panel, Ctrl+B executes a profile search as defined by the currently selected profile.

## Goto...

This option launches a dialog which allows you to type in an integer event offset value or a floating point number which is interpreted as a time stamp. Pressing OK on the dialog causes the current timeline to move to the specified location.

# **Distinguish Process Name by PID**

This option changes the description of process names to append their process ID. This can be useful when you have multiple processes of interest that have the same simple name.

## **Edit Current Event Description...**

This option launches the Edit Event Description dialog which allows you to define or change the name of an event and its description.




Figure 10-3. Add/Edit Event Description Dialog

## Code

This field contains the event ID of interest.

#### Name

This field defines the textual name that will be displayed in lieu of the event ID.

## Description

This field allows you to use the NightTrace format() function to define a (possibly complex) textual description of the event and its arguments.

## **Close All Trace Data**

This option closes all trace data segments; if some segments have not yet been saved, a dialog gives you the opportunity to cancel the operation.

## **Display Fields**

This option presents a sub-menu which allows you to select the columns to be displayed in the table.

# **Event Panel Search Dialog**

This dialog searches the Events panel for text. It does <u>not</u> search for text in Timeline panels.




Figure 10-4. Event Panel Search Dialog

This dialog is intended for textual searching of the information displayed in the Events panel. A more powerful search mechanism is available by pressing the Profile Search button which launches the Profiles dialog; see "Profiles Dialog" on page 12-2 for more information.

Event panel searches are controlled by checking the various fields of interest and specifying their search criteria.

The Search Options area contains the following.

## Treat search text as regular expression

When checked, all text in all search criteria fields are interpreted as regular expressions as defined by regex(3); otherwise, the search is executed for the exact text entered (modified by the Case sensitive search setting).

#### Case sensitive search

When unchecked, the search is executed without regard to case.

## Close dialog on successful search

This search dialog is non-modal, so it can stay open even after a search completes. Check this box if you want the dialog to automatically close if the search is successful.

## Match any/all criteria

This selection controls whether all or any of the checked fields must match their search criteria for a successful search.

The Search Criteria area contains individual text fields for the various columns in the Events panel. If the field is enabled (checked) then the text inside the field defines the criteria for that column.

#### **Search Forward**

Executes a forward search of the Events panel based on the specified criteria.

This button does <u>not</u> search for text in Timeline panels. Use the Profiles dialog (see "Profiles Dialog" on page 12-2) for such actions.

## Search Backward

Executes a backward search of the Events panel based on the specified criteria.

This button does <u>not</u> search for text in Timeline panels. Use the Profiles dialog (see "Profiles Dialog" on page 12-2) for such actions.

A timeline panel allows you to analyze trace events both graphically and textually.

## **Default Timeline**

The figure below is an example of a default user timeline.




Figure 11-1. Default User Timeline

A default user timeline consists of the following areas.

- Current Timeline Indicator
- Global Ruler
- Interval Ruler
- Event Graphs
- Event Description Area

The timeline is laid out horizontally and displays trace events as they occurred over time. Events to the left occurred chronologically before events to the right.

The timeline display is interactive. It reacts to zoom, search, and positioning operations.

## **Current Timeline Indicator**

The Current Timeline Indicator is a vertical dashed line which spans much of the vertical area of a timeline. It represents the current time and is synchronized with all other panels throughout the current NightTrace session.

Clicking anywhere within a ruler or event graph in a timeline moves the current timeline. It also responds to search operations throughout NightTrace.

## **Global Ruler**

The Global Ruler is the bottom-most ruler in the timeline.



Figure 11-2. Global Ruler

This ruler is the basic mechanism used for moving throughout the entire trace data set with the mouse.

The ruler is annotated with hash marks with time values in units of seconds. It represents the <u>entire</u> data set, not just the data that is currently viewed (also known as the current interval).

The portion of the ruler that has a gray background represents the section of the entire data set that comprises the current interval -- that is, the events that are currently visible in the timeline. Inside the gray area is a single vertical black line which extends through the entire height of the ruler. It represents the location of the current timeline within the current interval.

## **NOTE**

If the current interval is sufficiently small, the width of the gray area may be indistinguishable from the vertical black line within it. To change the current interval, simply click anywhere in the global ruler. Hence, to look at data near the end of the data set, click very near the end in the global ruler.

See "Keyboard Traversal" on page 11-6 for valuable information on how to use the keyboard to traverse within the current interval and throughout the entire data set.

## **Interval Ruler**

The Interval Ruler is the ruler just above the Global Ruler.



Figure 11-3. Interval Ruler

The Internal Ruler represents the current interval. It is annotated with hash marks with time values in seconds.

Clicking anywhere in the ruler changes the current timeline to that location.

See "Keyboard Traversal" on page 11-6 for valuable information on how to use the keyboard to traverse within the current interval and throughout the entire data set.

The interval ruler can also contain additional objects, as described below.

# Tags 1

A tag icon is displayed on the ruler for any tag associated with that time. Tags are convenient ways of marking events of interest. They can be annotated with user comments and are saved across NightTrace sessions.

To create a tag using the timeline, double-click a location in the Interval Ruler. You can then annotate the tag by right-clicking on its icon and selecting Annotate... from the context menu.

See "Tags List Panel" on page 14-1 for more information.

## Daemon Paused

This icon is displayed when a daemon is Paused. Events are no longer collected until the daemon is resumed.

#### NOTE

If the incoming data rate in streaming mode exceeds NightTrace's ability to pass data from the daemon to the display buffer, NightTrace automatically pauses and resumes the daemon in order to catch up. You can increase the <u>Stream Buffer Size</u> using the Daemons Definition dialog to avoid this.

## Daemon Resumed R

This icon is displayed when a daemon is Resumed.

## Lost Data

This icon is displayed when event loss is detected. It is associated with an NT\_LOST\_DATA event, which is not normally displayed in event graphs; however, you can explicitly search for this event. The first argument to the event contains the number of events that were lost.

When event loss occurs, all states currently active in state graphs are terminated

Event loss can occur for a variety of reasons. See "Preventing Trace Event Loss" on page 5-1.

## Time Warp

This icon is displayed when an internal inconsistency is detected within timestamps. This is most often indicative of a system problem or an internal operating system issue. This is essentially an internal operating system or hardware error, but instead of throwing all data away, NightTrace marks the data set and continues as best it can.

## **Event Graphs**

An Event Graph is a rectangular area within a timeline which contains vertical lines representing events of interest.

Thread: cos(14079)			
Thread: sin(14078)			
Thread: main(14077)			
User Events:			

Figure 11-4. Event Graph with Labels

The graphic above shows data boxes on the left hand side which react to changes in the current timeline.

The event graphs on the right display a vertical line when at least one event occurs at that location. Zooming in may provide more detail and the single vertical line may expand to indicate individual events.

Event graphs can be tailored to display events meeting only certain criteria. See "Creating Timeline Objects" on page 11-8 for information on creating and modifying event graphs.


In a default user timeline, an event graph is created for each thread that has logged trace events, if the application has been linked with the thread-aware version of the NightTrace Logging API library (See "Threads and Logging" on page 2-31 for more information.). Each of these graphs only displays events logged by their respective thread. The bottom-most event graph in a user timeline represents all user events -- those logged by any thread, registered or not.

A textual description of the closest event immediately preceding the current timeline is displayed in right-hand portion of the Event Description Area at the bottom of the panel.

As you hover the mouse cursor over any event in the event graphs, a textual description of the event under the mouse cursor is displayed in the left-hand portion of the Event Description Area at the bottom of the panel.

# **Event Description Area**

The Event Description Area provides a textual description of the events.



## Figure 11-5. Event Description Area

The area consists of two rectangular text areas.

## **Hover Event Description**

The area on the left-hand side describes the event immediately under the mouse cursor. As you move the mouse throughout the timeline and hover over an event, this area updates. If multiple events reside under the mouse cursor, the hover area indicates this. You must zoom in to obtain individual event information in such cases.

The detailed textual description in this area includes the timespan between the hover event and the current timeline.

TIP

To determine the amount of time between two events within the current interval, set the current timeline on one event and then hover the mouse cursor over the second event of interest.

To determine the amount of time between two events which are not both visible in the current timeline, either zoom out so both events are visible or tag each event and use the Tags List Panel to examine the timespans.

## **Current Event Description**

The area on the right-hand side describes the current event. The *current event* is the event immediately at the current timeline or the event most closely preceding it in time.

Event descriptions are provided by default by NightTrace. You can control how events are described by providing customized event descriptions using the Event Descriptions Panel.

# **Keyboard Traversal**

Timelines are designed to be efficiently traversed through keyboard shortcuts when the window focus is in a timeline.

The following table describes keyboard traversal.

Table 11-1. Timeline Keyboard Traversal

Key Sequence	Action
RightArrow	Moves the current timeline to the next event in time
LeftArrow	Moves the current timeline to the previous event in time
UpArrow	Zooms in or out, depending on the Zooming preference (see "Zooming Controls" on page 7-42).
DownArrow	Zooms in or out, depending on your Zooming preference (see "Zooming Controls" on page 7-42).
Alt+UpArrow	Zooms all the way in or out, depending on your Zooming preference (see "Zooming Controls" on page 7-42).
Alt+DownArrow	Zooms all the way in or out, depending on your Zooming preference (see "Zooming Controls" on page 7-42).
Alt+LeftArrow	Goes to the first event in the data set

Table 11-1. Timeline Keyboard Traversal (Cont.)

Key Sequence	Action
Alt+RightArrow	Goes to the last event in the data set
Ctrl+RightArrow	Shifts the current interval to the right
Ctrl+LeftArrow	Shifts the current interval to the left
Ctrl+F	Displays the Profiles Dialog to allow you to define or select a search criteria
Ctrl+G	Executes a forward search using the currently selected profile in the Profile Status List. If no profile is selected, it searches for the next event.
Ctrl+B	Executes a backward search using the currently selected profile in the Profile Status List. If no profile is selected, it searches for the previous event.
Ctrl+I	Launches the Goto dialog which allows you to enter times or offsets that control which events are displayed in the interval.
Alt+G	Identical to Ctrl+G except that the search is constrained by the bounds of the current interval.
Alt+B	Identical to Ctrl+B except that the search is constrained by the bounds of the current interval.
Alt+V	Toggles between the current timeline and the last location of the current timeline. This is especially useful for returning to the previous location after executing a search.

In addition to keyboard shortcuts, moving the mouse wheel back and forth causes the timeline to zoom in and out.

# **Creating Timeline Objects**

Timeline objects can be created or modified by entering Edit mode using the context menu of a Timeline panel.




Figure 11-6. Timeline Editing

In edit mode, the background of the timeline turns into a grid. Objects can be created and inserted into the grid using the context menu.




Figure 11-7. Timeline Context Menu

Most timeline objects must be inserted into a Graph Container. By default, a user timeline contains one large graph container consuming the center and largest portion of the timeline.

To insert an event graph, state graph, data graph, ruler, or locator into a graph container, select the graph container by clicking on it and then select the appropriate option from the context menu.

## **NOTE**

If you cannot select the graph container because its edges are obscured by graphs within the container, click on any object in the container, then Shift+Click to select that container.

Once selected, the mouse cursor will change. Click inside the graph container and drag the mouse up or down and release the mouse button. The new object is inserted.

#### **NOTE**

Graph containers, and objects in general, can be resized using the mouse. Position the cursor over an edge or corner, wait for the cursor to change to a resizing cursor, then left click and drag to resize.

Double-click the new object to bring up its editing dialog, as described in the sections below.

## **Event Graph**

An Event Graph displays vertical lines for each event that matches the criteria of the event graph.




Figure 11-8. Edit Event Graph Profile Dialog

The definition of an event graph is essentially identical to defining a condition profile using the Profiles Dialog.

Only events matching the conditions set within this dialog will be shown in the event graph.

Colors can be specified in the Event Color field by clicking on the color bar to the right of the text field and selecting a color from the Color Selection dialog or by entering in the text field a standard color name (see "Standard Color Names" on page 11-19) or RGB notation (i.e., #rrggbb where r, g and b are hexadecimal characters representing the red, green and blue color components, respectively).

Additional adjustments can be made by selecting various options from the context menu when the event graph is selected.

## State Graph

A State Graph is an Event Graph that can optionally display states as well.




Figure 11-9. Edit State Graph Profile Dialog

The definition of a state graph is essentially identical to defining a state profile using the Profiles Dialog, with the additional capability of selecting individual events to be displayed as in an Event Graph.

During the time in which a state is active, a solid bar appears in the lower vertical half of the state graph. Events as selected by the Events field in this dialog appear as vertical lines spanning the entire vertical space of the graph.

Colors can be specified in the Event Color and State Color fields by clicking on the color bar to the right of the text field and selecting a color from the Color Selection dialog or by entering in the text field a standard color name (see "Standard Color Names" on page 11-19) or RGB notation (i.e., #rrggbb where r, g and b are hexadecimal characters representing the red, green and blue color components, respectively).

Additional adjustments can be made by selecting various options from the context menu when the state graph is selected.

## **Data Graph**

A Data Graph is similar to a State Graph, except that a data block or line is shown in lieu of the solid state bar of a state graph. The height of the line or block indicates the value of the data.




Figure 11-10. Edit Data Graph Profile Dialog

The definition of a data graph is essentially identical to defining a condition profile using the Profiles Dialog, with the addition of three fields which define how the data is to be displayed.

#### Value

This field must be a valid NightTrace expression which defines a value. Typically this will be something simple like an argument associated with the events as defined in the Events field; e.g. arg1. See "Using Expressions" on page 15-1 for more information on expressions.

## Min Value Max Value

If set to CALC, NightTrace automatically calculates the minimum and/or maximum values of all data items matching the profile's criteria and adjusts the vertical scaling appropriately such that the largest data value consumes the entire vertical space of the graph and the smallest consumes a single pixel.

You may change the fields to specific values and NightTrace will adjust the scaling accordingly. Data values that fall outside the specified minimum or maximum values will be plotted as the minimum or maximum value specified, respectively.

## **Drawing and Coloring Options...**

Pressing this button displays the Data Graph Options dialog that allows you to select the color of data values and their boundaries and select attributes which affect how the data graph is drawn.

Additional adjustments can be made by selecting various options from the context menu when the data graph is selected.

## **Data Graph Options Dialog**

The Data Graph Options dialog is launched from the Edit Data Graph Profile dialog when the Drawing and Coloring Options... button is pressed.




Figure 11-11. Data Graph Options Dialog

The dialog consists of two areas which control how data graphs are drawn and the colors used for the data values and boundaries.

Combining the various Drawing and Coloring options provides a wide variety of graph types, as shown in "Drawing and Coloring Examples" on page 11-16.

## **Drawing Attributes**

## **Connect Data Values**

This option draws a line between all consecutive data items. Each data item is drawn as a small point on the graph.

#### **Extend Data Values**

This option causes a polygon to be drawn, which extends from the X coordinate of the last data item up to the X coordinate of the current data item.

## Coloring

The Coloring area defines the color mode used to draw the data graph and the colors associated with the mode selected from the drop-down:




Figure 11-12. Data Graph Options Dialog Color Mode Selector

The color mode selector provides four options:

## Single Color

In Single Color mode, a single color is used to draw all data values. The color is defined by the Primary Color item in the dialog.

## Gradient

In Gradient mode, a linear color gradient is used to draw all data values and data value boundaries. The end-points of the gradient are defined by the Primary Color and High Color items in the dialog. The color gradient is strictly vertical, reflecting the value of each data item. Primary Color represents the smallest data value whereas High Color represents the largest data value.

## **Discrete Thresholds**

In Discrete Thresholds mode, a set of colors is used to reflect various value thresholds of the data. An arbitrary number of thresholds can be entered, using the Color Thresholds table in the dialog.

The Primary Color is used as the default threshold -- the threshold matching all values not covered by specific thresholds entered in the table.

The portions of the data items and boundaries that are drawn that fall into each threshold will be of the corresponding threshold color.

#### **Auto Differentiated**

In Auto Differentiated mode, a unique color is randomly assigned to each data value encountered in the data graph. You cannot predict which color will be assigned to which data value, but once the color is shown it will remain associated with only that data value.

This option is not recommended for data sets which have a large range of values, since individual colors become hard to distinguish as the number of colors required increases dramatically.

An interesting application of this color mode combines its use with Extend Data Values and a strict application of graph Minimum and Maximum boundaries.

Consider a data set consisting of non-negative integers, such as the PID value of a set of processes. Setting the Minimum and Maximum graph boundaries in the Data Graph dialog to zero and one, respectively, combined with Extend Data Values and Auto Differentiated will cause a single block of data to be drawn for each data value of the same height, but with a unique color. Kernel display pages use this technique to show process activities on each CPU.

## **Primary Color**

The Primary Color is used for the Single Color, Gradient, and Discrete Thresholds color modes.

A color may be selected by clicking on the color bar to the right of the text field and selecting a color from the Color Selection dialog or by entering in the text field a standard color name (see "Standard Color Names" on page 11-19) or RGB notation (i.e., #rrggbb where r, g and b are hexadecimal characters representing the red, green and blue color components, respectively).

When a color is entered in the text field and the dialog focus moves away from the text field, the color bar is updated with the new color (unless it is invalid, in which case it turns black).

## **High Color**

The High Color is only used with the Gradient color mode.

Colors may be selected by clicking on the color bar to the right of the text field and selecting a color from the Color Selection dialog or by entering in the text field a standard color name (see "Standard Color Names" on page 11-19) or RGB notation (i.e., #rrggbb where r, g and b are hexadecimal characters representing the red, green and blue color components, respectively).

When a color is entered in the text field and the dialog focus moves away from the text field, the color bar to the text field is updated with the new color (unless it is invalid, in which case it turns black).

#### **Color Thresholds**

The Color Thresholds table is only used with the Discrete Thresholds color mode.

The table automatically expands as you enter individual thresholds.

Enter a color by clicking or entering a cell in the Color column. This launches a Color Selection dialog.

Enter a threshold value as an integer or floating-point numeric literal in the Threshold column by double-clicking in the cell or typing while positioned in the cell.

The value entered for a threshold is the inclusive lower bound of the threshold. The exclusive upper bound is defined by the closest threshold above it by value, not necessarily by visual position in the table. If no threshold exists, the upper bound extends to the maximum value that can be plotted.

Traverse the cells in the table by clicking with the mouse or using the arrow keys. Using the Tab key will cause the focus to leave the table.

Remove cells by selecting the cells to be removed and pressing the Delete key (or Crtl+X).

Thresholds are automatically sorted in ascending order by NightTrace before and after the dialog is shown.

The Primary Color is used for the default threshold, which matches all values lower than the lowest threshold entered in the table.

## **Drawing and Coloring Examples**

Figure 11-13 shows several different data graphs reflecting the same data, but using different combinations of Drawing and Coloring attributes.




Figure 11-13. Data Graph Examples

## **Color Selection Dialog**

The Color Selection Dialog aids you in selecting a color by allowing you to select from a list of basic or customized colors, enter RGB values, or select a color from a spectrum.

It is launched when clicking on a colored button to the right of a color selection text field, or when clicking in cells in the Color column of the Color Thresholds table.




Figure 11-14. Color Selection Dialog

When using the mouse to select a color from the spectrum, be sure to choose an Alpha value from the slider at the right-hand side of the dialog.

A common error is to click in the spectrum area and click on OK, expecting to get the exact color associated with your mouse click in the spectrum, but effectively getting black instead due to the Alpha setting. The color in the spectrum is modified by the Alpha value associated with the vertical slider setting. The actual color you are selecting is always shown in the medium-sized rectangle beneath the lower-left corner of the spectrum.

## **Standard Color Names**

NightTrace supports the standard color names shown in Table 11-1.

**Table 11-1. Standard Color Names** 

aliceblue	darkslategray	lightpink	paleturquoise	
antiquewhite	darkslategrey	lightsalmon	palevioletred	
aqua	darkturquoise	lightseagreen	papayawhip	
aquamarine	darkviolet	lightskyblue	peachpuff	
azure	deeppink	lightslategray	peru	
beige	deepskyblue	lightslategrey	pink	
bisque	dimgray	lightsteelblue	plum	
black	dimgrey	lightyellow	powderblue	
blanchedalmond	dodgerblue	lime	purple	
blue	firebrick	limegreen	red	
blueviolet	floralwhite	linen	rosybrown	
brown	forestgreen	magenta	royalblue	
burlywood	fuchsia	maroon	saddlebrown	
cadetblue	gainsboro	mediumaquamarine	salmon	
chartreuse	ghostwhite	mediumblue	sandybrown	
chocolate	gold	mediumorchid	seagreen	
coral	goldenrod	mediumpurple	seashell	
cornflowerblue	gray	mediumseagreen	sienna	
cornsilk	grey	mediumslateblue	silver	
crimson	green	mediumspringgreen	skyblue	
cyan	greenyellow	mediumturquoise	slateblue	
darkblue	honeydew	mediumvioletred	slategray	
darkcyan	hotpink	midnightblue	slategrey	
darkgoldenrod	indianred	mintcream	snow	
darkgray	indigo	mistyrose	springgreen	
darkgreen	ivory	moccasin	steelblue	
darkgrey	khaki	navajowhite	tan	
darkkhaki	lavender	navy	teal	
darkmagenta	lavenderblush	oldlace	thistle	
darkolivegreen	lawngreen	olive	tomato	
darkorange	lemonchiffon	olivedrab	turquoise	
darkorchid	lightblue	orange	violet	
darkred	lightcoral	orangered	wheat	
darksalmon	lightcyan	orchid	white	
darkseagreen	lightgoldenrodyellow	palegoldenrod	whitesmoke	
darkslateblue	lightgray	palegreen	yellow	
				_

## **Interval Ruler**

You can add an Interval Ruler to a graph container using the Ruler option of the Add to Selected Graph Container sub-menu of the timeline's context menu.

## **Global Ruler**

You can add a Global Ruler to a graph container using the Locator option of the Add to Selected Graph Container sub-menu of the timeline's context menu.

## Label

Labels are static text areas that can be placed anywhere within a timeline. They do not have to be inserted into a graph container.

You can add a label by using the Add Label option of the timeline's context menu.

Once added, double-click the label to set its text.

Once defined, you can adjust attributes of the label by selecting various options from the context menu when the label is selected, for example:

## Adjust Font/Alignment in Selected


This menu item allows you to select a font for the label, and to adjust its vertical and horizontal alignment.

## **Adjust Colors in Selected**

This menu item allows you to select the color of the text and the color of the label's background.

## Data Box

A Data Box is a dynamic label that can be placed anywhere in a timeline. The value displayed in the box is dependent on the current timeline.



## Figure 11-15. Edit Data Box Profile

The definition of a Data Box is essentially identical to defining a condition profile using the Profiles Dialog, with the addition of the following field:

## Output

This field must be a valid NightTrace string expression. Typically, it involves use of the format() function. For example:

```
format("The current value is: %f", arg_dbl())
```

See "Using Expressions" on page 15-1 for more information.

Once defined, you can adjust the box by selecting various options from the context menu when the data box is selected; for example:

## Adjust Font/Alignment in Selected

This menu item allows you to select font for the text to be displayed and to adjust its vertical and horizontal alignment.

## Adjust Colors in Selected

This menu item allows you to select the color of the text and the color of the label's background.

## **Default CUDA AI Timeline**




Figure 11-16. CUDA Al Timeline

When CUDA Application Illumination trace points are detected in the event data set (see "cuda" on page 4-65), NightTrace automatically builds a timeline similar to the figure above.

The following features distinguish CUDA AT timelines from others.

- The databox on the left side in the middle of the panel lists details about the execution of the CUDA kernel at or immediately prior to the current timeline. It includes the grid and block configurations, the name of the kernel, and execution times.
- The tall data graph in the middle of the panel plots the duration of individual CUDA kernel executions.

## **Default CUDA GPU Timeline**

When CUDA GPU trace points are detected in the event data set (see "NightTrace CUDA Tracing API" on page 2-32), NightTrace automatically builds a timeline similar to the following.




Figure 11-17. Default CUDA GPU Timeline

The colorful rows represent activity on individual Symmetric Multiprocessors (SM) inside a GPU. The actual number of rows will depend on the number of SMs your GPU had and whether they logged any trace data.

The following features distinguish CUDA GPU timelines from others:

- The trace data is segregated by SM (instead of by CPU as in a kernel timeline).
- The only events shown (by default) are those logged by ntrace\_cuda\_event() calls executed by the GPU.

A single vertical line in one of the event graphs may actually (and usually
does) represent more than one event. Unlike most all other trace data, the
times of these individual events are identical, and you will only see a single
vertical line no matter how far you zoom in.

Due to the last issue in the bullet list above, another panel is included along with the CUDA GPU timeline; that panel is shown here.




Figure 11-18. CUDA Warp Panel

A CUDA Warp panel is very much like an Events panel, except it only shows the events associated with a GPU's execution of a single warp. A warp, in CUDA parlance, is the execution of a subset of threads by a single symmetric processor. Effectively, all events logged by the same ntrace\_cuda\_event() by the same warp will be at the same exact time.

Thus they appear as a single vertical line in the CUDA GPU timeline.

As you traverse through the data set, this panel shows you all the events for the warp associated with the current time.

Checking the Filter to unique trace event/argument values checkbox causes the warp to coalesce events with the same event ID and argument set within the warp, as shown by the following figure.




Figure 11-19. Filtered CUDA Warp Panel

As you can see, there are two sets of similar events in this warp.

If you hover over one of the sets, a tool tip more fully describes the members of the set.

As you move through events within the current warp, the representative event will change in the filtered CUDA Warp panel so that it is shown. For example, if you moved the timeline an event or two forward, the first event in the figure above might be at Offset 12920.

# 12 Profiles

Profiles include any condition or state you use within a NightTrace session, including those used in search and summary operations.

In NightTrace, a condition is the "logical and" of several criteria such as event codes, processes, and threads. Conditions may be used to examine matching events of interest.

A state profile is a combination of two conditions which identify the start and end requirements of a state. All other profiles are simply condition profiles, although they can be as complex as you need them to be.

Profiles can be used in:

- searches
- summaries
- graphs

Profiles are managed using the Profiles dialog.

# **Profiles Dialog**

This dialog contains a list of profiles and allows you to define new profiles using drop-down option lists for commonly requested conditions and states. Profiles can be further customized providing you complete control over detailed profile conditions.




Figure 12-1. Profiles Dialog

## **Profile Status List**

The top portion of the dialog contains the Profile Status List table. Profiles are displayed in a table with the following columns:

## Type

This column displays a state icon for state profiles; otherwise nothing is displayed.

#### Name

This column displays the profile's name.

## **Status**

This column indicates whether the event at or immediately previous to the current timeline satisfies the conditions of the profile.

## Count

This column displays a count of the number of instances of events that satisfy the conditions of the profile.

#### Last

This column displays the last event offset before the current timeline which satisfied the conditions of the profile.

## Offset

This column displays the last event offset that concluded the profile's state -- this is only valid for states.

## **Context Menu**

The Profile Status List table's context menu is shown below.



Figure 12-2. Profile Status List Table Context Menu

## **Delete**

This option deletes the profile definitions currently selected in the table.

## Search Forward

This option executes a forward search for the currently selected profile.

## Search Backward

This option executes a backward search for the currently selected profile.

#### Search Forward within Timeline Interval

This option executes a forward search for the currently selected profile; the range of events to search is constrained by the current Timeline interval.

## Search Backward within Timeline Interval

This option executes a backward search for the currently selected profile; the range of events to search is constrained by the current Timeline interval.

## **Summarize**

This option executes a summary action on the currently selected profile.

## **Summarize within Timeline Interval**

This option executes a summary action on the currently selected profile; the range of events to summary is constrained by the current Timeline interval.

## Move Up


This option moves the currently selected profiles one position towards the beginning of the table.

#### Move Down

This option moves the currently selected profiles one position towards the end of the table.

## **Display Fields**

This option displays a sub-menu which allows you to select which columns are visible within the table.



## **Profile Definition**

This area of the dialog contains various criteria fields which define a profile.

## Key/Value

The Key/Value option list provides a starting point for profile definition. Selecting items from the option list populates the individual condition fields below with the values and expressions required to specify the key (and value) you have selected.

The option list provides the following items:

## Condition

State System Call All Events System Call Enter Events System Call Leave Events System Call State Exception All Events **Exception Enter Events** Exception Leave Events Exception State Interrupt All Events Interrupt Enter Events Interrupt Leave Events Interrupt State Function All Events Function Enter Events Function Return Events Function State Tagged Events

#### Condition

This option populates the condition fields to create a condition profile which will match any event, unconditionally. It is useful when you wish to manually enter conditions starting from a clean template.

#### State

This option populates the condition fields to create a state profile which starts on any event and ends on any event. It is useful when you wish to manually enter state conditions starting from a clean template.

System Call All Events System Call Enter Events System Call Exit Events System Call State

These options populate the condition fields such that the profile detects the existence of a specific system call, as indicated by the specific option selected. After selecting one of these options, a system call list will launch allowing you to select an individual system call.

Selecting System Call All Events will match events representing the entry, suspension, resumption, and exit of a system call.

Selecting System Call Enter Events or System Call Exit Events will match events representing entry and resumption of a system call, or suspension and exit, respectively.

Selecting System Call State defines a state which begins when a system calls is entered or resumed, and terminates when the system call is suspended or exits.

When a specific system call is selected, the name of the system call will appear in a read-only text field beneath the Key/Value option list. The specific system call associated with the profile can be changed by pressing the Values... button and selecting a different value from the list.

#### NOTE

Multiple system calls may be selected from the Key/Value pop-up menu.

Exception All Events
Exception Enter Events
Exception Exit Events
Exception State

These options populate the condition fields such that the profile detects the existence of a specific machine exception, as indicated by the specific option selected. After selecting one of these options, an exception list will launch allowing you to select an individual exception.

Selecting Exception All Events will match events representing the entry, suspension, resumption, and exit of an exception.

Selecting Exception Enter Events or Exception Exit Events will match events representing entry and resumption of an exception, or suspension and exit, respectively.

Selecting Exception State defines a state which begins when an exception is entered or resumed, and terminates when the exception is suspended or exits.

When a specific exception is selected, the name of the exception will appear in a read-only text field beneath the Key/Value option list. The specific exception associated with the profile can be changed by pressing the Values... button and selecting a different value from the list.

#### NOTE

Multiple exceptions may be selected from the Key/Value pop-up menu.

Interrupt All Events Interrupt Enter Events Interrupt Exit Events Interrupt State

These options populate the condition fields such that the profile detects the existence of a specific machine interrupt, as indicated by the specific option selected. After selecting one of these options, an interrupt list will launch allowing you to select an individual interrupt.

Selecting Interrupt All Events will match events representing the entry, suspension, resumption, and exit of an interrupt.

Selecting Interrupt Enter Events or Interrupt Exit Events will match events representing entry and resumption of an interrupt, or suspension and exit, respectively.

Selecting Interrupt State defines a state which begins when an interrupt is entered and terminates when the interrupt exits.

When a specific interrupt is selected, the name of the interrupt will appear in a read-only text field beneath the Key/Value option list. The specific interrupt associated with the profile can be changed by pressing the Values... button and selecting a different value from the list.

#### **NOTE**

Multiple interrupts may be selected from the Key/Value pop-up menu.

Function All Events Function Enter Events Function Exit Events Function State

These options are for use when you have loaded Application Illumination (AI) trace data. AI trace data is generated by using the **nlight(1)** tool to instrument your user application automatically, recording the call and return from all (or selected) functions in your application. See Chapter 4, "Application Illumination" for more information.

These options populate the condition fields such that the profile detects the existence of a specific function calls, as indicated by the specific option selected. After selecting one of these options, a function list will launch allowing you to select an individual function (or several functions).

Selecting Function All Events will match events representing the entry, suspension, resumption, and exit of a function.

Selecting Function Enter Events or Function Exit Events will match events representing entry and return from of a function, respectively.

Selecting Function State defines a state which begins when a function is entered and terminates when the function returns.

#### NOTE

Multiple functions may be selected from the Key/Value pop-up menu.

#### **Tagged Events**

This option populates the condition fields such that the profile detects the event associated with the tag that you select from the list that is launched when choosing this option.

When a specific tag is selected, the name of the tag will appear in a read-only text field beneath the Key/Value option list. The specific tag associated with the profile can be changed by pressing the Values... button and selecting a different value from the list.

If no tagged events exist, this menu option is desensitized.

#### NOTE

Multiple tags may be selected from the Key/Value pop-up menu.

#### Choose Profile...

You can select from previously-defined profiles using the Choose Profile... button.

Selecting an entry from the list displayed by this button populates the Profile Definition criteria with the conditions associated with that profile. The current profile becomes the profile you selected. Subsequent changes will be applied to the profile if you press the Apply, Search/Close, or Summarize buttons. A new profile will be created if you press the Add button.

Alternatively, when checking the Import by Reference checkbox in the Choose Profile dialog, the Profile Definition criteria will be populated with a condition that references the selected profile. This technique allows you to add additional conditions to the selected profile while preserving the named association. Thus subsequent changes to the selected profile will be reflected in the new profile you create.

After choosing a Key/Value pair or previously defined profile using the Choose Profile... button, you can further customize the condition or state by using the individual text fields and selection lists in the dialog.

Any customized changes which are subsequently made appear in the criteria text fields with a salmon-colored background. Pressing the Reset button restores the default conditions that were populated when you selected the profile.

# Events Start Events End Events

The Events, Start Events and End Events criteria allows you restrict the condition to events listed in the text fields. Values in the text fields are required to be a comma-separated list of numeric event numbers or ranges or event names. The Browse... buttons to the right of the text fields allows you to select from a list of known event names. The values ALL, and ALLUSER are special entries referring to classes of events, as indicated by their name.

Start Events and End Events are only shown for state profiles whereas Events is only shown for condition profiles. Start Events and End Events refers to events which are candidates for the beginning or end of a state, respectively. Events refers to all events.

#### **Exclude Events**

Exclude Events allows you restrict the condition to events that are not listed in the text field. It is only shown for condition profiles.

Values in the text field are required to be a comma-separated list of numeric event numbers or ranges or event names. The Browse... button to the right of the text field allows you to select from a list of known event names. The value NONE is a special entry referring to null set of events, which means that no events are excluded.

# Condition Start Condition End Condition

The Condition, Start Condition, and End Condition criteria allows you restrict the profile using NightTrace's expression language. Values in the text fields are required to be a boolean NightTrace expressions whose syntax is roughly that of the C language, with built-in functions for accessing attributes of events. See "Using Expressions" on page 15-1 for more information on expression syntax and semantics.

Start Condition and End Condition are only shown for state profiles whereas Condition is only shown for condition profiles. Start Condition and End Condition refers to the conditions which must be met for the beginning or end of a state, respectively, whereas Condition applies globally to the profile.

#### **Processes**

The Processes criterion allows you restrict the condition to events generated by processes that are specified in the text field.

Values in the text field are required to be a comma-separated list of process names or PIDs (see getpid(2) and gettid(2)). The Browse... button to the right of the text field allows you to select from a list of known processes.

#### NOTE

All Linux threads within the same program share the same PID value. For trace events generated with the NightTrace Logging API, the value logged as the process identifier is the common PID. For kernel events, the value logged for the process identifier is the thread's TID (see gettid(2)).

If multiple processes have the same name (perhaps two unrelated programs both called **a.out**) selecting that name from the list or placing that text in the text field will match both processes. Similarly, for multi-threaded processes, the specified process name will match all threads within the process.

Placing a process name in the Processes list is equivalent to adding a condition restriction using the following NightTrace expression:

```
process_name == "a.out"
```

#### **Threads**

The Threads criterion allows you restrict the condition to events generated by threads that are specified in the text field.

Values in the text field are required to be a comma-separated list of thread IDs (see gettid(2)). The Browse... button to the right of the text field allows you to select from a list of known threads by name. This list is only available when user trace data from registered threads is loaded. See "Threads and Logging" on page 2-31 for more information.

If multiple threads with the same name exist, specifying the thread name will match all such threads.

Placing a thread name in the Threads list is equivalent to adding to adding a condition restriction using the following NightTrace expression:

thread name == "mythread"

#### **Nodes**

The Nodes criterion allows you restrict the condition to events generated on the systems that are specified in the text field.

Values in the text field are required to be a comma-separated list of system names (see hostname(1)). The Browse... button to the right of the text field allows you to select from a list of known hosts present in the loaded trace data sets by name.

Use of the Nodes condition is only useful when capturing and analyzing data from multiple systems; this requires using the Real-time Clock and Interrupt Module (RCIM) as a synchronized timing source or having multiple systems synchronized through another means; e.g. NTP or PTP. See the *Real-Time Clock and Interrupt Module User's Guide* (0891082) for more information.

Placing a node name in the **Nodes** list is equivalent to adding to adding a condition restriction using the following NightTrace expression:

```
node_name == "a.out"
```

#### **Output Script**

This text field does not impose a constraint on the profile. It allows you to specify an alternative shell script that is executed for summary operations. By default, the following scripts are executed for condition and state profile summaries, respectively:

- /usr/lib/NightTrace/bin/event-summary.sh
- /usr/lib/NightTrace/bin/state-summary.sh

All script output generated to *stdout* will be displayed in the Profiles Result panel which is automatically created when a summary is executed for a new profile. Output from *stderr* is not captured.

Summary data is passed to the specified script via environment variables. See "Summary Script Environment Variables" on page 12-14 for more information.

The path to the summary output script is saved as part of a NightTrace session and can be utilized in subsequent **ntrace** invocations, including batch mode summary execution via command line options.

#### **CPUs**

The CPUs list allows you to place CPU restrictions on the profile.

The list can either be the word all, or a comma-separated list of CPU numbers or ranges of CPU numbers; for example: 0,2-3.

To the right of the text field a description of the resultant CPU mask is shown. Some system interfaces require CPU affinity to be specified as a mask, with each bit in the mask representing a CPU. The mask is shown to remind you that the numbers you enter into the text field here are logical CPU <u>numbers</u>, not hexadecimal characters in a CPU mask.

If you enter something invalid into the text field, the description to the right changes to the word invalid, shown in red. Ultimately, syntactically-invalid CPU lists are automatically replaced with a list indicating all.

#### Name

The Name text field defines the name of the profile. The profile's name is automatically set when selecting a previously-defined profile or when creating a new profile. You can change the name by typing in a modified name in the text field. Changing the name of a profile does not, in and of itself, create a new profile. A new profile is created if you press the Add button. Pressing the Apply, Search/Close, or Summaries buttons applies the name change (and all other outstanding profiles changes) to the current profile as well as executes the associated action, if any.

### **Control Buttons**

The checkbox and buttons at the bottom of the dialog operate on the profile as defined by the remainder of the dialog.

#### Close dialog on summary or successful search

The Profiles dialog is non-modal, so it can stay open after search or summary operations. Clear this checkbox if you want the dialog to remain visible after a summary or successful search operation.

#### Add

The Add button creates a new profile based on the Profile criteria. If another profile with the same name already exists, the name of the new profile is automatically adjusted to be unique by appending a numeric value to the name.

#### **Apply**

The Apply button modifies an existing profile based on the Profile criteria. If the profile did not previously exist, it adds the profile.

#### Search Backward

Executes a backward search for the selected profile.

#### **Search Forward**

Executes a forward search for the selected profile.

#### **Halt Search**

Halts a currently active search.

#### **Summarize**

The Summarize button executes a summary action based on the current profile.

Summaries can also be executed by pressing the Summary icon on the tool bar or selecting the Summarize option from the Summary menu.

See "Summarizing Statistical Information" on page 12-13 for more information.

# **Summarizing Statistical Information**

A variety of statistics are available for summaries of condition and state profiles.

#### **Condition Summaries**

The following statistics are provided for condition profile summaries:

- The number of matches summarized
- The minimum time gap between matches and the ordinal trace event number (offset) where it began
- The maximum time gap between matches and the ordinal trace event number (offset) where it began
- The average time gap between matches

#### **State Summaries**

The following statistics are generated for state profile summaries:

- The number of matches summarized
- The minimum time gap between matches and the ordinal trace event number (offset) where it began
- The maximum time gap between matches and the ordinal trace event number (offset) where it began
- The average time gap between matches
- The sum of the time gaps between matches
- The minimum time duration of a match and the ordinal trace event number (offset) where it began
- The maximum time duration of a match and the ordinal trace event number (offset) where it began
- The average time duration of a match
- The sum of the time durations of matches

# **Summary Scripts**

Summary results are printed by invoking summary scripts to display the statistical information. By default, NightTrace provides an event summary and a state summary script that print the statistics as described above.

User-define scripts may be used in place of the default scripts. See "Output Script" on page 12-11 for more information on specifying user-defined scripts.

# **Summary Script Environment Variables**

The following summary environment variables are passed to summary scripts

**Table 11-2. Summary Script Environment Variables** 

Variable	Meaning
NT_SUM_TYPE	Contains text describing the type of summary: "Event Summary" or "State Summary".
NT_SUM_NUM	The number of occurrences of the state or event, expressed in decimal integer format.
NT_SUM_MIN_GAP	The minimum gap between occurrences of the state or event, expressed in seconds in decimal floating point format.
NT_SUM_MAX_GAP	The maximum gap between occurrences of the state or event, expressed in seconds in decimal floating point format.
NT_SUM_AVG_GAP	The average gap between occurrences of the state or event, expressed in seconds in decimal floating point format.
NT_SUM_TOTAL_GAP	The total time for all gaps between occurrences of the state or event, expressed in seconds in decimal floating point format.
NT_SUM_MIN_GAP_OFFSET	The offset at which the minimum gap between occurrences of the state or event occurred expressed in decimal integer format.
NT_SUM_MAX_GAP_OFFSET	The offset at which the maximum gap between occurrences of the state or event occurred expressed in decimal integer format.
NT_SUM_MIN_DURATION	For states, the minimum state duration expressed in seconds in decimal floating point format.
NT_SUM_MAX_DURATION	For states, the maximum state duration expressed in seconds in decimal floating point format.
NT_SUM_AVG_DURATION	For states, the average state duration expressed in seconds in decimal floating point format.

**Table 11-2. Summary Script Environment Variables** 

Variable	Meaning
NT_SUM_TOTAL_DURATION	For states, the total of all state durations, expressed in seconds in decimal floating point format.
NT_SUM_MIN_DURATION_OFFSET	For states, the offset at which the minimum state duration occurred, expressed in decimal integer format.
NT_SUM_MAX_DURATION_OFFSET	For states, the offset at which the maximum state duration occurred, expressed in decimal integer format.

# **Event Descriptions Panel**

The Event Descriptions panel presents a table with a row for each known event ID. The table describes the event name and description associated with each event ID.




Figure 13-1. Event Descriptions Panel

The table can be sorted by clicking on a column header. Subsequent clicks on a column header cell that is already defined as the sort key (as indicated by the dark-red chevron), causes the sort direction to reverse.

The table consists of the following columns.

#### Code

This column contains the event ID of interest.

#### Name

This column defines the textual name that will be displayed in lieu of the event ID.

#### Description

This column describes the format of the textual description used for the event.

Pressing the Add... or Edit buttons launches the Event Description dialog which allows you to change these values.



Figure 13-2. Event Description Dialog

The Description field allows you to use the NightTrace format() function to define a (possibly complex) textual description of the event and its arguments.

The Tags List panel presents a table of all tagged events in the current NightTrace session.




Figure 14-1. Tags List Panel

Tags are a convenient mechanism of identifying an event or time of interest.

Tags appears as small yellow notes with the tag's number on the ruler of Timelines.

Tags are saved as part of NightTrace sessions, so they can be useful in quickly locating an event of interest in subsequent execution of NightTrace on the same data set.

The notation capability allows you to add explanatory text for a tag and to share it with others by saving the session and directing another user to look for a specific tag name.

# **Creating Tags**

You can create a tag using one of the following three methods:

- 1. Double-click on any row in an Events panel; the tag will be associated with the time of the event whose row you double-clicked.
- 2. Double-click on any event in an EventGraph in a Timeline; the tag will be associated with the time of the event you double-clicked.
- 3. Double-click on a ruler in a Timeline -- the tag will be associated with the time associated with the location you clicked in the ruler.

# **Tags List Table**

Clicking on a row in the Tags List table causes the current timeline to be moved to the time associated with the tag.

The Tags List table consists of the following columns:

#### Tag

This column shows the name of the tag.

ID

This column shows the tag's integer ID value.

#### **Tag Time**

This column shows the time of the tag.

#### **Near Offset**

This column shows the ordinal offset of the nearest event.

#### **From Current**

This column shows the time between the tag and the current timeline.

Since the current timeline is always moved to the time associated with the tag you click in the table, its From Current value will often be zero (unless you change the location of the current timeline with some other operation -- e.g. executing a search or clicking in a Timeline panel).

#### **Notation**

The notation field is free-form text which you can provide.

## **Context Menu**

The Tags List panel context menu is shown below.



Figure 14-2. Tags List Panel Context Menu

#### Annotate...

This option opens a simple dialog which lets you add or change the notation associated with the selected tag. This option is disabled if multiple tags are currently selected.

#### Delete

This option deletes all currently selected tags.

#### **Delete All**

This option deletes all tags in the current session.

#### **Display Fields**

This option displays a sub-menu which allows you to select which columns are visible within the table.



# **Control Buttons**

The Annotate... and Delete buttons operate on the currently selected tags in the table (the Annotate... button is disabled if more than one tag is selected).

The Delete All button deletes all tags from the current session.

# **Using Expressions**

## **Overview**

NightTrace allows you to use expressions to aid in the analysis of trace data.

NightTrace expressions are comprised of a combination of *operators* and *operands* and can evaluate to numbers, strings, or boolean values.

See "Operators" on page 15-1 for a list of valid operators and "Operands" on page 15-1 for a discussion of valid operands.

# **Operators**

Operators in NightTrace expressions include:

- arithmetic operators: (), \*, /, % (modulo), +, -, unary -
- shift operators: <<, >>
- bitwise operators: ~ (not), & (and), ^ (exclusive or), | (or)
- logical operators: ! (not), && (and), | | (or)
- relational operators: <, <=, >, >=, == (equivalence), != (non-equivalence)
- conditional operator: expr? true\_value: false\_value
- unary cast operations for the following supported data types (where the parentheses are required):
  - (long long)
  - (long double)
  - (unsigned long)
  - (unsigned long long)

NightTrace operators follow the operator precedence rules of the C programming language.

# **Operands**

Operands include:

• "Constants" on page 15-2

- "Functions" on page 15-4
- "Profile References" on page 15-181 (in functions only)

Operand types are largely based on the C programming language and include:

- integer
- long integer
- · long long integer
- double-precision floating point
- long double-precision floating point
- character
- string
- boolean
- bit fields

## **Constants**

Constants are one type of operand that may be used in NightTrace expressions.

Integer literals may be expressed using typical C language notation:

- decimal literals have no special prefix
- octal literals begin with a zero
- hexadecimal literals begin with a 0x

Floating point literals are always considered to be double-precision floating point literals.

Standard C decimal floating point literals are supported and have the following syntax:

$$fore.aft[E|e[+|-]exp]$$

fore . aft

any combination of decimal digits 0 through 9

E or e

can optionally precede an optional sign and exponent

+ or -

optional sign

exp

a decimal number specifying the power of 10 to which fore . aft is multiplied

Alternatively, floating point literals following the C99 standard are also supported and have the following syntax:

$$0 \times fore.aft [P | p[+ |-]exp]$$

0x

defines this as a hexadecimal literal

fore.aft

any combination of hexadecimal digits 0 through 9, a through f, or A through F.

Porp

can optionally precede an optional sign and exponent

+ or -

optional sign

exp

a decimal number specifying the power of 2 to which fore . aft is multiplied

String literals must be enclosed within double quotes; to include a double quote in a constant string literal, precede the double quote with a backslash character. For example:

The case-insensitive boolean constants TRUE and FALSE have the values 1 and 0, respectively.

Table 15-1 shows units and suffixes for time constants.

Table 15-1. Time Units and Constant Suffixes

Time Unit	Suffix
Seconds (This is the default)	S
Milliseconds (10e-3 seconds)	ms
Microseconds (10e-6 seconds)	us
Nanoseconds (10e-9 seconds)	ns

## **Functions**

Functions are pre-defined NightTrace entities that may be used in an *expression*. NightTrace defines five classes of functions:

- "String Functions" on page 15-17
- "Trace Event Functions" on page 15-19
- "State Functions" on page 15-58
- "Offset Functions" on page 15-130
- "Summary Functions" on page 15-165
- "Format and Table Functions" on page 15-172

The general syntax of all function calls except summary, format, and table functions is as follows. (Optional parts of function calls are in brackets ([]).)

```
function_name[([parameter])]
```

The prefix of the function\_name determines its class as follows:

```
offset_
```

Functions with this prefix provide information about the trace event at the specified *offset* (or ordinal trace event number). See "Offset Functions" on page 15-130.

```
start
```

Functions with this prefix provide information about the *start event* of the *most recent instance of a state*. See "Start Functions" on page 15-58.

end

Functions with this prefix provide information about the *end event* of the *last completed instance of a state* See "End Functions" on page 15-92.

```
state
```

Functions with this prefix provide information about instances of states. See "Multi-State Functions" on page 15-126.

```
event_
```

Functions with this prefix provide information about instances of events. See "Multi-Event Functions" on page 15-56.

Some functions can be optionally suffixed by a number, N, which specifies the Nth argument logged with the trace event. N defaults to 1 and can have the values 1 through the maximum argument logged. For example,

```
arg()
```

Returns the first argument

arg1()

Returns the first argument

arg3()

Returns the third argument

start\_id()

Returns a trace event ID

state\_gap()

Returns the time between instances of a state

Table 15-1 contains a complete list of functions sorted by general catagories. For an alphabetic list of all functions, refer to the Index.

Table 15-1. NightTrace Functions

Syntax	Return Type
strcmp $(s1, s2)$ strncmp $(s1, s2, n)$	An integer indicating less than, equal to, or greater than zero as $s1$ , or the first $n$ bytes thereof, is compared to $s2$ .
id [([PR])] start_id [([PR])] end_id [([PR])] offset_id (offset_expr)	The integer trace event ID.
arg[N] [([PR])] start_arg[N] [([PR])] end_arg[N] [([PR])] offset_arg[N] (offset_expr)	The integer trace event argument.
arg[N]_dbl [([PR])] start_arg[N]_dbl [([PR])] end_arg[N]_dbl [([PR])] offset_arg[N]_dbl (offset_expr)	The double-precision floating point <i>trace</i> event argument.
$\begin{array}{c} \operatorname{arg}[N]\_\operatorname{long}\left[([PR])\right] \\ \operatorname{start\_arg}[N]\_\operatorname{long}\left[([PR])\right] \\ \operatorname{end\_arg}[N]\_\operatorname{long}\left[([PR])\right] \\ \operatorname{offset\_arg}[N]\_\operatorname{long}\left(offset\_expr\right) \end{array}$	The long integer trace event argument.
arg[N]_long_dbl [([PR])] start_arg[N]_long_dbl [([PR])] end_arg[N]_long_dbl [([PR])] offset_arg[N]_long_dbl (offset_expr)	The long double-precision trace event argument.
$\begin{split} & \arg[N]\_long\_long[([PR])] \\ & \text{start\_arg}[N]\_long\_long[([PR])] \\ & \text{end\_arg}[N]\_long\_long[([PR])] \\ & \text{offset\_arg}[N]\_long\_long(offset\_expr) \end{split}$	The long long integer trace event argument.

**Table 15-1. NightTrace Functions** 

Syntax	Return Type
blk_arg(byte_offset[,PR]) start_blk_arg(byte_offset[,PR]) end_blk_arg(byte_offset[,PR]) offset_blk_arg(byte_offset,offset_expr)	The integer <i>trace event argument</i> at a particular byte offset in the argument space.
blk_arg_bits (byte_offset, bit_offset, bit_size[, PR]) start_blk_arg_bits (byte_offset, bit_offset, bit_size[, PR]) end_blk_arg_bits (byte_offset, bit_offset, bit_size[, PR]) offset_blk_arg_bits (byte_offset, bit_offset, bit_size, offset_expr)	The integer <i>trace event argument</i> extracted as a signed bit field with a particular byte offset, bit offset, and bit size in the argument space.
blk_arg_char (byte_offset[,PR]) start_blk_arg_char (byte_offset[,PR]) end_blk_arg_char (byte_offset[,PR]) offset_blk_arg_char (byte_offset, offset_expr)	The signed character <i>trace event argument</i> at a particular byte offset in the argument space.
blk_arg_dbl (byte_offset[,PR]) start_blk_arg_dbl (byte_offset[,PR]) end_blk_arg_dbl (byte_offset[,PR]) offset_blk_arg_dbl (byte_offset, offset_expr)	The double-precision <i>trace event argument</i> at a particular byte offset in the argument space.
blk_arg_flt (byte_offset[,PR]) start_blk_arg_flt (byte_offset[,PR]) end_blk_arg_flt (byte_offset[,PR]) offset_blk_arg_flt (byte_offset, offset_expr)	The single-precision <i>trace event argument</i> at a particular byte offset in the argument space.
blk_arg_long(byte_offset[,PR]) start_blk_arg_long(byte_offset[,PR]) end_blk_arg_long(byte_offset[,PR]) offset_blk_arg_long(byte_offset,offset_expr)	The long integer <i>trace event argument</i> at a particular byte offset in the argument space.
blk_arg_long_bits (byte_offset[,PR]) start_blk_arg_long_bits (byte_offset[,PR]) end_blk_arg_long_bits (byte_offset[,PR]) offset_blk_arg_long_bits (byte_offset, offset_expr)	The long integer <i>trace event argument</i> extracted as a signed bit field with a particular byte offset, bit offset, and bit size in the argument space.
blk_arg_long_dbl (byte_offset[,PR]) start_blk_arg_long_dbl (byte_offset[,PR]) end_blk_arg_long_dbl (byte_offset[,PR]) offset_blk_arg_long_dbl (byte_offset, offset_expr)	The long double-precision <i>trace event argument</i> at a particular byte offset in the argument space.
blk_arg_long_long (byte_offset[,PR]) start_blk_arg_long_long (byte_offset[,PR]) end_blk_arg_long_long (byte_offset[,PR]) offset_blk_arg_long_long (byte_offset, offset_expr)	The long long integer <i>trace event argument</i> at a particular byte offset in the argument space.
blk_arg_long_ubits (byte_offset[,PR]) start_blk_arg_long_ubits (byte_offset[,PR]) end_blk_arg_long_ubits (byte_offset[,PR]) offset_blk_arg_long_ubits (byte_offset,offset_expr)	The long integer <i>trace event argument</i> extracted as an unsigned bit field with a particular byte offset, bit offset, and bit size in the argument space.

**Table 15-1. NightTrace Functions** 

Syntax	Return Type
blk_arg_short (byte_offset[,PR]) start_blk_arg_short (byte_offset[,PR]) end_blk_arg_short (byte_offset[,PR]) offset_blk_arg_short (byte_offset, offset_expr)	The short integer <i>trace event argument</i> at a particular byte offset in the argument space.
blk_arg_string (byte_offset, max_size[,PR]) start_blk_arg_string (byte_offset, max_size[,PR]) end_blk_arg_string (byte_offset, max_size[,PR]) offset_blk_arg_string (byte_offset, max_size, offset_expr)	The null-byte terminated string <i>trace event</i> argument at a particular byte offset in the argument space.
blk_arg_ubits (byte_offset, bit_offset, bit_size[, PR]) start_blk_arg_ubits (byte_offset, bit_offset, bit_size[, PR]) end_blk_arg_ubits (byte_offset, bit_offset, bit_size[, PR]) offset_blk_arg_ubits (byte_offset, bit_offset, bit_size, offset_expr)	The integer <i>trace event argument</i> extracted as an unsigned bit field with a particular byte offset, bit offset, and bit size in the argument space.
blk_arg_uchar (byte_offset[,PR]) start_blk_arg_uchar (byte_offset[,PR]) end_blk_arg_uchar (byte_offset[,PR]) offset_blk_arg_uchar (byte_offset,offset_expr)	The unsigned character <i>trace event argument</i> at a particular byte offset in the argument space.
blk_arg_uint (byte_offset[,PR]) start_blk_arg_uint (byte_offset[,PR]) end_blk_arg_uint (byte_offset[,PR]) offset_blk_arg_uint (byte_offset[,PR])	The unsigned integer <i>trace event argument</i> at a particular byte offset in the argument space, converted to type long.
blk_arg_ulong_long(byte_offset[,PR]) start_blk_arg_ulong_long(byte_offset[,PR]) end_blk_arg_ulong_long(byte_offset[,PR]) offset_blk_arg_ulong_long(byte_offset[,PR])	The unsigned long long integer <i>trace event</i> argument at a particular byte offset in the argument space.
blk_arg_ushort (byte_offset[,PR]) start_blk_arg_ushort (byte_offset[,PR]) end_blk_arg_ushort (byte_offset[,PR]) offset_blk_arg_ushort (byte_offset,offset_expr)	The unsigned short integer <i>trace event argument</i> at a particular byte offset in the argument space.
num_args [([PR])] start_num_args [([PR])] end_num_args [([PR])] offset_num_args (offset_expr)	The number of arguments associated with a trace event.
cuda [([ <i>PR</i> ])]	Returns one if the event is a CUDA GPU event, otherwise zero. See "NightTrace CUDA Tracing API" on page 2-32.
cuda_warp [([PR])]	Returns the warp ID of the event. See "NightTrace CUDA Tracing API" on page 2-32.

**Table 15-1. NightTrace Functions** 

Syntax	Return Type
${\tt cuda\_sm}\left[([PR]) ight]$	Returns the GPU symmetric multiprocessor (SM) ID that logged the event. See "Night-Trace CUDA Tracing API" on page 2-32.
cuda_lane [([PR])]	Returns the ID of the lane that logged the event. See "NightTrace CUDA Tracing API" on page 2-32.
cuda_thr_x [([ <i>PR</i> ])]	Returns the index in the X dimension of the CUDA thread that logged the event. See "NightTrace CUDA Tracing API" on page 2-32.
cuda_thr_y [([ <i>PR</i> ])]	Returns the index in the Y dimension of the CUDA thread that logged the event. See "NightTrace CUDA Tracing API" on page 2-32.
cuda_thr_z [([ <i>PR</i> ])]	Returns the index in the Z dimension of the CUDA thread that logged the event. See "NightTrace CUDA Tracing API" on page 2-32.
cuda_blk_x [([ <i>PR</i> ])]	Returns the index in the X dimension of the CUDA block that logged the event. See "NightTrace CUDA Tracing API" on page 2-32.
cuda_blk_y [([ <i>PR</i> ])]	Returns the index in the Y dimension of the CUDA thread that logged the event. See "NightTrace CUDA Tracing API" on page 2-32.
cuda_blk_z [([ <i>PR</i> ])]	Returns the index in the Z dimension of the CUDA block that logged the event. See "NightTrace CUDA Tracing API" on page 2-32.
${\tt cuda\_time}\left[\left(\left[PR ight] ight) ight]$	Returns the raw clock value of the GPU symmetric processor at the time the event was logged. See "NightTrace CUDA Tracing API" on page 2-32.
<pre>pid [([PR])]     start_pid [([PR])]     end_pid [([PR])]     offset_pid (offset_expr)</pre>	The integer process identifier (PID) associated with a trace event.
thread_id[([PR])] start_thread_id[([PR])] end_thread_id[([PR])] offset_thread_id(offset_expr)	The integer <i>thread</i> identifier ( <i>thread ID</i> ) associated with a <i>trace event</i> .

**Table 15-1. NightTrace Functions** 

Syntax	Return Type
tid [([PR])] start_tid [([PR])] end_tid [([PR])] offset_tid (offset_expr)	The integer NightTrace thread identifier ( <i>TID</i> ) associated with a <i>trace event</i> .
$\begin{array}{c} \texttt{time}\left[([PR])\right]\\ \texttt{start\_time}\left[([PR])\right]\\ \texttt{end\_time}\left[([PR])\right]\\ \texttt{offset\_time}\left(\textit{offset\_expr}\right) \end{array}$	The double-precision floating point time, expressed in units of seconds, between a <i>trace event</i> and the earliest trace event from all <i>trace event files</i> currently in use.
node_id [([PR])] start_node_id [([PR])] end_node_id [([PR])] offset_node_id (offset_expr)	The internally-assigned integer <i>node identi-</i> <i>fier</i> associated with a <i>trace event</i> .
node_name [([PR])] start_node_name [([PR])] end_node_name [([PR])] offset_node_name (offset_expr)	The string describing the name of the system from which a <i>trace event</i> was logged.
process_name[([PR])] offset_process_name(offset_expr)	The string describing the name of the process ( <i>PID</i> ) associated with a <i>trace event</i> .
$\label{thread_name}  \begin{tabular}{ll} thread\_name [([PR])] \\ offset\_thread\_name (offset\_expr) \\ \end{tabular}$	The string describing the name of the C <i>thread</i> associated with a <i>trace event</i> .
event_gap [([PR])] state_gap [([PR])]	The double-precision floating point time, expressed in units of seconds, between the instances of either a <i>trace event</i> or a <i>state</i> .
state_dur[([ <i>PR</i> ])]	The double-precision floating point time, expressed in units of seconds, of an instance of a <i>state</i> .
event_matches $[([PR])]$ state_matches $[([PR])]$ summary_matches $[()]$	The integer number of instances of either a <i>trace event</i> or a <i>state</i> .
state_status [([PR])]	The boolean status of a <i>state</i> ; true if the <i>current time line</i> is within an instance of the state, false otherwise. See "state_status()" on page 15-129 for important details.
$\begin{array}{c} \text{offset}\left[\left([PR]\right)\right] \\ \text{start\_offset}\left[\left([PR]\right)\right] \\ \text{end\_offset}\left[\left([PR]\right)\right] \end{array}$	The integer ordinal number (offset) of a trace event.
min_offset(expr) max_offset(expr)	The integer ordinal number (offset) of a trace event associated with a minimum or maximum occurrence of expr.
min (expr) max (expr) avg (expr) sum (expr)	The minimum, maximum, average, or sum of <i>expr</i> values before the <i>current time</i> . The return type is that of <i>expr</i> .

Table 15-1. NightTrace Functions

Syntax	Return Type
get_string(table_name[, int_expr])	The character string associated with item int_expr in string table table_name.
get_item(table_name, "str_const")	The first integer item number associated with string <i>str_const</i> in string table <i>table_name</i> .
get_format(table_name[, int_expr])	The character string associated with item int_expr in format table table_name.
format ("format_string" [, arg])	A character string to format and display.

## **Function Parameters**

If the function has a *parameter*, the parentheses are required. Otherwise, they are optional. For example,

arg2

No parentheses are required

arg2()

No parentheses are required

arg2(Myprof)

Parentheses are required

In many functions, the *parameter* is optional because it can be inferred from context. For trace event functions, the *current trace event* is used if the parameter is omitted. For state functions, the state being defined is used if the parameter is omitted. (Thus, state functions without parameters can only be used inside state definitions). For example,

arg1()

Operates on the current trace event

arg1(my\_cond)

Operates on the profile reference my\_cond

end\_arg1()

Operates on the *last completed instance* of the state being defined and can only appear within a state definition

```
end_arg1(my_state)
```

Operates on the *last completed instance* of the state defined by the *profile reference* my\_state

This manual uses the following conventions for function parameters:

PR

A user-defined *profile reference*. If supplied, the function applies to the specified profile. For more information, see "Profiles Dialog" on page 12-2.

offset\_expr

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

expr

Any valid NightTrace expression (see "Overview" on page 15-1).

table name

An unquoted character string that represents the name of a *string table* or *format table*.

int\_expr

An integer expression that acts as an index into the specified *string table* or *format table*. *int\_expr* must either match an identifying integer value in the *table\_name* table, or the *table\_name* table must have a default item line.

str\_const

A string constant literal that acts as an index into the specified *string table*.

format\_string

A character string that contains literal characters and conversion specifications. Conversion specifications modify zero or more *args*.

arg

An optional expression to be formatted and displayed.

#### **NOTE**

NightTrace does not perform semantic error checking of functions. For example, if you ask for information about the second argument, but no second argument was logged, NightTrace does not tell you. Similarly, NightTrace does not flag the use of undefined *profile references*.

# **Function Terminology**

In order to use the NightTrace functions effectively, it may be useful to understand some of the concepts associated with them.

A *trace event* represents a user-defined event, logged with optional data arguments. Events are given discrete numbers to identify them; this number is called the *trace event ID*. A *state* is defined to be the interval of time between two specific events.

The descriptions of the functions further speak in terms of "instances" of states. These are best defined as:

#### current instance

The instance of a state which has begun but has not yet completed. Thus, the *current time line* would be positioned within the region from the *start event* up to, but not including, the *end event*.

#### last completed instance

The most recent instance of a state that has already completed. Thus, the *current time line* would be positioned either on, or after, the *end event* for a state.

#### most recent instance

If the *current time line* is positioned within a current instance of a state, then it is that instance of the state. Otherwise, it is the last completed instance of a state.

Figure 15-1 illustrates some of these concepts with a State Graph.




Figure 15-1. Function Terminology Illustrated

A more detailed example is illustrated in Figure 15-2.




Figure 15-2. States and Events

The following discusses the terminology with respect to **time line x**, **time line y**, and **time line z**.

Assuming the current time line was positioned at **time line x** in Figure 15-2, the various "instances" would be defined as:

current instance

No current instance is defined since the current time line is not positioned within any instance of a state.

last completed instance

Instance B

most recent instance

Instance B. Since the current time line is not positioned within any instance of a state, the most recent instance is the last completed instance.

The table below indicates the information returned by various NightTrace functions assuming the current time line was positioned at **time line x** in Figure 15-2.

.

state_status()	false	The current time line was not positioned within a current instance of a state.
<pre>state_gap()</pre>	~0.000020	The duration of time in seconds between event b and event c. The function operated the most recent instance of the state (instance B) and the immediately preceding instance (instance A).
state_dur()	~0.000090	The duration of time in seconds between event c and event d. The function operated on the last completed instance of the state (instance B).
state_matches()	2	Assuming no other instances of the state preceded those shown in the figure. The function operated on all completed instances of the state (which included instances A and B).
start_time()	~1.631750	The time associated with event c. The function operated on the most recent instance of the state (instance B).
end_time()	~1.631840	The time associated with event d. The function operated on the last completed instance of the state (instance B).

Assuming the current time line was positioned at **time line y** in Figure 15-2, the various "instances" would be defined as:

current instance

Instance C

last completed instance

Instance B

most recent instance

Instance C

The table below indicates the information returned by various NightTrace functions assuming the current time line was positioned at **time line y** in Figure 15-2.

state_status()	true	The current time line was positioned inside a current instance of the state (instance C).
state_gap()	~0.000030	The duration of time in seconds between event d and event e. The function operated on the most recent instance of the state (instance C) and the immediately preceding instance (instance B).
state_dur()	~0.000090	The duration of time in seconds between event c and event d. The function operated on the last completed instance of the state (instance B).
state_matches()	2	Assuming no other instances of the state preceded those shown in the figure. The function operated on all completed instances of the state (which included instances A and B).
start_time()	~1.631870	The time associated with event e. The function operated on the most recent instance of the state (instance C).
end_time()	~1.631840	The time associated with event d. The function operated on the last completed instance of the state (instance B).

Assuming the current time line was positioned at **time line z** in Figure 15-2, the various "instances" would be defined as:

current instance

No current instance is defined since the current time line is positioned on the *end event* of an instance of a state.

last completed instance

Instance C

most recent instance

Instance C

The table below indicates the information returned by various NightTrace functions assuming the current time line was positioned at **time line z** in Figure 15-2.

.

T	1	
state_status()	false	The current time line was not positioned inside a current instance of the state. Even though the current time line is positioned on an <i>end event</i> of the state (event f), the corresponding instance is said to have already completed.
state_gap()	~0.000030	The duration of time in seconds between event d and event e. The function operated on the most recent instance of the state (instance C) and the immediately preceding instance (instance B).
state_dur()	~0.000040	The duration of time in seconds between event e and event f. The function operated on the last completed instance of the state (instance C).
state_matches()	3	Assuming no other instances of the state preceded those shown in the figure. The function operated on all completed instances of the state (which included instances A, B, and C).
start_time()	~1.631870	The time associated with event e. The function operated on the most recent instance of the state (instance C).
end_time()	~1.631910	The time associated with event f. The function operated on the last completed instance of the state (instance C).

# **String Functions**

The string functions compare two strings. They include the following:

- strcmp()
- strncmp()

# strcmp()

#### **DESCRIPTION**

The strcmp() function compares the two strings, sI and s2. It returns an integer less than, equal to, or greater than zero if sI is found, respectively, to be less than, to match, or be greater than s2.

#### **SYNTAX**

```
strcmp(s1, s2);
```

#### **PARAMETERS**

s1

The string to be compared to s2

*s*2

The string to be compared to s1

#### **RETURN TYPE**

integer

#### **SEE ALSO**

• "strncmp()" on page 15-18

# strncmp()

#### **DESCRIPTION**

The strncmp() function is similar to strcmp() in that it compares two strings, sI and s2, and returns an integer less than, equal to, or greater than zero if sI is found, respectively, to be less than, to match, or be greater than s2. However, strncmp() only compares the first (at most) n bytes of sI and s2.

#### **SYNTAX**

```
strncmp(s1, s2) n;
```

#### **PARAMETERS**

s1

The string to be compared to s2

*s*2

The string to be compared to s1

n

The maximum number of bytes in s1 and s2 to be compared

#### **RETURN TYPE**

integer

#### **SEE ALSO**

• "strcmp()" on page 15-17

### **Trace Event Functions**

The trace event functions operate on either the *profile reference* specified to that function or the *current trace event*. They include the following:

- id
- arg
- arg\_dbl()
- arg\_long()
- arg\_long\_dbl()
- arg\_long\_long()
- blk\_arg()
- blk\_arg\_bits()
- blk\_arg\_char()
- blk\_arg\_dbl()
- blk\_arg\_flt()
- blk\_arg\_long()
- blk\_arg\_long\_bits()
- blk\_arg\_long\_dbl()
- blk\_arg\_long\_long()
- blk\_arg\_long\_ubits()
- blk\_arg\_short()
- blk\_arg\_string()
- blk\_arg\_ubits()
- blk\_arg\_uchar()
- blk\_arg\_uint()
- blk\_arg\_ulong\_long()
- blk\_arg\_ushort()
- cuda()
- cuda\_warp()
- cuda\_sm()
- cuda\_lane()
- cuda\_thr\_y()
- cuda\_thr\_y()

- cuda\_thr\_z()
- cuda\_blk\_x()
- cuda\_blk\_y()
- cuda\_blk\_z()
- cuda\_time()
- num\_args()
- pid()
- cpu()
- thread\_id()
- tid()
- offset()
- time()
- node\_id()
- node\_name()
- process\_name()
- thread\_name()
- Multi-event functions

# id()

## **DESCRIPTION**

The id() function returns the *trace event ID* of the last instance of a *trace event*.

### **SYNTAX**

 $\mathrm{id}\left[\left(\left[PR\right]\right)\right]$ 

## **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, the function returns the *trace event ID* of the last instance of the trace event which satisfies the conditions of the specified specified profile. If omitted, the function returns the *trace event ID* of the current trace event. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

integer

- "start\_id()" on page 15-59
- "end\_id()" on page 15-94
- "offset\_id()" on page 15-132

# arg()

## **DESCRIPTION**

The arg() function returns the value of a particular *trace event argument*.

### **SYNTAX**

arg[N][([PR])]

### **PARAMETERS**

N

Specifies the Nth argument logged with the trace event. Defaults to 1.

PR

A user-defined *profile reference*. If supplied, the function returns the specified argument for the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the specified argument for the *current trace event*. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

integer

- "arg\_long()" on page 15-24
- "arg\_dbl()" on page 15-23
- "arg\_long\_long()" on page 15-26
- "arg\_long\_dbl()" on page 15-25
- "num\_args()" on page 15-44
- "start\_arg()" on page 15-61
- "end\_arg()" on page 15-95
- "offset\_arg()" on page 15-133

# arg\_dbl()

## **DESCRIPTION**

The arg\_dbl() function returns the value of a particular *trace event argument*.

### **SYNTAX**

 $arg[N]_dbl[([PR])]$ 

### **PARAMETERS**

N

Specifies the Nth argument logged with the trace event. Defaults to 1.

PR

A user-defined *profile reference*. If supplied, the function returns the specified argument for the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the specified argument for the *current trace event*. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

double-precision floating point

- "arg()" on page 15-22
- "arg\_long()" on page 15-24
- "num\_args()" on page 15-44
- "start\_arg\_dbl()" on page 15-62
- "end\_arg\_dbl()" on page 15-96
- "offset\_arg\_dbl()" on page 15-134

# arg\_long()

## **DESCRIPTION**

The arg\_long() function returns the value of a particular *trace event argument*.

### **SYNTAX**

arg[N]\_long[([PR])]

### **PARAMETERS**

N

Specifies the Nth argument logged with the trace event. Defaults to 1.

PR

A user-defined *profile reference*. If supplied, the function returns the specified argument for the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the specified argument for the *current trace event*. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

double-precision floating point

- "arg()" on page 15-22
- "num\_args()" on page 15-44
- "start\_arg\_long()" on page 15-63
- "end\_arg\_long()" on page 15-97
- "offset\_arg\_long()" on page 15-135

## arg\_long\_dbl()

## **DESCRIPTION**

The arg\_long\_dbl() function returns the value of a particular *trace event argument*.

## **SYNTAX**

arg[N]\_long\_dbl[([PR])]

### **PARAMETERS**

N

Specifies the *N*th argument logged with the *trace event*. Defaults to 1.

PR

A user-defined *profile reference*. If supplied, the function returns the specified argument for the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the specified argument for the *current trace event*. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

long double-precision floating point

- "arg()" on page 15-22
- "num\_args()" on page 15-44
- "start\_arg\_long\_dbl()" on page 15-64
- "end\_arg\_long\_dbl()" on page 15-98
- "offset\_arg\_long\_dbl()" on page 15-136

# arg\_long\_long()

## **DESCRIPTION**

The arg\_long\_long() function returns the value of a particular *trace event argument*.

## **SYNTAX**

arg[N]\_long\_long[([PR])]

### **PARAMETERS**

N

Specifies the Nth argument logged with the trace event. Defaults to 1.

PR

A user-defined *profile reference*. If supplied, the function returns the specified argument for the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the specified argument for the *current trace event*. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

long long integer

- "arg()" on page 15-22
- "num\_args()" on page 15-44
- "start\_arg\_long\_long()" on page 15-65
- "end\_arg\_long\_long()" on page 15-99
- "offset\_arg\_long\_long()" on page 15-137

## blk\_arg()

## **DESCRIPTION**

The blk\_arg() function returns the value of a trace event argument located at a particular byte offset in the argument space associated with an event.

## **SYNTAX**

blk\_arg(byte\_offset[,PR])

## **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, the function returns the specified argument for the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the specified argument for the *current trace event*. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "start\_blk\_arg()" on page 15-66
- "end\_blk\_arg()" on page 15-100
- "offset\_blk\_arg()" on page 15-138

## blk\_arg\_bits()

### **DESCRIPTION**

The blk\_arg\_bits() function returns the value of a trace event signed bit field argument located at a particular byte and bit offset with a particular bit size in the argument space associated with an event.

### **SYNTAX**

blk\_arg\_bits (byte\_offset, bit\_offset, bit\_size[, PR])

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

bit offset

Specifies the bit offset of the argument recorded with the *trace\_event\_blk*.

bit size

Specifies the size in bits of the argument record with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, the function returns the specified argument for the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the specified argument for the *current trace event*. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "start\_blk\_arg\_bits()" on page 15-67
- "end\_blk\_arg\_bits()" on page 15-101
- "offset\_blk\_arg\_bits()" on page 15-139

## blk\_arg\_char()

## **DESCRIPTION**

The blk\_arg\_char() function returns the value of a trace event signed character argument located at a particular byte offset in the argument space associated with an event.

### **SYNTAX**

blk\_arg\_char (byte\_offset[,PR])

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

PR

A user-defined *profile reference*. If supplied, the function returns the specified argument for the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the specified argument for the *current trace event*. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "start\_blk\_arg\_char()" on page 15-68
- "end\_blk\_arg\_char()" on page 15-102
- "offset\_blk\_arg\_char()" on page 15-140

## blk\_arg\_dbl()

### **DESCRIPTION**

The blk\_arg\_dbl() function returns the value of a trace event double-precision floating point argument located at a particular byte offset in the argument space associated with an event.

### **SYNTAX**

blk\_arg\_dbl (byte\_offset[, PR])

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

PR

A user-defined *profile reference*. If supplied, the function returns the specified argument for the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the specified argument for the *current trace event*. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

double-precision floating point

- "num\_args()" on page 15-44
- "start\_blk\_arg\_dbl()" on page 15-69
- "end\_blk\_arg\_dbl()" on page 15-103
- "offset\_blk\_arg\_dbl()" on page 15-141

## blk\_arg\_flt()

## **DESCRIPTION**

The blk\_arg\_flt() function returns the value of a trace event single-precision floating point argument located at a particular byte offset in the argument space associated with an event.

### **SYNTAX**

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

PR

A user-defined *profile reference*. If supplied, the function returns the specified argument for the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the specified argument for the *current trace event*. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

double-precision floating point

- "num\_args()" on page 15-44
- "start\_blk\_arg\_flt()" on page 15-70
- "end\_blk\_arg\_flt()" on page 15-104
- "offset\_blk\_arg\_flt()" on page 15-142

# blk\_arg\_long()

## **DESCRIPTION**

The blk\_arg\_long() function returns the value of a trace event long integer argument located at a particular byte offset in the argument space associated with an event.

### **SYNTAX**

blk\_arg\_long(byte\_offset[,PR])

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

PR

A user-defined *profile reference*. If supplied, the function returns the specified argument for the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the specified argument for the *current trace event*. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

long integer

- "num\_args()" on page 15-44
- "start\_blk\_arg\_long()" on page 15-71
- "end\_blk\_arg\_long()" on page 15-105
- "offset\_blk\_arg\_long()" on page 15-143

# blk\_arg\_long\_bits()

### **DESCRIPTION**

The blk\_arg\_long\_bits() function returns the value of a trace event signed long bit field argument located at a particular byte and bit offset with a particular bit size in the argument space associated with an event.

### **SYNTAX**

blk arg long bits (byte offset, bit offset, bit size[, PR])

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

bit offset

Specifies the bit offset of the argument recorded with the *trace\_event\_blk*.

bit size

Specifies the size in bits of the argument record with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, the function returns the specified argument for the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the specified argument for the *current trace event*. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

long integer

- "num\_args()" on page 15-44
- "start\_blk\_arg\_long\_bits()" on page 15-72
- "end\_blk\_arg\_long\_bits()" on page 15-106
- "offset\_blk\_arg\_long\_bits()" on page 15-144

# blk\_arg\_long\_dbl()

### **DESCRIPTION**

The blk\_arg\_long\_dbl() function returns the value of a trace event long double-precision floating point argument located at a particular byte offset in the argument space associated with an event.

### **SYNTAX**

blk\_arg\_long\_dbl (byte\_offset[, PR])

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

PR

A user-defined *profile reference*. If supplied, the function returns the specified argument for the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the specified argument for the *current trace event*. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

long double-precision floating point

- "num\_args()" on page 15-44
- "start\_blk\_arg\_long\_dbl()" on page 15-73
- "end\_blk\_arg\_long\_dbl()" on page 15-107
- "offset\_blk\_arg\_long\_dbl()" on page 15-145

# blk\_arg\_long\_long()

## **DESCRIPTION**

The blk\_arg\_long\_long() function returns the value of a trace event long long integer argument located at a particular byte offset in the argument space associated with an event.

### **SYNTAX**

blk\_arg\_long\_long(byte\_offset[,PR])

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

PR

A user-defined *profile reference*. If supplied, the function returns the specified argument for the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the specified argument for the *current trace event*. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

long long integer

- "num\_args()" on page 15-44
- "start\_blk\_arg\_long\_long()" on page 15-74
- "end\_blk\_arg\_long\_long()" on page 15-108
- "offset\_blk\_arg\_long\_long()" on page 15-146

# blk\_arg\_long\_ubits()

### **DESCRIPTION**

The blk\_arg\_long\_ubits() function returns the value of a trace event unsigned long integer bit field argument located at a particular byte and bit offset with a particular bit size in the argument space associated with an event.

### **SYNTAX**

blk arg long ubits (byte offset, bit offset, bit size[, PR])

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

bit offset

Specifies the bit offset of the argument recorded with the *trace\_event\_blk*.

bit size

Specifies the size in bits of the argument record with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, the function returns the specified argument for the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the specified argument for the *current trace event*. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

long long integer

- "num\_args()" on page 15-44
- "start\_blk\_arg\_long\_ubits()" on page 15-75
- "end\_blk\_arg\_long\_ubits()" on page 15-109
- "offset\_blk\_arg\_long\_ubits()" on page 15-147

## blk\_arg\_short()

## **DESCRIPTION**

The blk\_arg\_short() function returns the value of a trace event short integer argument located at a particular byte offset in the argument space associated with an event.

### **SYNTAX**

blk\_arg\_short (byte\_offset[, PR])

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

PR

A user-defined *profile reference*. If supplied, the function returns the specified argument for the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the specified argument for the *current trace event*. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "start\_blk\_arg\_short()" on page 15-76
- "end\_blk\_arg\_short()" on page 15-110
- "offset\_blk\_arg\_short()" on page 15-148

# blk\_arg\_string()

### **DESCRIPTION**

The blk\_arg\_string() function returns the value of a trace event null terminated string argument located at a particular byte offset in the argument space associated with an event.

#### **SYNTAX**

blk\_arg\_string(byte\_offset, max\_size[, PR])

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk* or *trace\_event\_string*.

max\_size

Specifies the maximum length of string that might be returned. If the arguments were recorded with *trace\_event\_blk*, this is also the total number of bytes allocated in the block for the string, regardless of its actual length.

PR

A user-defined *profile reference*. If supplied, the function returns the specified argument for the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the specified argument for the *current trace event*. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

string

- "num\_args()" on page 15-44
- "start\_blk\_arg\_string()" on page 15-77
- "end\_blk\_arg\_string()" on page 15-111
- "offset\_blk\_arg\_string()" on page 15-149

## blk\_arg\_ubits()

### **DESCRIPTION**

The blk\_arg\_ubits() function returns the value of a trace event unsigned bit field argument located at a particular byte and bit offset with a particular bit size in the argument space associated with an event.

### **SYNTAX**

blk\_arg\_ubits (byte\_offset, bit\_offset, bit\_size[, PR])

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

bit offset

Specifies the bit offset of the argument recorded with the *trace\_event\_blk*.

bit size

Specifies the size in bits of the argument record with trace\_event\_blk.

PR

A user-defined *profile reference*. If supplied, the function returns the specified argument for the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the specified argument for the *current trace event*. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "start\_blk\_arg\_ubits()" on page 15-78
- "end\_blk\_arg\_ubits()" on page 15-112
- "offset\_blk\_arg\_ubits()" on page 15-150

# blk\_arg\_uchar()

### **DESCRIPTION**

The blk\_arg\_uchar() function returns the value of a trace event unsigned character argument located at a particular byte offset in the argument space associated with an event.

### **SYNTAX**

blk\_arg\_uchar (byte\_offset[, PR])

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

PR

A user-defined *profile reference*. If supplied, the function returns the specified argument for the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the specified argument for the *current trace event*. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "start\_blk\_arg\_uchar()" on page 15-79
- "end\_blk\_arg\_uchar()" on page 15-113
- "offset\_blk\_arg\_uchar()" on page 15-151

## blk\_arg\_uint()

### **DESCRIPTION**

The blk\_arg\_uint() function converts the unsigned integer trace event argument at a particular byte offset in the argument space to a long.

### **NOTE**

You can convert the long return value to an unsigned value using the cast operator. For example:

```
(unsigned long) blk_arg_uint(0) > 0x80000000
```

### **SYNTAX**

```
blk_arg_uint(byte_offset[,PR])
```

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, the function returns the specified argument for the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the specified argument for the *current trace event*. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

long

- "num\_args()" on page 15-44
- "start\_blk\_arg\_uint()" on page 15-80
- "end\_blk\_arg\_uint()" on page 15-114
- "offset\_blk\_arg\_uint()" on page 15-152

# blk\_arg\_ulong\_long()

### **DESCRIPTION**

The blk\_arg\_ulong\_long() function returns the value of a trace event unsigned long long integer argument located at a particular byte offset in the argument space associated with an event.

### **SYNTAX**

blk\_arg\_ulong\_long(byte\_offset[,PR])

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

PR

A user-defined *profile reference*. If supplied, the function returns the specified argument for the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the specified argument for the *current trace event*. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

unsigned long long integer

- "num\_args()" on page 15-44
- "start\_blk\_arg\_ulong\_long()" on page 15-81
- "end\_blk\_arg\_ulong\_long()" on page 15-115
- "offset\_blk\_arg\_ulong\_long()" on page 15-153

# blk\_arg\_ushort()

## **DESCRIPTION**

The blk\_arg\_ushort() function returns the value of a trace event unsigned short integer argument located at a particular byte offset in the argument space associated with an event.

### **SYNTAX**

blk\_arg\_ushort (byte\_offset[, PR])

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

PR

A user-defined *profile reference*. If supplied, the function returns the specified argument for the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the specified argument for the *current trace event*. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "start\_blk\_arg\_ushort()" on page 15-82
- "end\_blk\_arg\_ushort()" on page 15-116
- "offset\_blk\_arg\_ushort()" on page 15-154

# num\_args()

## **DESCRIPTION**

The num\_args() function returns the number of arguments logged with a *trace event*. For events recorded with trace\_event\_blk(), it returns the number of bytes recorded in the argument space.

### **SYNTAX**

num\_args [([PR])]

### **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, the function returns the number of arguments of the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the number of arguments of the *current trace event*. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

integer

- "arg()" on page 15-22
- "start\_num\_args()" on page 15-83
- "end\_num\_args()" on page 15-117
- "offset\_num\_args()" on page 15-155

### cuda functions

### **DESCRIPTION**

All the cuda functions listed here relate to events that were logged by a CUDA Graphical Processing Unit. See "NightTrace CUDA Tracing API" on page 2-32 for more information.

This description assumes the user has in-depth knowledge of the workings of CUDA and the attributes referenced below.

The first function in the list below, cuda, returns 1 if the event is an event logged by a CUDA GPU. Otherwise it returns zero.

The last function in the list below, cuda\_time, returns the raw clock time of the GPU symetrical multiprocessor when the event was logged.

All the other functions return the CUDA attribute as per their name.

#### **SYNTAX**

```
\begin{array}{l} \operatorname{cuda}\left[([PR])\right] \\ \operatorname{cuda\_warp}\left[([PR])\right] \\ \operatorname{cuda\_sm}\left[([PR])\right] \\ \operatorname{cuda\_lane}\left[([PR])\right] \\ \operatorname{cuda\_thr\_y}\left[([PR])\right] \\ \operatorname{cuda\_thr\_y}\left[([PR])\right] \\ \operatorname{cuda\_thr\_z}\left[([PR])\right] \\ \operatorname{cuda\_blk\_x}\left[([PR])\right] \\ \operatorname{cuda\_blk\_y}\left[([PR])\right] \\ \operatorname{cuda\_blk\_z}\left[([PR])\right] \\ \operatorname{cuda\_blk\_z}\left[([PR])\right] \\ \operatorname{cuda\_time}\left[([PR])\right] \\ \operatorname{cuda\_time}\left[([PR])\right] \\ \end{array}
```

## **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, the function returns the appropriate CUDA attribute of the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the appropriate CUDA attribute of the *current trace event*. For more information, see "Profile References" on page 15-181.

#### **NOTE**

If the event is not a CUDA GPU event, the return value will be zero. See "NightTrace CUDA Tracing API" on page 2-32 for more information.

### **RETURN TYPE**

integer

# pid()

### **DESCRIPTION**

The pid() function returns the global process identifier (PID) associated with a *trace event*.

### NOTE

All Linux threads within the same program share the same PID value. For trace events generated with the NightTrace Logging API, the value logged as the process identifier is the common PID..

## **SYNTAX**

pid [([*PR*])]

### **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, the function returns the global process identifier of the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the global process identifier of the *current trace event*. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

integer

- "start\_pid()" on page 15-84
- "end\_pid()" on page 15-118
- "offset\_pid()" on page 15-156

# thread\_id()

## **DESCRIPTION**

The thread\_id() function returns the *thread* identifier associated with a *trace event*. The thread identifier is the value of the system call **gettid(2)**.

## **SYNTAX**

thread\_id [([PR])]

### **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, the function returns the thread identifier of the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the thread identifier of the *current trace event*. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

integer

- "start\_thread\_id()" on page 15-85
- "end\_thread\_id()" on page 15-119
- "offset\_thread\_id()" on page 15-157

# tid()

## **DESCRIPTION**

The tid() function returns the internally-assigned NightTrace thread identifier (*TID*) associated with a *trace event*.

## **SYNTAX**

tid[([PR])]

## **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, the function returns the NightTrace thread identifier of the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the NightTrace thread identifier of the *current trace event*. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

integer

- "start\_tid()" on page 15-86
- "end\_tid()" on page 15-120
- "offset\_tid()" on page 15-158

# cpu()

### **DESCRIPTION**

The cpu() function returns the logical CPU number associated with a *trace event*. CPUs are logically numbered starting at 0 and monotonically increase thereafter.

### **NOTE**

This function is only valid when applied to events from Night-Trace kernel trace event files. Kernel tracing is not supported on all operating system distributions. See "Kernel Dependencies" on page B-1 for more information.

## **SYNTAX**

cpu[([PR])]

### **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, the function returns the logical CPU number of the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the logical CPU number of the *current trace event*. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

integer

- "start\_cpu()" on page 15-87
- "end\_cpu()" on page 15-121
- "offset\_cpu()" on page 15-159

# offset()

## **DESCRIPTION**

The offset() function returns the ordinal number (offset) of a trace event.

### **SYNTAX**

offset [([PR])]

### **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, the function returns the ordinal number (*offset*) of the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the ordinal number (*offset*) of the *current trace event*. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

integer

- "start\_offset()" on page 15-88
- "end\_offset()" on page 15-122
- "min\_offset()" on page 15-169
- "max\_offset()" on page 15-170

# time()

## **DESCRIPTION**

The time() function returns the time, in seconds, associated with a *trace event*. Times are relative to the earliest trace event from all trace data files currently in use.

## **SYNTAX**

time[([PR])]

### **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, the function returns the time, in seconds, of the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the time, in seconds, of the *current trace event*. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

double-precision floating point

- "event\_gap()" on page 15-56
- "start\_time()" on page 15-89
- "end\_time()" on page 15-123
- "state\_gap()" on page 15-126
- "state\_dur()" on page 15-127
- "offset\_time()" on page 15-160

# node\_id()

### **DESCRIPTION**

The node\_id() function returns the internally-assigned *node identifier* associated with a *trace event*.

#### NOTE

The node\_id() function is of limited usefulness since the node identifier is an internally-assigned integer number assigned by NightTrace. The node\_name() function is more useful, as it returns the name of the system from which a trace event was logged. (See "node\_name()" on page 15-53 for more information about this function.)

### **SYNTAX**

 $node_id[([PR])]$ 

#### **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, the function returns the node identifier of the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the node identifier of the *current trace event*. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

integer

- "start\_node\_id()" on page 15-90
- "offset\_node\_id()" on page 15-161
- "end\_node\_id()" on page 15-124

# node\_name()

## **DESCRIPTION**

The node\_name() function returns the name of the system from which a *trace* event was logged.

## **SYNTAX**

node\_name [([PR])]

### **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, the function returns the name of system from which the last instance of the trace event which satisfies the conditions for the specified profile was logged. If omitted, the function returns the name of the system from which the *current trace event* was logged. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

string

- "start\_node\_name()" on page 15-91
- "offset\_node\_name()" on page 15-162
- "end\_node\_name()" on page 15-125

# process\_name()

## **DESCRIPTION**

The process\_name() function returns the name of the process associated with a *trace event*.

## **SYNTAX**

process\_name [([PR])]

### **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, the function returns the name associated with the *PID* of the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the name associated with the *PID* of the *current trace event*. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

string

## **SEE ALSO**

• "offset\_process\_name()" on page 15-163

# thread\_name()

### **DESCRIPTION**

The thread\_name() function returns the thread name associated with a *trace* event.

Thread names are only available when user trace data is loaded and then only for threads registered with the NightTrace Logging API.

See "Threads and Logging" on page 2-31 for a discussion of the threads and the NightTrace Logging API.

## **SYNTAX**

thread\_name [([PR])]

### **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, the function returns the thread name associated with the last instance of the trace event which satisfies the conditions for the specified profile. If omitted, the function returns the thread name associated with the *current trace event*. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

string

#### **SEE ALSO**

• "offset\_thread\_name()" on page 15-164

## **Multi-Event Functions**

Multi-event functions return information about one or more instances of an event:

- event\_gap()
- event\_matches()

## event\_gap()

### **DESCRIPTION**

The event\_gap() function returns the time, in seconds, between the most recent occurrence of a specific event and its immediately preceding occurrence.

#### **SYNTAX**

```
event_gap [([PR])]
```

## **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, the function calculates the gap between the two most recent occurrences of events which satisfy the conditions of the specified profile. If omitted, the function calculates the gap between the current trace event and the event immediately preceding it. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

double-precision floating point

- "time()" on page 15-51
- "state\_gap()" on page 15-126
- "state\_dur()" on page 15-127

# event\_matches()

# **DESCRIPTION**

The event\_matches() function returns the number of occurrences of a *trace event* on or before the *current time line*.

## **SYNTAX**

event\_matches [([PR])]

## **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, the function calculates the number of occurrences of events which satisfy the conditions of the specified profile on or before the current time line. If omitted, the function calculates the number of occurrences of all events on or before the current time line. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

integer

# **SEE ALSO**

• "summary\_matches()" on page 15-171

# **State Functions**

In its simplest form, a *state* is a region of time bounded by two *trace events*. A state definition requires the specification of two trace events, a *start event* and an *end event*, respectively. Additional conditions may be specified in a state definition to further constrain the state. The state functions include the following:

- "Start Functions" on page 15-58
- "End Functions" on page 15-92
- "Multi-State Functions" on page 15-126

#### **NOTE**

Currently, NightTrace does not supported nesting of states. Thus, once the conditions which satisfy a *start event* are met, no other instances of that state can begin until the end condition has been met.

### **Start Functions**

The start functions provide information about the *start event* of the *most recent instance of a state*. The state to which the start function applies is either the *profile reference* specified to the function, or the state being currently defined. Thus, if a profile is not specified, start functions are only meaningful when used in *expressions* associated within a state definition. In addition, start functions should not be used in a recursive manner in a Start Expression; a start function should not be specified in a Start Expression that applies to the state definition containing that Start Expression. Conversely, an End Expression may include start functions that apply to the state definition containing that End Expression.

#### **NOTE**

Start functions provide information about the *most recent instance* of a state, whereas end functions (see "End Functions" on page 15-92) provide information about the *last completed instance of a state*.

Start functions include the following:

- start\_id()
- start\_arg()
- start\_arg\_dbl()
- start\_arg\_long()
- start\_arg\_long()

- start\_arg\_long\_dbl()
- start\_arg\_long\_long()
- start\_blk\_arg()
- start\_blk\_arg\_bits()
- start\_blk\_arg\_char()
- start\_blk\_arg\_dbl()
- start\_blk\_arg\_flt()
- start\_blk\_arg\_long()
- start\_blk\_arg\_long\_bits()
- start\_blk\_arg\_long\_dbl()
- start\_blk\_arg\_long\_long()
- start\_blk\_arg\_long\_ubits()
- start\_blk\_arg\_short()
- start\_blk\_arg\_string()
- start\_blk\_arg\_ubits()
- start\_blk\_arg\_uchar()
- start\_blk\_arg\_uint()
- start\_blk\_arg\_ulong\_long()
- start\_blk\_arg\_ushort()
- start\_num\_args()
- start\_pid()
- start\_thread\_id()
- start\_tid()
- start\_cpu()
- start\_offset()
- start\_time()
- start\_node\_id()
- start\_node\_name()

## start\_id()

### **DESCRIPTION**

The start\_id() function returns the *trace event ID* of the *start event* of the *most recent instance of a state*.

## **SYNTAX**

 $start_id[([PR])]$ 

## **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

# **RETURN TYPE**

integer

- "id()" on page 15-21
- "end\_id()" on page 15-94
- "offset\_id()" on page 15-132

# start\_arg()

# **DESCRIPTION**

The start\_arg() function returns the value of a particular *trace event argument* associated with the *start event* of the *most recent instance of a state*.

### **SYNTAX**

 $start_arg[N][([PR])]$ 

## **PARAMETERS**

Ν

Specifies the Nth argument logged with the start event. Defaults to 1.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

integer

- "arg()" on page 15-22
- "start\_arg\_dbl()" on page 15-62
- "start\_num\_args()" on page 15-83
- "end\_arg()" on page 15-95
- "offset\_arg()" on page 15-133

## start\_arg\_dbl()

## **DESCRIPTION**

The start\_arg\_dbl() function returns the value of a particular *trace event* argument associated with the *start event* of the *most recent instance of a state*.

#### **SYNTAX**

```
start_arg[N]_dbl[([PR])]
```

## **PARAMETERS**

N

Specifies the *N*th argument logged with the *start event*. Defaults to 1.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

double-precision floating point

- "arg\_dbl()" on page 15-23
- "start\_arg()" on page 15-61
- "start\_num\_args()" on page 15-83
- "end\_arg\_dbl()" on page 15-96
- "offset\_arg\_dbl()" on page 15-134

# start\_arg\_long()

# **DESCRIPTION**

The start\_arg\_long() function returns the value of a particular *trace event* argument associated with the *start event* of the *most recent instance of a state*.

### **SYNTAX**

```
start_arg[N]_long[([PR])]
```

## **PARAMETERS**

N

Specifies the Nth argument logged with the start event. Defaults to 1.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

double-precision floating point

- "arg\_dbl()" on page 15-23
- "start\_arg()" on page 15-61
- "start\_num\_args()" on page 15-83
- "end\_arg\_dbl()" on page 15-96
- "offset\_arg\_long()" on page 15-135

# start\_arg\_long\_dbl()

## **DESCRIPTION**

The start\_arg\_long\_dbl() function returns the value of a particular *trace event argument* associated with the *start event* of the *most recent instance of a state*.

#### **SYNTAX**

```
start_arg[N]_long_dbl[([PR])]
```

## **PARAMETERS**

N

Specifies the *N*th argument logged with the *trace event*. Defaults to 1.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

long double-precision floating point

- "num\_args()" on page 15-44
- "arg\_long\_dbl()" on page 15-25
- "end\_arg\_long\_dbl()" on page 15-98
- "offset\_arg\_long\_dbl()" on page 15-136

# start\_arg\_long\_long()

# **DESCRIPTION**

The start\_arg\_long\_long() function returns the value of a particular *trace event argument* associated with the *start event* of the *most recent instance of a state*.

### **SYNTAX**

```
start_arg[N]_long_long[([PR])]
```

## **PARAMETERS**

Ν

Specifies the *N*th argument logged with the *trace event*. Defaults to 1.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

long long integer

- "arg\_long\_long()" on page 15-26
- "num\_args()" on page 15-44
- "end\_arg\_long\_long()" on page 15-99
- "offset\_arg\_long\_long()" on page 15-137

## start\_blk\_arg()

## **DESCRIPTION**

The start\_blk\_arg() function returns the value of a trace event argument located at a particular byte offset in the argument space associated with the event associated with the *start event* of the *most recent instance of a state*.

### **SYNTAX**

```
start_blk_arg (byte_offset[,PR])
```

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "blk\_arg()" on page 15-27
- "end\_blk\_arg()" on page 15-100
- "offset\_blk\_arg()" on page 15-138

### start\_blk\_arg\_bits()

## **DESCRIPTION**

The start\_blk\_arg\_bits() function returns the value of a trace event signed bit field argument located at a particular byte and bit offset with a particular bit size in the argument space associated with the event associated with the *start event* of the *most recent instance of a state*.

### **SYNTAX**

start\_blk\_arg\_bits (byte\_offset, bit\_offset, bit\_size[, PR])

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

bit offset

Specifies the bit offset of the argument recorded with the *trace\_event\_blk*.

bit size

Specifies the size in bits of the argument record with trace\_event\_blk.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "blk\_arg\_bits()" on page 15-28
- "end blk arg bits()" on page 15-101
- "offset\_blk\_arg\_bits()" on page 15-139

## start\_blk\_arg\_char()

## **DESCRIPTION**

The start\_blk\_arg\_char() function returns the value of a trace event signed character argument located at a particular byte offset in the argument space associated with the event associated with the *start event* of the *most recent instance of a state*.

## **SYNTAX**

```
start_blk_arg_char (byte_offset[,PR])
```

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

#### **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "blk\_arg\_char()" on page 15-29
- "end\_blk\_arg\_char()" on page 15-102
- "offset\_blk\_arg\_char()" on page 15-140

## start\_blk\_arg\_dbl()

## **DESCRIPTION**

The start\_blk\_arg\_dbl() function returns the value of a trace event double-precision floating point argument located at a particular byte offset in the argument space associated with the event associated with the *start event* of the *most recent instance of a state*.

### **SYNTAX**

start\_blk\_arg\_dbl (byte\_offset[,PR])

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

#### **RETURN TYPE**

double-precision floating point

- "num\_args()" on page 15-44
- "blk\_arg\_dbl()" on page 15-30
- "end\_blk\_arg\_dbl()" on page 15-103
- "offset\_blk\_arg\_dbl()" on page 15-141

## start\_blk\_arg\_flt()

## **DESCRIPTION**

The start\_blk\_arg\_flt() function returns the value of a trace event single-precision floating point argument located at a particular byte offset in the argument space associated with the event associated with the *start event* of the *most recent instance of a state*.

### **SYNTAX**

```
start blk_arg_flt (byte_offset[,PR])
```

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

#### **RETURN TYPE**

double-precision floating point

- "num\_args()" on page 15-44
- "blk\_arg\_flt()" on page 15-31
- "end\_blk\_arg\_flt()" on page 15-104
- "offset\_blk\_arg\_flt()" on page 15-142

# start\_blk\_arg\_long()

# **DESCRIPTION**

The start\_blk\_arg\_long() function returns the value of a trace event long integer argument located at a particular byte offset in the argument space associated with the event associated with the *start event* of the *most recent instance of a state*.

### **SYNTAX**

start\_blk\_arg\_long (byte\_offset[,PR])

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

long integer

- "num\_args()" on page 15-44
- "blk\_arg\_long()" on page 15-32
- "end\_blk\_arg\_long()" on page 15-105
- "offset\_blk\_arg\_long()" on page 15-143

### start\_blk\_arg\_long\_bits()

## **DESCRIPTION**

The start\_blk\_arg\_long\_bits() function returns the value of a trace event signed long bit field argument located at a particular byte and bit offset with a particular bit size in the argument space associated with the event associated with the *start* event of the *most recent instance of a state*.

### **SYNTAX**

start\_blk\_arg\_long\_bits(byte\_offset,bit\_offset,bit\_size[,PR])

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

bit offset

Specifies the bit offset of the argument recorded with the *trace\_event\_blk*.

bit size

Specifies the size in bits of the argument record with trace\_event\_blk.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

long integer

- "num\_args()" on page 15-44
- "blk\_arg\_long\_bits()" on page 15-33
- "end blk arg long bits()" on page 15-106
- "offset\_blk\_arg\_long\_bits()" on page 15-144

# start\_blk\_arg\_long\_dbl()

## **DESCRIPTION**

The start\_blk\_arg\_long\_dbl() function returns the value of a trace event long double-precision floating point argument located at a particular byte offset in the argument space associated with the event associated with the *start event* of the *most recent instance of a state*.

### **SYNTAX**

```
start_blk_arg_long_dbl (byte_offset[,PR])
```

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

#### **RETURN TYPE**

long double-precision floating point

- "num\_args()" on page 15-44
- "blk\_arg\_long\_dbl()" on page 15-34
- "end\_blk\_arg\_long\_dbl()" on page 15-107
- "offset\_blk\_arg\_long\_dbl()" on page 15-145

# start\_blk\_arg\_long\_long()

## **DESCRIPTION**

The start\_blk\_arg\_long\_long() function returns the value of a trace event long long integer argument located at a particular byte offset in the argument space associated with the event associated with the *start event* of the *most recent instance of a state*.

## SYNTAX

```
start_blk_arg_long_long (byte_offset[,PR])
```

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

long long integer

- "num\_args()" on page 15-44
- "blk\_arg\_long\_long()" on page 15-35
- "end\_blk\_arg\_long\_long()" on page 15-108
- "offset\_blk\_arg\_long\_long()" on page 15-146

## start\_blk\_arg\_long\_ubits()

## **DESCRIPTION**

The start\_blk\_arg\_long\_ubits() function returns the value of a trace event unsigned long integer bit field argument located at a particular byte and bit offset with a particular bit size in the argument space associated with the event associated with the *start event* of the *most recent instance of a state*.

### **SYNTAX**

start\_blk\_arg\_long\_ubits(byte\_offset,bit\_offset,bit\_size[,PR])

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

bit offset

Specifies the bit offset of the argument recorded with the *trace\_event\_blk*.

bit size

Specifies the size in bits of the argument record with trace\_event\_blk.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

long long integer

- "num\_args()" on page 15-44
- "blk\_arg\_long\_ubits()" on page 15-36
- "end blk arg long ubits()" on page 15-109
- "offset\_blk\_arg\_long\_ubits()" on page 15-147

## start\_blk\_arg\_short()

## **DESCRIPTION**

The start\_blk\_arg\_short() function returns the value of a trace event short integer argument located at a particular byte offset in the argument space associated with the event associated with the *start event* of the *most recent instance of a state*.

### **SYNTAX**

start\_blk\_arg\_short (byte\_offset[,PR])

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "blk\_arg\_short()" on page 15-37
- "end\_blk\_arg\_short()" on page 15-110
- "offset\_blk\_arg\_short()" on page 15-148

### start\_blk\_arg\_string()

## **DESCRIPTION**

The start\_blk\_arg\_string() function returns the value of a trace event null terminated string argument located at a particular byte offset in the argument space associated with the event associated with the *start event* of the *most recent instance of a state*.

### **SYNTAX**

start\_blk\_arg\_string(byte\_offset, max\_size[, PR])

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk* or *trace\_event\_string*.

max\_size

Specifies the maximum length of string that might be returned. If the arguments were recorded with *trace\_event\_blk*, this is also the total number of bytes allocated in the block for the string, regardless of its actual length.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

string

- "num\_args()" on page 15-44
- "blk\_arg\_string()" on page 15-38
- "end\_blk\_arg\_string()" on page 15-111
- "offset\_blk\_arg\_string()" on page 15-149

### start\_blk\_arg\_ubits()

## **DESCRIPTION**

The start\_blk\_arg\_ubits() function returns the value of a trace event unsigned bit field argument located at a particular byte and bit offset with a particular bit size in the argument space associated with the event associated with the *start* event of the most recent instance of a state.

### **SYNTAX**

```
start_blk_arg_ubits (byte_offset, bit_offset, bit_size[, PR])
```

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

bit offset

Specifies the bit offset of the argument recorded with the *trace\_event\_blk*.

bit size

Specifies the size in bits of the argument record with trace\_event\_blk.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "blk\_arg\_ubits()" on page 15-39
- "end blk arg ubits()" on page 15-112
- "offset\_blk\_arg\_ubits()" on page 15-150

## start\_blk\_arg\_uchar()

# **DESCRIPTION**

The start\_blk\_arg\_uchar() function returns the value of a trace event unsigned character argument located at a particular byte offset in the argument space associated with the event associated with the *start event* of the *most recent instance of a state*.

## **SYNTAX**

```
start_blk_arg_uchar (byte_offset[,PR])
```

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

#### **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "blk\_arg\_uchar()" on page 15-40
- "end\_blk\_arg\_uchar()" on page 15-113
- "offset\_blk\_arg\_uchar()" on page 15-151

## start\_blk\_arg\_uint()

## **DESCRIPTION**

The start\_blk\_arg\_uint() function converts the unsigned integer trace event argument at a particular byte offset in the argument space associated with the *start event* of the *most recent instance of a state* to a long.

### **NOTE**

You can convert the long return value to an unsigned value using the cast operator. For example:

```
(unsigned long) start_blk_arg_uint(0) > 0x80000000
```

### **SYNTAX**

```
start_blk_arg_uint (byte_offset[,PR])
```

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

unsigned integer

- "num\_args()" on page 15-44
- "blk\_arg\_uint()" on page 15-41
- "end\_blk\_arg\_uint()" on page 15-114
- "offset\_blk\_arg\_uint()" on page 15-152

# start\_blk\_arg\_ulong\_long()

## **DESCRIPTION**

The start\_blk\_arg\_ulong\_long() function returns the value of a trace event unsigned long long integer argument located at a particular byte offset in the argument space associated with the event associated with the *start event* of the *most recent instance of a state*.

### **SYNTAX**

start\_blk\_arg\_ulong\_long(byte\_offset[,PR])

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

#### **RETURN TYPE**

unsigned long long integer

- "num\_args()" on page 15-44
- "blk\_arg\_ulong\_long()" on page 15-42
- "end\_blk\_arg\_ulong\_long()" on page 15-115
- "offset\_blk\_arg\_ulong\_long()" on page 15-153

## start\_blk\_arg\_ushort()

## **DESCRIPTION**

The start\_blk\_arg\_ushort() function returns the value of a trace event unsigned short integer argument located at a particular byte offset in the argument space associated with the event associated with the *start event* of the *most recent instance of a state*.

### **SYNTAX**

```
start_blk_arg_ushort (byte_offset[,PR])
```

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

#### **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "blk\_arg\_ushort()" on page 15-43
- "end\_blk\_arg\_ushort()" on page 15-116
- "offset\_blk\_arg\_ushort()" on page 15-154

## start\_num\_args()

# **DESCRIPTION**

The start\_num\_args() function returns the number of arguments associated with the *start event* of the *most recent instance of a state*. For events recorded with trace\_event\_blk(), it returns the number of bytes recorded in the argument space.

## **SYNTAX**

start\_num\_args[([PR])]

### **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

integer

- "start\_arg()" on page 15-61
- "num\_args()" on page 15-44
- "end\_num\_args()" on page 15-117
- "offset\_num\_args()" on page 15-155

## start\_pid()

## **DESCRIPTION**

The start\_pid() function returns the PID associated with the *start event* of the *most recent instance of a state*.

#### **NOTE**

All Linux threads within the same program share the same PID value. For trace events generated with the NightTrace Logging API, the value logged as the process identifier is the common PID..

## **SYNTAX**

start\_pid[([PR])]

## **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

integer

- "pid()" on page 15-46
- "end\_pid()" on page 15-118
- "offset\_pid()" on page 15-156

# start\_thread\_id()

# **DESCRIPTION**

The start\_thread\_id() function returns the *thread* identifier associated with the *start event* of the *most recent instance of a state*. The thread identifier is the value of the system call **gettid(2)**.

## **SYNTAX**

start\_thread\_id[([PR])]

### **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

integer

- "thread\_id()" on page 15-47
- "end\_thread\_id()" on page 15-119
- "offset\_thread\_id()" on page 15-157

# start\_tid()

# **DESCRIPTION**

The start\_tid() function returns the internally-assigned NightTrace thread identifier (*TID*) associated with the *start event* of the *most recent instance of a state*.

### **SYNTAX**

start\_tid[([PR])]

## **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

integer

- "tid()" on page 15-48
- "end\_tid()" on page 15-120
- "offset\_tid()" on page 15-158

# start\_cpu()

# **DESCRIPTION**

The start\_cpu() function returns the logical CPU number associated with the *start event* of the *most recent instance of a state*. CPUs are logically numbered starting at 0 and monotonically increase thereafter.

## **NOTE**

This function is only valid when applied to events from Night-Trace kernel trace event files. Kernel tracing is not supported on all operating systems. See "Kernel Dependencies" on page B-1 for more information.

### **SYNTAX**

start\_cpu[([PR])]

### **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

integer

- "cpu()" on page 15-49
- "end\_cpu()" on page 15-121
- "offset\_cpu()" on page 15-159

# start\_offset()

# **DESCRIPTION**

The start\_offset() function returns the ordinal number (offset) of the start event of the most recent instance of a state.

### **SYNTAX**

start\_offset[([PR])]

## **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

integer

- "offset()" on page 15-50
- "end\_offset()" on page 15-122

# start\_time()

# **DESCRIPTION**

The start\_time() function returns the time, in seconds, associated with the *start event* of the *most recent instance of a state*. Times are relative to the earliest trace event from all trace data files currently in use.

## **SYNTAX**

```
start\_time[([PR])]
```

### **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

double-precision floating point

- "time()" on page 15-51
- "end\_time()" on page 15-123
- "state\_gap()" on page 15-126
- "state\_dur()" on page 15-127
- "offset\_time()" on page 15-160

## start\_node\_id()

# **DESCRIPTION**

The start\_node\_id() function returns the internally-assigned *node identifier* associated with the *start event* of the *most recent instance of a state*.

### **SYNTAX**

start\_node\_id[([PR])]

## **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

integer

- "node\_id()" on page 15-52
- "offset\_node\_id()" on page 15-161
- "end\_node\_id()" on page 15-124

# start\_node\_name()

# **DESCRIPTION**

The start\_node\_name() function returns the name of the system from which the *start event* of the *most recent instance of a state* was logged.

### **SYNTAX**

start\_node\_name[([PR])]

## **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

string

- "node\_name()" on page 15-53
- "offset\_node\_name()" on page 15-162
- "end\_node\_name()" on page 15-125

## **End Functions**

The end functions provide information about the *end event* of the *last completed instance* of a state. The state to which the end function applies is either the *profile reference* specified to the function, or the state being currently defined. Thus, if a profile is not specified, end functions are only meaningful when used in expressions associated within a state definition.

#### NOTE

End functions provide information about the *last completed instance of a state*, whereas start functions (see "Start Functions" on page 15-58) provide information about the *most recent instance of a state*.

## End functions include:

- end\_id()
- end\_arg()
- end\_arg\_dbl()
- end\_arg\_long\_dbl()
- end\_arg\_long\_long()
- end\_blk\_arg()
- end\_blk\_arg\_bits()
- end\_blk\_arg\_char()
- end\_blk\_arg\_dbl()
- end\_blk\_arg\_flt()
- end\_blk\_arg\_long()
- end\_blk\_arg\_long\_bits()
- end\_blk\_arg\_long\_dbl()
- end\_blk\_arg\_long\_long()
- end\_blk\_arg\_long\_ubits()
- end\_blk\_arg\_short()
- end\_blk\_arg\_string()
- end\_blk\_arg\_ubits()
- end\_blk\_arg\_uchar()
- end\_blk\_arg\_uint()
- end\_blk\_arg\_ulong\_long()

- end\_blk\_arg\_ushort()
- end\_num\_args()
- end\_pid()
- end\_thread\_id()
- end\_tid()
- end\_cpu()
- end\_offset()
- end\_time()
- end\_node\_id()
- end\_node\_name()

# end\_id()

# **DESCRIPTION**

The end\_id() function returns the *trace event ID* associated with the *end event* of the *last completed instance of a state*.

### **SYNTAX**

 $end_id[([PR])]$ 

## **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

integer

- "id()" on page 15-21
- "start\_id()" on page 15-59
- "offset\_id()" on page 15-132

## end\_arg()

# **DESCRIPTION**

The end\_arg() function returns the value of a particular *trace event argument* associated with the *end event* of the *last completed instance of a state*.

### **SYNTAX**

 $end_arg[N][([PR])]$ 

## **PARAMETERS**

N

Specifies the *N*th argument logged with the trace event. Defaults to 1.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

integer

- "arg()" on page 15-22
- "start\_arg()" on page 15-61
- "end\_arg()" on page 15-95
- "end\_num\_args()" on page 15-117
- "offset\_arg()" on page 15-133

## end\_arg\_dbl()

# **DESCRIPTION**

The end\_arg\_dbl() function returns the value of a particular *trace event argument* associated with the *end event* of the *last completed instance of a state*.

#### **SYNTAX**

 $end_arg[N]_dbl[([PR])]$ 

## **PARAMETERS**

N

Specifies the *N*th argument logged with the trace event. Defaults to 1.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

double-precision floating point

- "arg\_dbl()" on page 15-23
- "start\_arg\_dbl()" on page 15-62
- "end\_num\_args()" on page 15-117
- "offset\_arg\_dbl()" on page 15-134

# end\_arg\_long()

# **DESCRIPTION**

The end\_arg\_long() function returns the value of a particular *trace event argument* associated with the *end event* of the *last completed instance of a state*.

### **SYNTAX**

 $end_arg[N]_long[([PR])]$ 

## **PARAMETERS**

N

Specifies the *N*th argument logged with the trace event. Defaults to 1.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

double-precision floating point

- "arg\_long()" on page 15-24
- "start\_arg\_long()" on page 15-63
- "end\_num\_args()" on page 15-117
- "offset\_arg\_long()" on page 15-135

# end\_arg\_long\_dbl()

## **DESCRIPTION**

The end\_arg\_long\_dbl() function returns the value of a particular *trace event argument* associated with the *start event* of the *most recent instance of a state*.

#### **SYNTAX**

```
end_arg[N]_long_dbl[([PR])]
```

## **PARAMETERS**

N

Specifies the Nth argument logged with the trace event. Defaults to 1.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

long double-precision floating point

- "num\_args()" on page 15-44
- "arg\_long\_dbl()" on page 15-25
- "start\_arg\_long\_dbl()" on page 15-64
- "offset\_arg\_long\_dbl()" on page 15-136

# end\_arg\_long\_long()

# **DESCRIPTION**

The end\_arg\_long\_long() function returns the value of a particular *trace event argument*.

### **SYNTAX**

end\_arg[N]\_long\_long [([PR])]

## **PARAMETERS**

Ν

Specifies the Nth argument logged with the trace event. Defaults to 1.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

long long integer

- "arg\_long\_long()" on page 15-26
- "num\_args()" on page 15-44
- "start\_arg\_long\_long()" on page 15-65
- "offset\_arg\_long\_long()" on page 15-137

# end\_blk\_arg()

# **DESCRIPTION**

The end\_blk\_arg() function returns the value of a trace event argument located at a particular byte offset in the argument space associated with the event associated with the *end event* of the *most recent instance of a state*.

### **SYNTAX**

```
end_blk_arg(byte_offset[,PR])
```

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "blk\_arg()" on page 15-27
- "start\_blk\_arg()" on page 15-66
- "offset\_blk\_arg()" on page 15-138

## end\_blk\_arg\_bits()

## **DESCRIPTION**

The end\_blk\_arg\_bits() function returns the value of a trace event signed bit field argument located at a particular byte and bit offset with a particular bit size in the argument space associated with the event associated with the *end event* of the *most recent instance of a state*.

### **SYNTAX**

```
end_blk_arg_bits (byte_offset, bit_offset, bit_size[, PR])
```

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

bit offset

Specifies the bit offset of the argument recorded with the *trace\_event\_blk*.

bit size

Specifies the size in bits of the argument record with trace\_event\_blk.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "blk\_arg\_bits()" on page 15-28
- "start\_blk\_arg\_bits()" on page 15-67
- "offset\_blk\_arg\_bits()" on page 15-139

## end\_blk\_arg\_char()

## **DESCRIPTION**

The end\_blk\_arg\_char() function returns the value of a trace event signed character argument located at a particular byte offset in the argument space associated with the event associated with the end event of the most recent instance of a state.

## **SYNTAX**

```
end_blk_arg_char(byte_offset[,PR])
```

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

#### **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "blk\_arg\_char()" on page 15-29
- "start\_blk\_arg\_char()" on page 15-68
- "offset\_blk\_arg\_char()" on page 15-140

# end\_blk\_arg\_dbl()

## **DESCRIPTION**

The end\_blk\_arg\_dbl() function returns the value of a trace event double-precision floating point argument located at a particular byte offset in the argument space associated with the event associated with the *end event* of the *most recent instance of a state*.

### **SYNTAX**

```
end_blk_arg_dbl (byte_offset[,PR])
```

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

#### **RETURN TYPE**

double-precision floating point

- "num\_args()" on page 15-44
- "blk\_arg\_dbl()" on page 15-30
- "start\_blk\_arg\_dbl()" on page 15-69
- "offset\_blk\_arg\_dbl()" on page 15-141

## end\_blk\_arg\_flt()

## **DESCRIPTION**

The end\_blk\_arg\_flt() function returns the value of a trace event single-precision floating point argument located at a particular byte offset in the argument space associated with the event associated with the *end event* of the *most recent instance of a state*.

### **SYNTAX**

```
end_blk_arg_flt(byte_offset[,PR])
```

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

#### **RETURN TYPE**

double-precision floating point

- "num\_args()" on page 15-44
- "blk\_arg\_flt()" on page 15-31
- "start\_blk\_arg\_flt()" on page 15-70
- "offset\_blk\_arg\_flt()" on page 15-142

# end\_blk\_arg\_long()

# **DESCRIPTION**

The end\_blk\_arg\_long() function returns the value of a trace event long integer argument located at a particular byte offset in the argument space associated with the event associated with the end event of the most recent instance of a state.

### **SYNTAX**

end\_blk\_arg\_long(byte\_offset[,PR])

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

long integer

- "num\_args()" on page 15-44
- "blk\_arg\_long()" on page 15-32
- "start\_blk\_arg\_long()" on page 15-71
- "offset\_blk\_arg\_long()" on page 15-143

## end\_blk\_arg\_long\_bits()

## **DESCRIPTION**

The end\_blk\_arg\_long\_bits() function returns the value of a trace event signed long bit field argument located at a particular byte and bit offset with a particular bit size in the argument space associated with the event associated with the *end* event of the most recent instance of a state.

### **SYNTAX**

end\_blk\_arg\_long\_bits (byte\_offset, bit\_offset, bit\_size[, PR])

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

bit offset

Specifies the bit offset of the argument recorded with the *trace\_event\_blk*.

bit size

Specifies the size in bits of the argument record with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

long integer

- "num\_args()" on page 15-44
- "blk\_arg\_long\_bits()" on page 15-33
- "start blk arg long bits()" on page 15-72
- "offset\_blk\_arg\_long\_bits()" on page 15-144

## end\_blk\_arg\_long\_dbl()

## **DESCRIPTION**

The end\_blk\_arg\_long\_dbl() function returns the value of a trace event long double-precision floating point argument located at a particular byte offset in the argument space associated with the event associated with the *end event* of the *most recent instance of a state*.

### **SYNTAX**

```
end_blk_arg_long_dbl (byte_offset[,PR])
```

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

#### **RETURN TYPE**

long double-precision floating point

- "num\_args()" on page 15-44
- "blk\_arg\_long\_dbl()" on page 15-34
- "start\_blk\_arg\_long\_dbl()" on page 15-73
- "offset\_blk\_arg\_long\_dbl()" on page 15-145

## end\_blk\_arg\_long\_long()

## **DESCRIPTION**

The end\_blk\_arg\_long\_long() function returns the value of a trace event long long integer argument located at a particular byte offset in the argument space associated with the event associated with the *end event* of the *most recent instance of a state*.

## **SYNTAX**

end\_blk\_arg\_long\_long(byte\_offset[,PR])

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

#### **RETURN TYPE**

long long integer

- "num\_args()" on page 15-44
- "blk\_arg\_long\_long()" on page 15-35
- "start\_blk\_arg\_long\_long()" on page 15-74
- "offset\_blk\_arg\_long\_long()" on page 15-146

## end\_blk\_arg\_long\_ubits()

## **DESCRIPTION**

The end\_blk\_arg\_long\_ubits() function returns the value of a trace event unsigned long integer bit field argument located at a particular byte and bit offset with a particular bit size in the argument space associated with the event associated with the end event of the most recent instance of a state.

### **SYNTAX**

end\_blk\_arg\_long\_ubits (byte\_offset, bit\_offset, bit\_size[, PR])

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

bit offset

Specifies the bit offset of the argument recorded with the *trace\_event\_blk*.

bit size

Specifies the size in bits of the argument record with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

long long integer

- "num\_args()" on page 15-44
- "blk\_arg\_long\_ubits()" on page 15-36
- "start blk arg long ubits()" on page 15-75
- "offset\_blk\_arg\_long\_ubits()" on page 15-147

## end\_blk\_arg\_short()

## **DESCRIPTION**

The end\_blk\_arg\_short() function returns the value of a trace event short integer argument located at a particular byte offset in the argument space associated with the event associated with the end event of the most recent instance of a state.

### **SYNTAX**

end\_blk\_arg\_short (byte\_offset[,PR])

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "blk\_arg\_short()" on page 15-37
- "start\_blk\_arg\_short()" on page 15-76
- "offset\_blk\_arg\_short()" on page 15-148

## end\_blk\_arg\_string()

## **DESCRIPTION**

The end\_blk\_arg\_string() function returns the value of a trace event null terminated string argument located at a particular byte offset in the argument space associated with the event associated with the *end event* of the *most recent instance of a state*.

## **SYNTAX**

end\_blk\_arg\_string(byte\_offset, max\_size[, PR])

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk* or *trace\_event\_string*.

max\_size

Specifies the maximum length of string that might be returned. If the arguments were recorded with *trace\_event\_blk*, this is also the total number of bytes allocated in the block for the string, regardless of its actual length.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

# **RETURN TYPE**

string

- "num\_args()" on page 15-44
- "blk\_arg\_string()" on page 15-38
- "start\_blk\_arg\_string()" on page 15-77
- "offset\_blk\_arg\_string()" on page 15-149

## end\_blk\_arg\_ubits()

## **DESCRIPTION**

The end\_blk\_arg\_ubits() function returns the value of a trace event unsigned bit field argument located at a particular byte and bit offset with a particular bit size in the argument space associated with the event associated with the *end event* of the *most recent instance of a state*.

### **SYNTAX**

end\_blk\_arg\_ubits (byte\_offset, bit\_offset, bit\_size[, PR])

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

bit offset

Specifies the bit offset of the argument recorded with the *trace\_event\_blk*.

bit size

Specifies the size in bits of the argument record with trace\_event\_blk.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "blk\_arg\_ubits()" on page 15-39
- "start\_blk\_arg\_ubits()" on page 15-78
- "offset\_blk\_arg\_ubits()" on page 15-150

## end\_blk\_arg\_uchar()

# **DESCRIPTION**

The end\_blk\_arg\_uchar() function returns the value of a trace event unsigned character argument located at a particular byte offset in the argument space associated with the event associated with the *end event* of the *most recent instance of a state*.

## **SYNTAX**

```
end_blk_arg_uchar (byte_offset[,PR])
```

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

#### **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "blk\_arg\_uchar()" on page 15-40
- "start\_blk\_arg\_uchar()" on page 15-79
- "offset\_blk\_arg\_uchar()" on page 15-151

## end\_blk\_arg\_uint()

## **DESCRIPTION**

The end\_blk\_arg\_uint() function converts the unsigned integer trace event argument at a particular byte offset in the argument space associated with the *end event* of the *most recent instance of a state* to a long.

### **NOTE**

You can convert the long return value to an unsigned value using the cast operator. For example:

```
(unsigned long) end_blk_arg_uint(0) > 0x80000000
```

### **SYNTAX**

```
end_blk_arg_uint (byte_offset[,PR])
```

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

unsigned integer

- "num\_args()" on page 15-44
- "blk\_arg\_uint()" on page 15-41
- "start\_blk\_arg\_uint()" on page 15-80
- "offset\_blk\_arg\_uint()" on page 15-152

# end\_blk\_arg\_ulong\_long()

## **DESCRIPTION**

The end\_blk\_arg\_ulong\_long() function returns the value of a trace event unsigned long long integer argument located at a particular byte offset in the argument space associated with the event associated with the end event of the most recent instance of a state.

### **SYNTAX**

end\_blk\_arg\_ulong\_long(byte\_offset[,PR])

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

#### **RETURN TYPE**

unsigned long long integer

- "num\_args()" on page 15-44
- "blk\_arg\_ulong\_long()" on page 15-42
- "start\_blk\_arg\_ulong\_long()" on page 15-81
- "offset\_blk\_arg\_ulong\_long()" on page 15-153

## end\_blk\_arg\_ushort()

## **DESCRIPTION**

The end\_blk\_arg\_ushort() function returns the value of a trace event unsigned short integer argument located at a particular byte offset in the argument space associated with the event associated with the end event of the most recent instance of a state.

### **SYNTAX**

end\_blk\_arg\_ushort (byte\_offset[,PR])

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

#### **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "blk\_arg\_ushort()" on page 15-43
- "start\_blk\_arg\_ushort()" on page 15-82
- "offset\_blk\_arg\_ushort()" on page 15-154

# end\_num\_args()

# **DESCRIPTION**

The end\_num\_args() function returns the number of arguments associated with the *end event* of the *last completed instance of a state*. For events recorded with trace\_event\_blk(), it returns the number of bytes recorded in the argument space.

## **SYNTAX**

```
end_num_args [([PR])]
```

### **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "start\_num\_args()" on page 15-83
- "end\_arg()" on page 15-95
- "offset\_num\_args()" on page 15-155

## end\_pid()

## **DESCRIPTION**

The end\_pid() function returns the PID associated with the *end event* of the *last completed instance of a state*.

#### **NOTE**

All Linux threads within the same program share the same PID value. For trace events generated with the NightTrace Logging API, the value logged as the process identifier is the common PID..

## **SYNTAX**

 $end_pid[([PR])]$ 

### **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

integer

- "pid()" on page 15-46
- "start\_pid()" on page 15-84
- "offset\_pid()" on page 15-156

# end\_thread\_id()

# **DESCRIPTION**

The end\_thread\_id() function returns the *thread* identifier associated with the *end event* of the *last completed instance of a state*. The thread identifier is that returned by the system call **gettid(2)**.

## **SYNTAX**

end\_thread\_id [([PR])]

### **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

integer

- "thread\_id()" on page 15-47
- "start\_thread\_id()" on page 15-85
- "offset\_thread\_id()" on page 15-157

# end\_tid()

# **DESCRIPTION**

The end\_tid() function returns the internally-assigned NightTrace thread identifier (*TID*) associated with the *end event* of the *last completed instance of a state*.

### **SYNTAX**

 $end_tid[([PR])]$ 

## **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

integer

- "tid()" on page 15-48
- "start\_tid()" on page 15-86
- "offset\_tid()" on page 15-158

## end\_cpu()

# **DESCRIPTION**

The end\_cpu() function returns the logical CPU number associated with the *end event* of the *last completed instance of a state*. CPUs are logically numbered starting at 0 and monotonically increase thereafter.

## **NOTE**

This function is only valid when applied to events from Night-Trace kernel trace event files. Kernel tracing is not supported on all operating systems. See "Kernel Dependencies" on page B-1 for more information.

#### **SYNTAX**

end\_cpu [([PR])]

### **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

integer

- "cpu()" on page 15-49
- "start\_cpu()" on page 15-87
- "offset\_cpu()" on page 15-159

# end\_offset()

# **DESCRIPTION**

The end\_offset() function returns the ordinal number (*offset*) of the *end event* of the *last completed instance of a state*.

### **SYNTAX**

end\_offset [([PR])]

## **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

integer

- "offset()" on page 15-50
- "start\_offset()" on page 15-88

# end\_time()

# **DESCRIPTION**

The end\_time() function returns the time, in seconds, associated with the *end event* of the *last completed instance of a state*. Times are relative to the earliest trace event from all trace data files currently in use.

## **SYNTAX**

end\_time[([PR])]

### **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

double-precision floating point

- "time()" on page 15-51
- "start\_time()" on page 15-89
- "state\_gap()" on page 15-126
- "state\_dur()" on page 15-127
- "offset\_time()" on page 15-160

# end\_node\_id()

# **DESCRIPTION**

The end\_node\_id() function returns the internally-assigned *node identifier* associated with the *end event* of the *last completed instance of a state*.

### **SYNTAX**

 $end_node_id[([PR])]$ 

## **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

integer

- "node\_id()" on page 15-52
- "start\_node\_id()" on page 15-90
- "offset\_node\_id()" on page 15-161

# end\_node\_name()

# **DESCRIPTION**

The end\_node\_name() function returns the name of the system from which the *end event* of the *last completed instance of a state* was logged.

### **SYNTAX**

end\_node\_name [([PR])]

## **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, it specifies the state to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

string

- "node\_name()" on page 15-53
- "start\_node\_name()" on page 15-91
- "offset\_node\_name()" on page 15-162

## **Multi-State Functions**

Multi-state functions return information about one or more instances of a state:

- state\_gap()
- state\_dur()
- state\_matches()
- state\_status()

For restrictions on usage, see "State Graph" on page 11-11.

## state\_gap()

## **DESCRIPTION**

The state\_gap() function returns the time in seconds between the *start event* of the *most recent instance of the state* and the *end event* of the instance immediately preceding it or zero if there was no previous instance.

## **SYNTAX**

```
state_gap [([PR])]
```

### **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, it specifies the *state* to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

double-precision floating point

- "start\_time()" on page 15-89
- "end\_time()" on page 15-123
- "event\_gap()" on page 15-56
- "state\_dur()" on page 15-127

# state\_dur()

# **DESCRIPTION**

The state\_dur() function returns the time in seconds between the *start event* and the *end event* of the *last completed instance of a state*. Thus, if the *current time line* occurs within an instance of the state but before it has ended, state\_dur() returns the duration of the previous instance or zero if there was no previous instance.

### **SYNTAX**

state\_dur[([PR])]

### **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, it specifies the *state* to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

double-precision floating point

## **SEE ALSO**

• "state\_gap()" on page 15-126

# state\_matches()

# **DESCRIPTION**

The state\_matches() function returns the number of completed instances of a state on or before the *current time line*.

### **SYNTAX**

state\_matches [([PR])]

## **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, it specifies the *state* to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

## **RETURN TYPE**

integer

- "Start Functions" on page 15-58
- "summary\_matches()" on page 15-171

# state\_status()

# **DESCRIPTION**

The state\_status() function indicates whether the *current time line* resides within a *current instance of a state*. Thus, if the current time line is positioned in the region from the *start event* up to, but not including, the *end event* of an instance of the state, the return value is TRUE. Otherwise, it is FALSE.

## **SYNTAX**

state\_status[([PR])]

### **PARAMETERS**

PR

A user-defined *profile reference*. If supplied, it specifies the *state* to which the function applies. If omitted, the function may only be used within a state definition and then applies to that state. For more information, see "Profile References" on page 15-181.

### **RETURN TYPE**

boolean

# **Offset Functions**

All offset functions take an expression that evaluates to an ordinal trace event (*offset*) as a parameter. (Offsets begin at zero.) These functions include the following:

- offset\_id()
- offset\_arg()
- offset\_arg\_dbl()
- offset\_arg\_long()
- offset\_arg\_long\_dbl()
- offset\_arg\_long\_long()
- offset\_blk\_arg()
- offset\_blk\_arg\_bits()
- offset\_blk\_arg\_char()
- offset\_blk\_arg\_dbl()
- offset\_blk\_arg\_flt()
- offset\_blk\_arg\_long()
- offset\_blk\_arg\_long\_bits()
- offset\_blk\_arg\_long\_dbl()
- offset\_blk\_arg\_long\_long()
- offset\_blk\_arg\_long\_ubits()
- offset\_blk\_arg\_short()
- offset\_blk\_arg\_string()
- offset\_blk\_arg\_ubits()
- offset\_blk\_arg\_uchar()
- offset\_blk\_arg\_uint()
- offset\_blk\_arg\_ulong\_long()
- offset\_blk\_arg\_ushort()
- offset\_num\_args()
- offset\_pid()
- offset\_thread\_id()
- offset\_tid()
- offset\_cpu()
- offset\_time()

- offset\_node\_id()
- offset\_node\_name()
- offset\_process\_name()
- offset\_thread\_name()

Usually, these functions take one of the following functions as a parameter:

- offset()
- start\_offset()
- end\_offset()
- min\_offset()
- max\_offset()

For information about these functions, see "offset()" on page 15-50, "start\_offset()" on page 15-88, "end\_offset()" on page 15-122, "min\_offset()" on page 15-169, and "max\_offset()" on page 15-170.

# offset\_id()

# **DESCRIPTION**

The offset\_id() function returns the *trace event ID* of the ordinal trace event (offset).

# **SYNTAX**

```
offset_id( offset_expr )
```

## **PARAMETERS**

```
offset_expr
```

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

## **RETURN TYPE**

integer

- "id()" on page 15-21
- "start\_id()" on page 15-59
- "end\_id()" on page 15-94

# offset\_arg()

# **DESCRIPTION**

The offset\_arg() function returns the value of a particular *trace event argument* for the ordinal trace event (*offset*).

# **SYNTAX**

```
offset_arg[N] (offset_expr)
```

## **PARAMETERS**

N

Specifies the *N*th argument logged with the trace event. Defaults to 1.

```
offset_expr
```

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

# **RETURN TYPE**

integer

- "arg()" on page 15-22
- "start\_arg()" on page 15-61
- "end\_arg()" on page 15-95
- "offset\_arg\_dbl()" on page 15-134
- "offset\_num\_args()" on page 15-155

# offset\_arg\_dbl()

# **DESCRIPTION**

The offset\_arg\_dbl() function returns the value of a particular *trace event* argument for the ordinal trace event (offset).

# **SYNTAX**

```
offset_arg[N]_dbl (offset_expr)
```

## **PARAMETERS**

N

Specifies the *N*th argument logged with the trace event. Defaults to 1.

offset\_expr

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

## **RETURN TYPE**

double-precision floating point

- "arg\_dbl()" on page 15-23
- "start\_arg\_dbl()" on page 15-62
- "end\_arg\_dbl()" on page 15-96
- "offset\_arg()" on page 15-133
- "offset\_num\_args()" on page 15-155

# offset\_arg\_long()

# **DESCRIPTION**

The offset\_arg\_long() function returns the value of a particular *trace event* argument for the ordinal trace event (offset).

# **SYNTAX**

offset\_arg[N]\_long (offset\_expr)

### **PARAMETERS**

Ν

Specifies the *N*th argument logged with the trace event. Defaults to 1.

offset\_expr

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

## **RETURN TYPE**

double-precision floating point

- "arg\_long()" on page 15-24
- "start\_arg\_long()" on page 15-63
- "end\_arg\_long()" on page 15-97
- "offset\_arg()" on page 15-133
- "offset\_num\_args()" on page 15-155

# offset\_arg\_long\_dbl()

# **DESCRIPTION**

The offset\_arg\_long\_dbl() function returns the value of a particular *trace event argument* for the ordinal trace event (offset).

# **SYNTAX**

```
offset_arg[N]_long_dbl (offset_expr)
```

### **PARAMETERS**

N

Specifies the Nth argument logged with the trace event. Defaults to 1.

offset\_expr

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

## **RETURN TYPE**

long double-precision floating point

- "num\_args()" on page 15-44
- "arg\_long\_dbl()" on page 15-25
- "start\_arg\_long\_dbl()" on page 15-64
- "end\_arg\_long\_dbl()" on page 15-98

# offset\_arg\_long\_long()

# **DESCRIPTION**

The offset\_arg\_long\_long() function returns the value of a particular *trace event argument* for the ordinal trace event (offset).

# **SYNTAX**

offset\_arg[N]\_long\_long(offset\_expr)

### **PARAMETERS**

Ν

Specifies the *N*th argument logged with the *trace event*. Defaults to 1.

offset\_expr

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

# **RETURN TYPE**

long long integer

- "num\_args()" on page 15-44
- "arg\_long\_long()" on page 15-26
- "start\_arg\_long\_long()" on page 15-65
- "end\_arg\_long\_long()" on page 15-99

# offset\_blk\_arg()

# **DESCRIPTION**

The offset\_blk\_arg() function returns the value of a trace event argument located at a particular byte offset in the argument space associated with the ordinal trace event (offset).

### **SYNTAX**

offset\_blk\_arg(byte\_offset,offset\_expr)

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

 $offset\_expr$ 

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

### **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "blk\_arg()" on page 15-27
- "start\_blk\_arg()" on page 15-66
- "end\_blk\_arg()" on page 15-100

# offset\_blk\_arg\_bits()

### **DESCRIPTION**

The offset\_blk\_arg\_bits() function returns the value of a trace event signed bit field argument located at a particular byte and bit offset with a particular bit size in the argument space associated with the event associated with the ordinal trace event (offset).

## **SYNTAX**

offset\_blk\_arg\_bits (byte\_offset, bit\_offset, bit\_size, offset\_expr)

# **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

bit offset

Specifies the bit offset of the argument recorded with the *trace\_event\_blk*.

bit size

Specifies the size in bits of the argument record with trace\_event\_blk.

offset\_expr

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

#### **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "blk\_arg\_bits()" on page 15-28
- "start\_blk\_arg\_bits()" on page 15-67
- "end\_blk\_arg\_bits()" on page 15-101

# offset\_blk\_arg\_char()

## **DESCRIPTION**

The offset\_blk\_arg\_char() function returns the value of a trace event signed character argument located at a particular byte offset in the argument space associated with the event associated with the ordinal trace event (offset).

### **SYNTAX**

offset\_blk\_arg\_char (byte\_offset, offset\_expr)

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

 $offset\_expr$ 

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

### **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "blk\_arg\_char()" on page 15-29
- "start\_blk\_arg\_char()" on page 15-68
- "end\_blk\_arg\_char()" on page 15-102

# offset\_blk\_arg\_dbl()

## **DESCRIPTION**

The offset\_blk\_arg\_dbl() function returns the value of a trace event double-precision floating point argument located at a particular byte offset in the argument space associated with the event associated with the ordinal trace event (offset).

### **SYNTAX**

offset\_blk\_arg\_dbl (byte\_offset, offset\_expr)

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

offset\_expr

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

### **RETURN TYPE**

double-precision floating point

- "num\_args()" on page 15-44
- "blk\_arg\_dbl()" on page 15-30
- "start\_blk\_arg\_dbl()" on page 15-69
- "end\_blk\_arg\_dbl()" on page 15-103

# offset\_blk\_arg\_flt()

## **DESCRIPTION**

The offset\_blk\_arg\_flt() function returns the value of a trace event single-precision floating point argument located at a particular byte offset in the argument space associated with the event associated with the ordinal trace event (offset).

### **SYNTAX**

```
offset blk_arg_flt (byte_offset, offset_expr)
```

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

 $offset\_expr$ 

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

### **RETURN TYPE**

double-precision floating point

- "num\_args()" on page 15-44
- "blk\_arg\_flt()" on page 15-31
- "start\_blk\_arg\_flt()" on page 15-70
- "end\_blk\_arg\_flt()" on page 15-104

# offset\_blk\_arg\_long()

# **DESCRIPTION**

The offset\_blk\_arg\_long() function returns the value of a trace event long integer argument located at a particular byte offset in the argument space associated with the event associated with the ordinal trace event (offset).

### **SYNTAX**

offset\_blk\_arg\_long (byte\_offset, offset\_expr)

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

offset\_expr

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

### **RETURN TYPE**

long integer

- "num\_args()" on page 15-44
- "blk\_arg\_long()" on page 15-32
- "start\_blk\_arg\_long()" on page 15-71
- "end\_blk\_arg\_long()" on page 15-105

# offset\_blk\_arg\_long\_bits()

### **DESCRIPTION**

The offset\_blk\_arg\_long\_bits() function returns the value of a trace event signed long bit field argument located at a particular byte and bit offset with a particular bit size in the argument space associated with the event associated with the ordinal trace event (offset).

### **SYNTAX**

```
offset_blk_arg_long_bits (byte_offset, bit_offset, bit_size, offset_expr)
```

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace event blk.

bit offset

Specifies the bit offset of the argument recorded with the *trace\_event\_blk*.

bit size

Specifies the size in bits of the argument record with *trace\_event\_blk*.

offset\_expr

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

### **RETURN TYPE**

long integer

- "num\_args()" on page 15-44
- "blk\_arg\_long\_bits()" on page 15-33
- "start\_blk\_arg\_long\_bits()" on page 15-72
- "end\_blk\_arg\_long\_bits()" on page 15-106

# offset\_blk\_arg\_long\_dbl()

# **DESCRIPTION**

The offset\_blk\_arg\_long\_dbl() function returns the value of a trace event long double-precision floating point argument located at a particular byte offset in the argument space associated with the event associated with the ordinal trace event (offset).

## **SYNTAX**

offset\_blk\_arg\_long\_dbl(byte\_offset,offset\_expr)

## **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

 $offset\_expr$ 

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

### **RETURN TYPE**

long double-precision floating point

- "num\_args()" on page 15-44
- "blk\_arg\_long\_dbl()" on page 15-34
- "start\_blk\_arg\_long\_dbl()" on page 15-73
- "end\_blk\_arg\_long\_dbl()" on page 15-107

# offset\_blk\_arg\_long\_long()

## **DESCRIPTION**

The offset\_blk\_arg\_long\_long() function returns the value of a trace event long long integer argument located at a particular byte offset in the argument space associated with the ordinal trace event (offset).

### **SYNTAX**

offset\_blk\_arg\_long\_long(byte\_offset,offset\_expr)

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

 $offset\_expr$ 

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

### **RETURN TYPE**

long long integer

- "num\_args()" on page 15-44
- "blk\_arg\_long\_long()" on page 15-35
- "start\_blk\_arg\_long\_long()" on page 15-74
- "end\_blk\_arg\_long\_long()" on page 15-108

# offset\_blk\_arg\_long\_ubits()

### **DESCRIPTION**

The offset\_blk\_arg\_long\_ubits() function returns the value of a trace event unsigned long integer bit field argument located at a particular byte and bit offset with a particular bit size in the argument space associated with the ordinal trace event (offset).

## **SYNTAX**

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace event blk.

bit offset

Specifies the bit offset of the argument recorded with the *trace\_event\_blk*.

bit size

Specifies the size in bits of the argument record with trace\_event\_blk.

offset\_expr

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

## **RETURN TYPE**

long long integer

- "num\_args()" on page 15-44
- "blk\_arg\_long\_ubits()" on page 15-36
- "start\_blk\_arg\_long\_ubits()" on page 15-75
- "end\_blk\_arg\_long\_ubits()" on page 15-109

# offset\_blk\_arg\_short()

## **DESCRIPTION**

The offset\_blk\_arg\_short() function returns the value of a trace event short integer argument located at a particular byte offset in the argument space associated with the ordinal trace event (offset).

## **SYNTAX**

offset\_blk\_arg\_short (byte\_offset, offset\_expr)

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

offset\_expr

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

### **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "blk\_arg\_short()" on page 15-37
- "start\_blk\_arg\_short()" on page 15-76
- "end\_blk\_arg\_short()" on page 15-110

# offset\_blk\_arg\_string()

### **DESCRIPTION**

The offset\_blk\_arg\_string() function returns the value of a trace event null terminated string argument located at a particular byte offset in the argument space associated with the event associated with the ordinal trace event (offset).

### **SYNTAX**

offset\_blk\_arg\_string(byte\_offset, max\_size, offset\_expr)

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk* or *trace\_event\_string*.

max\_size

Specifies the maximum length of string that might be returned. If the arguments were recorded with *trace\_event\_blk*, this is also the total number of bytes allocated in the block for the string, regardless of its actual length.

offset\_expr

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

## **RETURN TYPE**

string

- "num\_args()" on page 15-44
- "blk\_arg\_string()" on page 15-38
- "start\_blk\_arg\_string()" on page 15-77
- "end\_blk\_arg\_string()" on page 15-111

# offset\_blk\_arg\_ubits()

### **DESCRIPTION**

The offset\_blk\_arg\_ubits() function returns the value of a trace event unsigned bit field argument located at a particular byte and bit offset with a particular bit size in the argument space associated with the ordinal trace event (offset).

### **SYNTAX**

offset\_blk\_arg\_ubits (byte\_offset, bit\_offset, bit\_size, offset\_expr)

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with *trace\_event\_blk*.

bit offset

Specifies the bit offset of the argument recorded with the *trace\_event\_blk*.

bit size

Specifies the size in bits of the argument record with *trace\_event\_blk*.

offset\_expr

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

## **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "blk\_arg\_ubits()" on page 15-39
- "start\_blk\_arg\_ubits()" on page 15-78
- "end\_blk\_arg\_ubits()" on page 15-112

# offset\_blk\_arg\_uchar()

## **DESCRIPTION**

The offset\_blk\_arg\_uchar() function returns the value of a trace event unsigned character argument located at a particular byte offset in the argument space associated with the event associated with the ordinal trace event (offset).

### **SYNTAX**

offset\_blk\_arg\_uchar (byte\_offset, offset\_expr)

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

offset\_expr

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

### **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "blk\_arg\_uchar()" on page 15-40
- "start\_blk\_arg\_uchar()" on page 15-79
- "end\_blk\_arg\_uchar()" on page 15-113

# offset\_blk\_arg\_uint()

### **DESCRIPTION**

The offset\_blk\_arg\_uint() function converts the unsigned integer trace event argument at a particular byte offset in the argument space associated with the ordinal trace event (offset) to a long.

### **NOTE**

You can convert the long return value to an unsigned value using the cast operator. For example:

```
(unsigned long) offset_blk_arg_uint(0) > 0x80000000
```

### **SYNTAX**

```
offset_blk_arg_uint (byte_offset, offset_expr)
```

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

offset\_expr

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

### **RETURN TYPE**

unsigned integer

- "num\_args()" on page 15-44
- "blk\_arg\_uint()" on page 15-41
- "start\_blk\_arg\_uint()" on page 15-80
- "end\_blk\_arg\_uint()" on page 15-114

# offset\_blk\_arg\_ulong\_long()

# **DESCRIPTION**

The offset\_blk\_arg\_ulong\_long() function returns the value of a trace event unsigned long long integer argument located at a particular byte offset in the argument space associated with the ordinal trace event (offset).

### **SYNTAX**

offset\_blk\_arg\_ulong\_long(byte\_offset,offset\_expr)

### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

offset\_expr

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

### **RETURN TYPE**

unsigned long long integer

- "num\_args()" on page 15-44
- "blk\_arg\_ulong\_long()" on page 15-42
- "start\_blk\_arg\_ulong\_long()" on page 15-81
- "end\_blk\_arg\_ulong\_long()" on page 15-115

# offset\_blk\_arg\_ushort()

## **DESCRIPTION**

The offset\_blk\_arg\_ushort() function returns the value of a trace event unsigned short integer argument located at a particular byte offset in the argument space associated with the ordinal trace event (offset).

### **SYNTAX**

offset\_blk\_arg\_ushort (byte\_offset, offset\_expr)

#### **PARAMETERS**

byte offset

Specifies the byte offset of the argument recorded with trace\_event\_blk.

offset\_expr

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

### **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "blk\_arg\_ushort()" on page 15-43
- "start\_blk\_arg\_ushort()" on page 15-82
- "end\_blk\_arg\_ushort()" on page 15-116

# offset\_num\_args()

# **DESCRIPTION**

The offset\_num\_args() function returns the number of arguments logged with the ordinal trace event (offset). For events recorded with trace\_event\_blk(), it returns the number of bytes recorded in the argument space.

### **SYNTAX**

offset\_num\_args(offset\_expr)

### **PARAMETERS**

 $offset\_expr$ 

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

## **RETURN TYPE**

integer

- "num\_args()" on page 15-44
- "start\_num\_args()" on page 15-83
- "end\_num\_args()" on page 15-117
- "offset\_arg()" on page 15-133
- "offset\_arg\_dbl()" on page 15-134

# offset\_pid()

# **DESCRIPTION**

The offset\_pid() function returns the PID from which the ordinal trace event (offset) was logged.

### **NOTE**

All Linux threads within the same program share the same PID value. For trace events generated with the NightTrace Logging API, the value logged as the process identifier is the common PID..

## **SYNTAX**

offset\_pid (offset\_expr)

### **PARAMETERS**

offset\_expr

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

### **RETURN TYPE**

integer

- "pid()" on page 15-46
- "start\_pid()" on page 15-84
- "end\_pid()" on page 15-118

# offset\_thread\_id()

# **DESCRIPTION**

The offset\_thread\_id() function returns the *thread* identifier from which the ordinal trace event (*offset*) was logged. The thread identifier is the value returned from the system call <code>gettid(2)</code>.

### **SYNTAX**

offset\_thread\_id(offset\_expr)

### **PARAMETERS**

 $offset\_expr$ 

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

# **RETURN TYPE**

integer

- "thread\_id()" on page 15-47
- "start\_thread\_id()" on page 15-85
- "end\_thread\_id()" on page 15-119

# offset\_tid()

# **DESCRIPTION**

The offset\_tid() function returns the internally-assigned NightTrace thread identifier (*TID*) from which the ordinal trace event (*offset*) was logged.

# **SYNTAX**

```
offset_tid (offset_expr)
```

## **PARAMETERS**

```
offset_expr
```

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

## **RETURN TYPE**

integer

- "tid()" on page 15-48
- "start\_tid()" on page 15-86
- "end\_tid()" on page 15-120

# offset\_cpu()

## **DESCRIPTION**

The offset\_cpu() function returns the logical CPU number on which the ordinal trace event (offset) occurred. CPUs are logically numbered starting at 0 and monotonically increase thereafter.

### **NOTE**

This function is only valid when applied to events from Night-Trace kernel trace event files. Kernel tracing is not supported on all operating systems. See "Kernel Dependencies" on page B-1 for more information.

## **SYNTAX**

offset\_cpu (offset\_expr)

### **PARAMETERS**

offset\_expr

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

## **RETURN TYPE**

integer

- "cpu()" on page 15-49
- "start\_cpu()" on page 15-87
- "end\_cpu()" on page 15-121

# offset\_time()

# **DESCRIPTION**

The offset\_time() function returns the time in seconds between the beginning of the trace run and the ordinal trace event (offset).

# **SYNTAX**

```
offset_time (offset_expr)
```

## **PARAMETERS**

```
offset_expr
```

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

## **RETURN TYPE**

double-precision floating point

- "time()" on page 15-51
- "start\_time()" on page 15-89
- "end\_time()" on page 15-123

# offset\_node\_id()

# **DESCRIPTION**

The offset\_node\_id() function returns the internally-assigned *node identifier* from which the ordinal trace event (*offset*) was logged.

# **SYNTAX**

offset\_node\_id(offset\_expr)

## **PARAMETERS**

offset\_expr

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

# **RETURN TYPE**

integer

- "node\_id()" on page 15-52
- "start\_node\_id()" on page 15-90
- "end\_node\_id()" on page 15-124

# offset\_node\_name()

# **DESCRIPTION**

The offset\_node\_name() function returns the name of the system from which the ordinal trace event (offset) was logged.

# **SYNTAX**

offset\_node\_name (offset\_expr)

## **PARAMETERS**

offset\_expr

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

## **RETURN TYPE**

string

- "node\_name()" on page 15-53
- "start\_node\_name()" on page 15-91
- "end\_node\_name()" on page 15-125

# offset\_process\_name()

# **DESCRIPTION**

The offset\_process\_name() function returns the name of the process (PID) from which the ordinal trace event (offset) was logged.

# **SYNTAX**

offset\_process\_name (offset\_expr)

## **PARAMETERS**

offset\_expr

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

# **RETURN TYPE**

string

## **SEE ALSO**

• "process\_name()" on page 15-54

# offset\_thread\_name()

# **DESCRIPTION**

The offset\_thread\_name() function returns the thread name from which the ordinal trace event (offset) was logged.

# **SYNTAX**

offset\_thread\_name (offset\_expr)

## **PARAMETERS**

offset\_expr

An expression that evaluates to the *offset* (or ordinal trace event number) of a trace event.

## **RETURN TYPE**

string

## **SEE ALSO**

• "thread\_name()" on page 15-55

# **Summary Functions**

You usually use summary functions on the Summarize Form. Except for summary\_matches(), all of these functions take another expression as a parameter. They include the following:

- min()
- max()
- avg()
- sum()
- min\_offset()
- max\_offset()
- summary\_matches()

# min()

## **DESCRIPTION**

The min() function returns the minimum value of all occurrences of *expr* within a time range. When used in a Summarize Form, the time range is defined by that form. When used elsewhere, the time range is defined as the region starting with the first *trace event* and ending with the *current trace event*.

#### **SYNTAX**

min (expr)

#### **PARAMETERS**

expr

A numeric expression.

#### **RETURN TYPE**

data type of expr

# **SEE ALSO**

# max()

# **DESCRIPTION**

The max() function returns the maximum value of all occurrences of *expr* within a time range. When used in a Summarize Form, the time range is defined by that form. When used elsewhere, the time range is defined as the region starting with the first *trace event* and ending with the *current trace event*.

## **SYNTAX**

 $\max(expr)$ 

## **PARAMETERS**

expr

A numeric expression.

# **RETURN TYPE**

data type of expr

# **SEE ALSO**

# avg()

# **DESCRIPTION**

The avg() function returns the average value of all occurrences of *expr* within a time range. When used in a Summarize Form, the time range is defined by that form. When used elsewhere, the time range is defined as the region starting with the first *trace event* and ending with the *current trace event*.

## **SYNTAX**

avg (expr)

## **PARAMETERS**

expr

A numeric expression.

# **RETURN TYPE**

data type of expr

## **SEE ALSO**

# sum()

# **DESCRIPTION**

The sum() function returns the sum value of all occurrences of *expr* within a time range. When used in a Summarize Form, the time range is defined by that form. When used elsewhere, the time range is defined as the region starting with the first *trace event* and ending with the *current trace event*.

## **SYNTAX**

sum (expr)

## **PARAMETERS**

expr

A numeric expression.

# **RETURN TYPE**

data type of expr

# **SEE ALSO**

# min\_offset()

# **DESCRIPTION**

The min\_offset() function returns the ordinal trace event (offset) where the minimum value of the parameter occurred for matches in the time range. Thus, if the same minimum was seen more than once, the offset corresponds to the first one seen.

## **SYNTAX**

```
min_offset (expr)
```

## **PARAMETERS**

expr

A numeric expression.

## **RETURN TYPE**

integer

#### NOTE

There is no function that returns the trace event ID where the minimum value of the first argument occurred for all matches in the time range. You could obtain this value by nesting the functions as follows:

```
offset_id( min_offset( arg1() ) )
```

## **SEE ALSO**

# max\_offset()

# **DESCRIPTION**

The max\_offset() function returns the ordinal trace event (offset) where the maximum value of the parameter occurred for matches in the time range. Thus, if the same maximum was seen more than once, the offset corresponds to the first one seen.

# **SYNTAX**

```
max_offset (expr)
```

# **PARAMETERS**

expr

A numeric expression.

## **RETURN TYPE**

integer

#### **NOTE**

There is no function that returns the trace event ID where the maximum value of the first argument occurred for all matches in the time range. You could obtain this value by nesting the functions as follows:

```
offset_id( max_offset( arg1() ) )
```

## **SEE ALSO**

# summary\_matches()

# **DESCRIPTION**

The  $summary_matches()$  function returns the number of times the summary criteria was matched in the time range.

# **SYNTAX**

summary\_matches()

# **RETURN TYPE**

integer

- "event\_matches()" on page 15-57
- "state\_matches()" on page 15-128

# **Format and Table Functions**

The format function allows you to display a string. The table functions allow you to extract information from user-defined and pre-defined string and format tables. These functions include the following:

- get\_string()
- get\_item()
- get format()
- format()
- lookup pc()

For more information about tables, see "Tables" on page 6-12.

# get\_string()

The get\_string() routine dynamically looks up a string in a string table.

#### **SYNTAX**

```
get_string (table_name[, int_expr])
```

## **PARAMETERS**

table\_name

table\_name is an unquoted character string that represents the name of a string table. To avoid possible forward reference problems, try to make your get\_string() calls refer to previously-defined string tables. The following string table names are pre-defined in NightTrace: event, pid, tid, boolean, node\_name, pid\_nodename, tid\_nodename, vector, syscall, and device. For more information on these tables, see "Pre-Defined Strings Tables" on page 6-15.

int\_expr

int\_expr is an integer expression that acts as an index into the specified string table.
int\_expr must either match an identifying integer value in the table\_name string
table, or the table\_name string table must have a default item line; otherwise
get\_string() returns a string of int\_expr in decimal. Often int\_expr is based on a
NightTrace function.

If your table consists of only a default item line, omit this parameter.

#### **DESCRIPTION**

The following NightTrace constructs can call get\_string() to dynamically locate a static string in a string table:

- A Condition, Start Condition, or End Condition of a display object configuration
- A Condition, Start Condition, or End Condition of a Profile configuration
- An Output Text field of a Data Box
- A value field of a format table

For each get\_string() call, NightTrace follows these steps:

- 1. Evaluates int\_expr
- 2. Uses this value as an index into table\_name
- 3. Retrieves the associated string from *table\_name*
- 4. Returns a string

The following lines provide a brief example of a call to get\_string().

```
string_table (conditions) = {
  item = 1, "normal";
  item = 50, "YELLOW ALERT";
  item = 99, "RED ALERT";
  default_item = "N/A";
};
```

In this example the numeric argument associated with a trace event represents the current conditions (conditions). If the argument has the value 99, NightTrace:

- 1. Uses the value 99 as in index into conditions
- 2. Retrieves the associated string ("RED ALERT") from conditions
- 3. Returns "RED ALERT"

#### **RETURN TYPES**

On successful completion, <code>get\_string()</code> returns a string from a string table. NightTrace returns a string of the item number, <code>int\_expr</code>, in decimal if <code>table\_name</code> is not found, or if <code>int\_expr</code> is not found and there is no default item line. The first time <code>table\_name</code> is not found, NightTrace issues an error message. Because <code>get\_string()</code> returns a string, you can use it anywhere a string expression is appropriate.

For more information on string tables, see "String Tables" on page 6-13.

# get\_item()

The get\_item() routine looks up an item number in a string table.

#### **SYNTAX**

```
int get_item(table_name, "str_const")
```

#### **PARAMETERS**

table name

table\_name is an unquoted character string that represents the name of a string table. To avoid possible forward reference problems, try to make your get\_item() calls refer to previously-defined string tables. The following string table names are pre-defined in NightTrace: event, pid, tid, boolean, node\_name, pid\_nodename, and tid\_nodename..

str\_const

str\_const is a string constant literal that acts as an index into the specified string table. str\_const must either exactly match a string value in the table\_name string table, or the table\_name string table must have a default item line; otherwise the results are undefined. A table\_name may contain several item lines with the same str\_const value.

#### **DESCRIPTION**

Typically, a get\_item() call is used in conditional expressions for profiles, searches, summaries, or display object configurations.

The get\_item() call returns an index number into the specified string table (table\_name) for the first item in the table which matches the specified string (str\_const).

For example, assume that the following string table definition is in your page configuration file (see "String Tables" on page 6-13):

```
string_table (fruit) = {
  item = 3, "apple";
  item = 4, "orange";
  item = 5, "cherry";
  item = 6, "banana";
  default_item = "Unknown";
};
```

A get\_item() call can be used in an Condition when configuring a Data Box (see "Data Graph" on page 11-12):

#### Condition

```
arg1 = get_item(fruit, "cherry")
```

requiring the first argument of the associated trace event to be the same as the index value matching the entry for cherry in the fruit string table (which, in our example, is 5).

#### **RETURN TYPES**

On successful completion, <code>get\_item()</code> returns an item number from a string table. If several item lines within the string table have the same string value as <code>str\_const</code>, <code>get\_item()</code> returns the first item number from one of these item lines. If <code>table\_name</code> is not found, NightTrace issues an error message, and the results are undefined. If <code>str\_const</code> is not found and there is no default item line, the results are undefined. Because <code>get\_item()</code> returns an integer, you can use it anywhere an integer expression can be used.

For more information on string tables, see "String Tables" on page 6-13.

# get\_format()

The get\_format() routine dynamically looks up a string in a format table.

#### **SYNTAX**

```
get_format (table_name[, int_expr])
```

#### **PARAMETERS**

table name

table\_name is an unquoted character string that represents the name of a format table. To avoid possible forward reference problems, try to make your get\_format() calls refer to previously-defined format tables.

int\_expr

int\_expr is an integer expression that acts as an index into the specified format table.
int\_expr must either match an identifying integer value in the table\_name format table, or the table\_name format table must have a default item line; otherwise, the results are undefined. Often int\_expr is based on a NightTrace function.

If your table consists of only a default item line, omit this parameter.

## **DESCRIPTION**

A call to  $get\_format()$  must be the  $\underline{first}$  function call in an expression. You must not nest calls to  $get\_format()$ .

The Output Text field of a Data Box configuration can call <code>get\_format()</code> to dynamically locate a string in a format table. For each <code>get\_format()</code> call, Night-Trace follows these steps:

- 1. Evaluates *int\_expr*
- 2. Uses this value as an index into table name
- 3. Retrieves the associated string from table\_name
- 4. Replaces any conversion specifications in the associated string
- 5. Returns a string

Assume that the following format table definition is in your configuration file.

```
format_table (what_pid) = {
   item = 1, "Trace event 1 logged by pid %d'%d", "raw_pid()",
        "lwpid()";
   default_item = "Unaccounted for event ID (%d)", "id()";
};
```

Assume that you make the following call in the Then-Expression of a Data Box.

```
get_format (what_pid, id())
```

In this example, the what\_pid format table associates one dynamically-generated string with trace event ID 1 (id() == 1) and another string with all other trace events (default\_item). When NightTrace processes a trace event for the display object with the above get\_format(), it:

- 1. Evaluates the NightTrace id() function. (Assume it evaluates to 1)
- Calls get\_format()
- 3. Uses this value (1) as an index into the what\_pid format table
- 4. Retrieves the associated string ("Trace event 1 logged by pid %d'%d") from the what\_pid format table
- 5. Evaluates the NightTrace raw\_pid() and lwpid() functions. (Assume they evaluate to 213 and 1 respectively)
- 6. Replaces the %d conversion specifiers with the raw\_pid() and lwpid() values
- 7. Displays "Trace event 1 logged by pid 213'1"

## **RETURN TYPES**

On successful completion, get\_format() returns a format table string. Otherwise, it returns an empty string.

For more information on format tables, see "Format Tables" on page 6-17.

# format()

The format() routine displays a string.

#### **SYNTAX**

format ("format\_string" [, arg] ...)

#### **PARAMETERS**

format\_string

format\_string controls how the optional args are displayed. format\_string is based on the format parameter used in the printf(3) routine in C. It is a character string enclosed in double quotes that contains literal characters and conversion specifications. The literals are copied as is to the display object. Conversion specifications modify zero or more args.

arg

arg is an optional expression to be formatted and displayed.

#### **DESCRIPTION**

Call the format() function to display a string. You can do this only from the Output Text field of a Data Box. A call to format() must be the <u>first</u> function call in an expression. You must not nest calls to format().

The following lines provide examples of format() statements and what they display. Assume all variables have a value of 10 (decimal).

format( "Error")	Error
format( "Event=%d", id() )	Event=10
format( "Argument is %X", arg1())	Argument is A

#### **RETURN TYPES**

On successful completion, format() returns a string. Otherwise, it returns an empty string.

# lookup\_pc()

The lookup\_pc() routine returns the location of a program counter in the specified executable file.

#### **SYNTAX**

```
char * lookup_pc (long pc_value, char * executable_file_path)
```

#### **PARAMETERS**

```
pc_value
```

the address pointer value of the instruction to be located.

```
executable_file_path
```

the path of the executable file containing the pc.

#### **DESCRIPTION**

This function can be used in expressions, typically in format () statements.

Given a PC value, it returns a string describing the location of the PC in the specified executable file. The string returned includes the name of the routine containing it and the file and line number associated with the PC, depending on how much symbolic and debug information is available in the file.

NightTrace attempts to locate the executable using the specified *executable\_file\_path*. If the specified path is a simple file name without a directory indication, NightTrace will first attempt to match the file's specified simple name with those of any executables given on the command line. Otherwise, NightTrace will attempt to locate the file exactly as specified. For example,

```
ntrace /tmp/a.out
...
format ("My PC is %s", lookup_pc(arg1,"a.out"))
will refer to /tmp/a.out, whereas
format ("My PC is %s", lookup_pc(arg1,"./a.out"))
will reference $PWD/./a.out.
```

A handy way to use lookup\_pc is to use the built-in NightTrace function process\_name(). For example:

```
format ("My PC is %s", lookup_pc(arg1,process_name()))
```

substitutes the name of the process associated with the current trace event.

# **RETURN TYPES**

A string is always returned from lookup\_pc() regardless of whether it can locate the specified file or can obtain symbolic information from it. At a minimum, the string returned includes the address passed in as  $pc\_value$  in hexadecimal notation.

# **Profile References**

*Profile references* provide a means for referencing a set of one or more trace events which may be restricted by conditions specified by the user.

Profile references can be used within trace event functions (see "Trace Event Functions" on page 15-19).

A profile reference is simply the name of the profile.

Profiles are created and managed using the Profiles Definition panel (see "Profiles Dialog" on page 12-2 for more information).

# **Using the NightTrace Analysis API**

The NightTrace graphical user interface is one of the primary tools for analyzing trace data (see "The NightTrace Main Window" on page 7-1). However, the NightTrace Analysis Application Programming Interface provides users with even further control in summarizing or monitoring trace data.

The NightTrace Analysis API provides a basic interface to the data produced by NightTrace allowing users to process NightTrace data programmatically. It allows users to customize their analysis of NightTrace data, both expressly via user-written programs and as customized batch summaries.

For instance, a user may want to provide customized reports on user application or kernel activity, monitor a user application or the operating system itself and take action when a specific situation occurs, or filter a trace data file (to significantly reduce its size) for subsequent use with the GUI or API.

The NightTrace Analysis API can use either NightTrace data files generated by NightTrace user daemons or may reference a file descriptor connected to a streaming daemon as the input source.

The API allows the user to control the order in which the data is accessed and provides for event filtration as well as customized event and state definition specification using conditions currently provided in the NightTrace GUI tool.

In addition, all functions supported by the NightTrace GUI expression language are provided as user-callable functions.

The following sections describe the data structures and functions that comprise the Night-Trace Analysis API.

Sample programs using these data structures and functions are also provided (see "Night-Trace Analysis API Examples" on page E-1).

# **NightTrace Analysis Application Programming Interface**

The NightTrace Analysis Application Programming Interface consists of a number of data structures (see "Data Structures" on page 16-3) and functions (see "Functions" on page 16-10).

These data structures and functions are accessible via the C header file:

/usr/include/ntrace\_analysis.h

and the C library:

/usr/lib/libntrace\_analysis.a

and can be called by C and C++ programs.

Another useful file is /usr/include/ntrace\_events.h. That file contains #define values for all the kernel events and other special NightTrace events.

# **Data Structures**

The following data structures are part of the NightTrace Analysis Application Programming Interface:

```
- tr_arg_t (see "tr_arg_t" on page 16-3)
- tr_cb_t (see "tr_cb_t" on page 16-4)
- tr_cond_cb_func_t (see "tr_cond_cb_func_t" on page 16-4)
- tr_cond_func_t (see "tr_cond_func_t" on page 16-5)
- tr_cond_t (see "tr_cond_t" on page 16-5)
- tr_dir_t (see "tr_dir_t" on page 16-5)
- tr_offset_t (see "tr_offset_t" on page 16-5)
- tr_state_action_t (see "tr_state_action_t" on page 16-6)
- tr_state_b_func_t (see "tr_state_cb_func_t" on page 16-6)
- tr_state_info_t (see "tr_state_info_t" on page 16-7)
- tr_state_t (see "tr_state_t" on page 16-8)
- tr_stream_event_t (see "tr_stream_event_t" on page 16-8)
- tr_string_node_t (see "tr_string_node_t" on page 16-8)
- tr_string_node_t (see "tr_string_node_t" on page 16-8)
- tr_t (see "tr_t" on page 16-9)
```

See "Functions" on page 16-10 for information about the functions available in the Night-Trace Analysis API.

# tr\_arg\_t

tr\_arg\_t is defined as:

# tr\_cb\_t

tr\_cb\_t is an opaque handle that identies a particular callback. It is defined as:

```
typedef int tr_cb_t;
```

See "Data Structures" on page 16-3 for other data structures included in the NightTrace Analysis API.

# tr\_cond\_cb\_func\_t

# **PARAMETERS**

t

data set handle

c

handle of the condition associated with this call

offset

offset of the trace event satisfying the condition

occurrence

number of times the condition has been satisfied thus far

context

user-defined field specified when the callback is defined

disable

pointer to an integer; if the user sets the integer to a non-zero value, the registration of this function for the specified condition will be disabled for the remainder of the iteration pass

#### **SEE ALSO**

- "tr t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_offset\_t" on page 16-5

# tr\_cond\_func\_t

tr cond func t is defined as:

See "Data Structures" on page 16-3 for other data structures included in the NightTrace Analysis API.

# tr\_cond\_t

tr\_cond\_t is an opaque handle used to identify a particular condition. It is defined as:

```
typedef long tr_cond_t;
```

See "Data Structures" on page 16-3 for other data structures included in the NightTrace Analysis API.

# tr\_dir\_t

tr\_dir\_t is defined as:

```
typedef enum {tr_forward, tr_backward} tr_dir_t;
```

See "Data Structures" on page 16-3 for other data structures included in the NightTrace Analysis API.

# tr\_offset\_t

tr\_offset\_t is defined as:

```
typedef int tr_offset_t;
```

Values of type tr\_offset\_t represent the offset (aka position) of a trace event within the data set. Event offsets are assigned as monotonically increasing integers, starting with zero as the offset of the first event in the data set.

Functions which return tr\_offset\_t may return TR\_EOF, which indicates exceeding past either the beginning or end of the data set, respectively.

# tr\_state\_action\_t

tr\_state\_action\_t is an enumerated type which is used to specify when a certain function will be called. It is defined as:

See "Data Structures" on page 16-3 for other data structures included in the NightTrace Analysis API.

# tr\_state\_cb\_func\_t

#### **PARAMETERS**

```
t data set handle state
```

handle of the state associated with this call

```
offset
```

offset of the trace event satisfying the condition

occurrence

number of times the condition has been satisfied thus far

context

user-defined field specified when the callback is defined

disable

pointer to an integer; if the user sets the integer to a non-zero value, the registration of this function for the specified state will be disabled for the remainder of the iteration pass

See "Data Structures" on page 16-3 for other data structures included in the NightTrace Analysis API.

# tr\_state\_info\_t

```
tr_state_info_t is defined as:
     typedef struct {
         tr_offset_t start_offset;
         tr_offset_t end_offset;
         double gap;
         double duration;
         int count;
     } tr_state_info_t;
where:
     start_offset
          offset of the event that started the specified state
     end_offset
          offset of the event that ended the specified state
     gap
          time in seconds between the beginning of the last instance of the specified
          state and the end of the previous instance (or zero if no previous instance
          exists)
     duration
          time in seconds during which the specified state was active
     count
          number of completed instances of the specified state
```

See "Data Structures" on page 16-3 for other data structures included in the NightTrace Analysis API.

# tr\_state\_t

tr\_state\_t is an opaque handle used to identify a particular state. It is defined as:

```
typedef long tr state t;
```

See "Data Structures" on page 16-3 for other data structures included in the NightTrace Analysis API.

# tr\_stream\_event\_t

#### **NOTE**

The tr\_stream\_overflow event has been deprecated and no longer occurs.

See "Data Structures" on page 16-3 for other data structures included in the NightTrace Analysis API.

# tr stream func t

See "Data Structures" on page 16-3 for other data structures included in the NightTrace Analysis API.

# tr\_string\_node\_t

tr\_string\_node\_t is defined as:

```
typedef struct {
   int item;
   char * value;
} tr_string_node_t;
```

tr\_t

tr\_t is an opaque handle used to identify a particular data set. It is defined as:

# **Functions**

The functions that comprise the NightTrace Analysis Application Programming Interface are broken down into the following categories:

- "API Initialization and Destruction" on page 16-15
- "Error Detection, Collection, and Reporting" on page 16-17
- "Input Specification and Streaming Control" on page 16-19
- "Event Offset Positioning" on page 16-26
- "Basic Event Attribute Functions" on page 16-31
- "Conditions" on page 16-88
- "State-oriented Interfaces" on page 16-120
- "Output Function" on page 16-136
- "String Table Functions" on page 16-138
- "Callback Interfaces" on page 16-143

The following is a complete list of functions included in the NightTrace Analysis API:

- tr\_activate() (see "tr\_activate()" on page 16-131)
- tr append table() (see "tr append table()" on page 16-141)
- tr\_arg\_dbl() (see "tr\_arg\_dbl()" on page 16-39)
- tr\_arg\_dbl\_() (see "tr\_arg\_dbl\_()" on page 16-46)
- tr\_arg\_int() (see "tr\_arg\_int()" on page 16-37)
- tr\_arg\_int\_() (see "tr\_arg\_int\_()" on page 16-45)
- tr\_argtype() (see "tr\_argtype()" on page 16-51)
- tr\_argtype\_() (see "tr\_argtype\_()" on page 16-52)
- tr\_blk\_arg() (see "tr\_blk\_arg()" on page 16-52)
- tr\_blk\_arg\_() (see "tr\_blk\_arg\_()" on page 16-53)
- tr\_blk\_arg\_bits() (see "tr\_blk\_arg\_bits()" on page 16-54)
- tr\_blk\_arg\_bits\_() (see "tr\_blk\_arg\_bits\_()" on page 16-55)
- tr\_blk\_arg\_char() (see "tr\_blk\_arg\_char()" on page 16-56)
- tr\_blk\_arg\_char\_() (see "tr\_blk\_arg\_char\_()" on page 16-56)
- tr\_blk\_arg\_dbl() (see "tr\_blk\_arg\_dbl()" on page 16-57)
- tr\_blk\_arg\_dbl\_() (see "tr\_blk\_arg\_dbl\_()" on page 16-58)
- tr\_blk\_arg\_flt() (see "tr\_blk\_arg\_flt()" on page 16-59)

- tr\_blk\_arg\_flt\_() (see "tr\_blk\_arg\_flt\_()" on page 16-59)
- tr\_blk\_arg\_long() (see "tr\_blk\_arg\_long()" on page 16-60)
- tr\_blk\_arg\_long\_() (see "tr\_blk\_arg\_long\_()" on page 16-61)
- tr\_blk\_arg\_long\_bits() (see "tr\_blk\_arg\_long\_bits()" on page 16-62)
- tr\_blk\_arg\_long\_bits\_() (see "tr\_blk\_arg\_long\_bits\_()" on page 16-63)
- tr\_blk\_arg\_long\_dbl() (see "tr\_blk\_arg\_long\_dbl()" on page 16-64)
- tr\_blk\_arg\_long\_dbl\_() (see "tr\_blk\_arg\_long\_dbl\_()" on page 16-64)
- tr\_blk\_arg\_long\_long() (see "tr\_blk\_arg\_long\_long()" on page 16-65)
- tr\_blk\_arg\_long\_long\_() (see "tr\_blk\_arg\_long\_()" on page 16-61)
- tr\_blk\_arg\_long\_ubits() (see "tr\_blk\_arg\_long\_ubits()" on page 16-67)
- tr\_blk\_arg\_long\_ubits\_() (see "tr\_blk\_arg\_long\_ubits\_()" on page 16-68)
- tr\_blk\_arg\_short() (see "tr\_blk\_arg\_short()" on page 16-69)
- tr\_blk\_arg\_short\_() (see "tr\_blk\_arg\_short\_()" on page 16-69)
- tr\_blk\_arg\_string() (see "tr\_blk\_arg\_string()" on page 16-70)
- tr\_blk\_arg\_string\_() (see "tr\_blk\_arg\_string\_()" on page 16-71)
- tr\_blk\_arg\_ubits() (see "tr\_blk\_arg\_ubits()" on page 16-72)
- tr\_blk\_arg\_ubits\_() (see "tr\_blk\_arg\_ubits\_()" on page 16-73)
- tr\_blk\_arg\_uchar() (see "tr\_blk\_arg\_uchar()" on page 16-74)
- tr\_blk\_arg\_uchar\_() (see "tr\_blk\_arg\_uchar\_()" on page 16-75)
- tr\_blk\_arg\_ushort() (see "tr\_blk\_arg\_ushort()" on page 16-76)
- tr\_blk\_arg\_ushort\_() (see "tr\_blk\_arg\_ushort\_()" on page 16-76)
- tr cancel cb() (see "tr cancel cb()" on page 16-144)
- tr\_close() (see "tr\_close()" on page 16-21)
- tr\_cond\_and() (see "tr\_cond\_and()" on page 16-113)
- tr cond cb() (see "tr cond cb()" on page 16-145)
- tr\_cond\_copy() (see "tr\_cond\_copy()" on page 16-114)
- tr\_cond\_cpu() (see "tr\_cond\_cpu()" on page 16-94)
- tr cond cpu clear() (see "tr cond cpu clear()" on page 16-95)

- tr cond create() (see "tr cond create()" on page 16-89)
- tr\_cond\_expr\_and() (see "tr\_cond\_expr\_and()" on page 16-109)
- tr\_cond\_expr\_or() (see "tr\_cond\_expr\_or()" on page 16-110)
- tr\_cond\_find() (see "tr\_cond\_find()" on page 16-90)
- tr cond func and() (see "tr cond func and()" on page 16-106)
- tr\_cond\_func\_clear() (see "tr\_cond\_func\_clear()" on page 16-108)
- tr cond func or() (see "tr cond func or()" on page 16-104)
- tr\_cond\_id() (see "tr\_cond\_id()" on page 16-91)
- tr\_cond\_id\_clear() (see "tr\_cond\_id\_clear()" on page 16-93)
- tr\_cond\_id\_range() (see "tr\_cond\_id\_range()" on page 16-92)
- tr\_cond\_name() (see "tr\_cond\_name()" on page 16-116)
- tr\_cond\_node() (see "tr\_cond\_node()" on page 16-102)
- tr\_cond\_node\_clear() (see "tr\_cond\_node\_clear()" on page 16-103)
- tr\_cond\_not() (see "tr\_cond\_not()" on page 16-111)
- tr\_cond\_offset() (see "tr\_cond\_offset()" on page 16-119)
- tr\_cond\_or() (see "tr\_cond\_or()" on page 16-112)
- tr\_cond\_pid() (see "tr\_cond\_pid()" on page 16-96)
- tr\_cond\_pid\_clear() (see "tr\_cond\_pid\_clear()" on page 16-98)
- tr\_cond\_pid\_name() (see "tr\_cond\_pid\_name()" on page 16-97)
- tr\_cond\_register() (see "tr\_cond\_register()" on page 16-118)
- tr cond reset() (see "tr cond reset()" on page 16-90)
- tr\_cond\_satisfy() (see "tr\_cond\_satisfy()" on page 16-116)
- tr\_cond\_satisfy\_() (see "tr\_cond\_satisfy\_()" on page 16-117)
- tr cond tid() (see "tr cond tid()" on page 16-99)
- tr\_cond\_tid\_clear() (see "tr\_cond\_tid\_clear()" on page 16-101)
- tr\_cond\_tid\_name() (see "tr\_cond\_tid\_name()" on page 16-100)
- tr\_copy\_input() (see "tr\_copy\_input()" on page 16-136)
- tr\_copy\_input\_range() (see "tr\_copy\_input\_range()" on page 16-137)
- tr\_cpu() (see "tr\_cpu()" on page 16-81)
- tr\_cpu\_() (see "tr\_cpu\_()" on page 16-83)
- tr\_create\_table() (see "tr\_create\_table()" on page 16-140)
- tr\_destroy() (see "tr\_destroy()" on page 16-15)

- tr\_error\_check() (see "tr\_error\_check()" on page 16-18)
- tr\_error\_clear() (see "tr\_error\_clear()" on page 16-17)
- tr\_free() (see "tr\_free()" on page 16-25)
- tr\_get\_item() (see "tr\_get\_item()" on page 16-139)
- tr\_get\_string() (see "tr\_get\_string()" on page 16-138)
- tr\_halt() (see "tr\_halt()" on page 16-144)
- tr id() (see "tr id()" on page 16-32)
- tr\_id\_() (see "tr\_id\_()" on page 16-33)
- tr\_init() (see "tr\_init()" on page 16-15)
- tr\_iterate() (see "tr\_iterate()" on page 16-143)
- tr\_nargs() (see "tr\_nargs()" on page 16-36)
- tr\_nargs\_() (see "tr\_nargs\_()" on page 16-36)
- tr\_next\_event() (see "tr\_next\_event()" on page 16-26)
- tr\_next\_event\_() (see "tr\_next\_event\_()" on page 16-27)
- tr\_node() (see "tr\_node()" on page 16-84)
- tr\_node\_() (see "tr\_node\_()" on page 16-84)
- tr\_open\_file() (see "tr\_open\_file()" on page 16-19)
- tr\_open\_stream() (see "tr\_open\_stream()" on page 16-20)
- tr\_pid() (see "tr\_pid()" on page 16-77)
- tr\_pid\_() (see "tr\_pid\_()" on page 16-78)
- tr\_prev\_event() (see "tr\_prev\_event()" on page 16-27)
- tr\_prev\_event\_() (see "tr\_prev\_event\_()" on page 16-28)
- tr\_process\_name() (see "tr\_process\_name()" on page 16-85)
- tr process name () (see "tr process name ()" on page 16-86)
- tr\_search() (see "tr\_search()" on page 16-29)
- tr\_seek() (see "tr\_seek()" on page 16-30)
- tr\_state\_active() (see "tr\_state\_active()" on page 16-134)
- tr\_state\_active\_() (see "tr\_state\_active\_()" on page 16-135)
- tr\_state\_cb() (see "tr\_state\_cb()" on page 16-146)
- tr\_state\_create() (see "tr\_state\_create()" on page 16-120)
- tr\_state\_end\_cond() (see "tr\_state\_end\_cond()" on page 16-129)
- tr\_state\_end\_cond\_clear() (see "tr\_state\_end\_cond\_clear()" on page 16-130)

- tr\_state\_end\_id() (see "tr\_state\_end\_id()" on page 16-125)
- tr\_state\_end\_id\_clear() (see "tr\_state\_end\_id\_clear()" on page 16-127)
- tr\_state\_end\_id\_range() (see "tr\_state\_end\_id\_range()" on page 16-126)
- tr\_state\_find() (see "tr\_state\_find()" on page 16-121)
- tr\_state\_info() (see "tr\_state\_info()" on page 16-132)
- tr\_state\_info\_() (see "tr\_state\_info\_()" on page 16-133)
- tr\_state\_name() (see "tr\_state\_name()" on page 16-122)
- tr\_state\_start\_cond() (see "tr\_state\_start\_cond()" on page 16-128)
- tr\_state\_start\_cond\_clear() (see "tr\_state\_start\_cond\_clear()" on page 16-129)
- tr\_state\_start\_id() (see "tr\_state\_start\_id()" on page 16-123)
- tr\_state\_start\_id\_clear() (see "tr\_state\_start\_id\_clear()" on page 16-125)
- tr\_state\_start\_id\_range() (see "tr\_state\_start\_id\_range()" on page 16-124)
- tr\_stream\_notify() (see "tr\_stream\_notify()" on page 16-22)
- tr\_stream\_read() (see "tr\_stream\_read()" on page 16-23)
- tr\_stream\_size() (see "tr\_stream\_size()" on page 16-24)
- tr\_thread\_id() (see "tr\_thread\_id()" on page 16-80)
- tr\_thread\_id\_() (see "tr\_thread\_id\_()" on page 16-81)
- tr\_thread\_name() (see "tr\_thread\_name()" on page 16-86)
- tr thread name () (see "tr thread name ()" on page 16-87)
- tr\_tid() (see "tr\_tid()" on page 16-79)
- tr\_tid\_() (see "tr\_tid\_()" on page 16-79)
- tr\_time() (see "tr\_time()" on page 16-34)
- tr\_time\_() (see "tr\_time\_()" on page 16-35)

# **API Initialization and Destruction**

The functions related to API initialization and destruction are:

- tr init() (see page 16-15)
- tr\_destroy() (see page 16-15)

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

# tr\_init()

tr\_init() returns an opaque handle that is required for all subsequent API functions and which identifies the data set.

## **SYNTAX**

```
extern tr_t tr_init (void);
```

### **RETURN VALUES**

Returns an opaque handle that is required for all subsequent API functions and which identifies the data set; in the event there is insufficient memory, TR\_NO\_HANDLE will be returned.

See "API Initialization and Destruction" on page 16-15 for related functions. See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

#### **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_destroy()

tr\_destroy() frees up any remaining memory associated with a handle returned by tr\_init().

## **NOTE**

tr\_destroy() expects a pointer to a handle, whereas all other functions expect the handle itself.

# **SYNTAX**

```
extern void tr_destroy (tr_t * t);
```

# **PARAMETERS**

t

data set handle

See "API Initialization and Destruction" on page 16-15 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_init()" on page 16-15

# **Error Detection, Collection, and Reporting**

Most individual functions within the API return an indiciation of whether the requested operation was successful. Most often, zero indicates success, and non-zero indicates failure. Exceptions to this rule are indiciated for each function.

Errors are collected by the API and can be retreived after calling a series of functions.

The functions related to error detection, collection, and reporting are:

```
tr_error_clear() (see page 16-17)tr error check() (see page 16-18)
```

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

# tr\_error\_clear()

tr\_error\_clear() is used to flush any collected errors and set the internal error state to zero, meaning success.

#### **SYNTAX**

```
extern void tr_error_clear (tr_t t);
```

#### **PARAMETERS**

t

data set handle

See "Error Detection, Collection, and Reporting" on page 16-17 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr error check()" on page 16-18

## tr\_error\_check()

tr\_error\_check() is used to determine the errors that have occurred since the beginning of the program or since the last time the error list was cleared.

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

list

the list of errors that have occurred (since the last call to tr\_error\_clear() or the beginning of the program). For each entry in the *list*, value describes the error and item refers to error (if appropriate). (See "tr\_string\_node\_t" on page 16-8 for more information.)

#### **RETURN VALUES**

Returns zero if no errors have occurred (since the last call to tr\_error\_clear() or the beginning of the program); otherwise, returns the number of errors in the list of errors pointed to by *list*. If the user passes in a NULL value for the address of *list*, *list* is not set.

See "Error Detection, Collection, and Reporting" on page 16-17 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_string\_node\_t" on page 16-8
- "tr\_error\_clear()" on page 16-17

# **Input Specification and Streaming Control**

The functions related to input specification and streaming control are:

```
- tr_open_file() (see page 16-19)
- tr_open_stream() (see page 16-20)
- tr_close() (see page 16-21)
- tr_stream_notify() (see page 16-22)
- tr_stream_read() (see page 16-23)
- tr_stream_size() (see page 16-24)
- tr_free() (see page 16-25)
```

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

## tr\_open\_file()

tr\_open\_file() opens the specified NightTrace data file and initializes the API for operation on the contained data set.

#### **NOTE**

Currently, only one input source is allowed per handle (until it is closed via tr\_close()).

#### **SYNTAX**

## **PARAMETERS**

t

data set handle

filename

the pathname of the NightTrace data file

#### **RETURN VALUES**

Returns zero on success; returns -1 if there is an error opening the data file.

See "Input Specification and Streaming Control" on page 16-19 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

#### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_close()" on page 16-21

#### tr\_open\_stream()

tr\_open\_stream() associates the specified file descriptor with a stream of raw trace data. The stream is normally generated by invoking **ntraceud** or **ntracekd** with the **--stream** option and piping **stdout** to the user application's **stdin**. Alternatively, the NightTrace GUI can launch a user application providing **stdin** as the data stream.

#### **NOTE**

Currently, only one input source is allowed per handle (until it is closed via tr\_close()).

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

fd

file descriptor providing streaming raw data

size

specifies the memory limit (in bytes) associated with events that have been read from the stream file descriptor but have not yet been consumed. This size can be dynamically adjusted via the tr\_stream\_size() function.

flags

may contain the following value:

TR\_STREAM\_SAVE - this instructs the API to retain all streamed events in memory even after they have been consumed. By default, for streaming data, once an event has been consumed by an API call, its memory will be (eventually) released and it cannot be referenced subsequently.

### **RETURN VALUES**

Returns zero on success; returns -1 if there is an error opening the data stream.

See "Input Specification and Streaming Control" on page 16-19 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_stream\_size()" on page 16-24
- "tr\_close()" on page 16-21

## tr\_close()

tr\_close() closes the specified data set and associated data file or stream file descriptor. In the case of a data stream, if the associated daemon is still running, the daemon will terminate with an error.

#### **NOTE**

Currently, only one input source is allowed per handle (until it is closed via tr\_close()).

## **SYNTAX**

```
extern void tr_close (tr_t t);
```

#### **PARAMETERS**

t

data set handle

See "Input Specification and Streaming Control" on page 16-19 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_open\_file()" on page 16-19
- "tr\_open\_stream()" on page 16-20

### tr\_stream\_notify()

tr\_stream\_notify() defines a callback which will occur when a stream event occurs as defined by tr\_stream\_event\_t.

#### **SYNTAX**

### **PARAMETERS**

```
t
    data set handle
event
    can be:
    tr_stream_overflow - This event has been deprecated and no longer occurs.
```

See tr\_stream\_read() for control over stream I/O operations.

 ${\tt tr\_stream\_stall} - A stall occurs when there is an insufficient number of events available to form a segment for consumption.$ 

func

callback function

## **RETURN VALUES**

Returns zero on success; returns -1 if the specified arguments are invalid or there is insufficient memory available to register the callback function.

See "Input Specification and Streaming Control" on page 16-19 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_stream\_event\_t" on page 16-8
- "tr\_stream\_func\_t" on page 16-8
- "tr\_stream\_size()" on page 16-24
- "tr\_stream\_read()" on page 16-23

#### tr\_stream\_read()

tr\_stream\_read() reads events from the input stream until no events are currently available or until the specified maximum is reached. A segmented input approach is utilized so that the actual number of events read may exceed the specified maximum (by the minimum segments size).

This function need not be called at all. The stream of data is read automatically as events are consumed (by tr\_next\_event(), tr\_iterate(), or tr\_copy\_input()).

This function is provided for situations where the rate at which events are generated exceeds that at which they are currently being consumed. If the consumption rate is significantly lower than the generation rate, the daemon writing the data to the stream could otherwise stall (block on the write) and data would be lost when the daemon's buffers fill. Calling tr\_stream\_read() in such situations ensures that data is read and stored internally for use when events are subsequently consumed by tr\_next\_event(), tr\_iterate(), or tr\_copy\_input().

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

max\_events

maximum number of events to be read

### **RETURN VALUES**

Returns the number of events read.

See "Input Specification and Streaming Control" on page 16-19 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr t" on page 16-9
- "tr\_next\_event()" on page 16-26
- "tr\_iterate()" on page 16-143
- "tr\_copy\_input()" on page 16-136

### tr\_stream\_size()

tr\_stream\_size() dynamically changes the memory limit originally specified via tr\_open\_stream(). It controls the amount of memory used to hold events that have been read from the stream file descriptor but have not yet been consumed.

#### **SYNTAX**

## **PARAMETERS**

t

data set handle

size

memory limit associated with streaming events

### **RETURN VALUES**

Returns zero on success; returns -1 if the specified size is invalid.

See "Input Specification and Streaming Control" on page 16-19 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_open\_stream()" on page 16-20

### tr\_free()

tr\_free() releases the memory associated with events whose offsets are less than or equal to the specified offset, if those events have been consumed.

This function has no effect if the events have not been consumed or if events are not being saved (e.g., tr\_open\_stream() called without the TR\_STREAM\_SAVE flag value).

### **SYNTAX**

### **PARAMETERS**

t

data set handle

event offset

specifies that the memory associated with events whose offsets are less than or equal to this value will be released when this function is called

#### **RETURN VALUES**

Returns zero on success; returns -1 if the specified offset is invalid.

See "Input Specification and Streaming Control" on page 16-19 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_open\_stream()" on page 16-20

# **Event Offset Positioning**

The functions related to event offset positioning are:

```
- tr_next_event() (see page 16-26)
- tr_next_event_() (see page 16-27)
- tr_prev_event() (see page 16-27)
- tr_prev_event_() (see page 16-28)
- tr_search() (see page 16-29)
- tr_seek() (see page 16-30)
```

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### tr\_next\_event()

tr\_next\_event() advances the offset to the next consecutive trace event.

#### **SYNTAX**

```
extern tr_offset_t tr_next_event (tr_t t);
```

#### **PARAMETERS**

t

data set handle

#### **RETURN VALUES**

Returns the offset of the trace event or TR\_EOF if the end of the data set has been reached in which case the current position is after the last trace event in the data set.

See "Event Offset Positioning" on page 16-26 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

### tr\_next\_event\_()

tr\_next\_event\_() advances to the next consecutive trace event meeting the specified condition in the data set.

### **SYNTAX**

#### **PARAMETERS**

t

data set handle

condition

handle of the desired condition

### **RETURN VALUES**

Returns the offset of the trace event or TR\_EOF if the end of the data set has been reached in which case the current position is after the last trace event in the data set.

See "Event Offset Positioning" on page 16-26 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_offset\_t" on page 16-5

# tr\_prev\_event()

tr\_prev\_event() advances to the previous trace event.

#### **SYNTAX**

```
extern tr_offset_t tr_prev_event (tr_t t);
```

### **PARAMETERS**

t

data set handle

### **RETURN VALUES**

Returns the offset of the trace event or TR\_EOF if the end of the data set has been reached in which case the current position is before the first event in the data set.

See "Event Offset Positioning" on page 16-26 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

#### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

#### tr\_prev\_event\_()

tr\_prev\_event\_() advances to the next consecutive trace event meeting the specified condition in the data set.

### **SYNTAX**

#### **PARAMETERS**

t

data set handle

condition

handle of the desired condition

## **RETURN VALUES**

Returns the offset of the trace event or TR\_EOF if the end of the data set has been reached in which case the current position is before the first event in the data set.

See "Event Offset Positioning" on page 16-26 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

• "tr\_t" on page 16-9

- "tr\_cond\_t" on page 16-5
- "tr\_offset\_t" on page 16-5

## tr\_search()

tr\_search() searches for the trace event matching the specified condition in the direction specified. The current position remains unchanged.

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

direction

direction in which to search

condition

handle of the desired condition

### **RETURN VALUES**

Returns the position of the matching trace event; if no matching event is found, TR\_EOF is returned.

See "Event Offset Positioning" on page 16-26 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_dir\_t" on page 16-5
- "tr\_cond\_t" on page 16-5
- "tr\_offset\_t" on page 16-5

## tr\_seek()

tr\_seek() sets the position to the specified offset. If the offset specifies a position that exceeds the offset of the last trace event, the position is set to the last event in the data set.

### **SYNTAX**

### **PARAMETERS**

t data set handle offset of the trace event

## **RETURN VALUES**

The offset of the trace event at the resultant position is returned.

See "Event Offset Positioning" on page 16-26 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## **Basic Event Attribute Functions**

The functions that deal with the basic attributes of trace events are:

- tr\_id() (see page 16-32)
- tr\_id\_() (see page 16-33)
- tr\_time() (see page 16-34)
- tr\_time\_() (see page 16-35)
- tr\_nargs() (see page 16-36)
- tr\_nargs\_() (see page 16-36)
- tr\_arg\_int() (see page 16-37)
- tr\_arg\_int\_() (see page 16-38)
- tr\_arg\_dbl() (see page 16-39)
- tr\_arg\_dbl\_() (see page 16-39)
- tr\_blk\_arg() (see page 16-52)
- tr\_blk\_arg\_() (see page 16-53)
- tr\_blk\_arg\_bits() (see page 16-54)
- tr\_blk\_arg\_bits\_() (see page 16-55)
- tr\_blk\_arg\_char() (see page 16-56)
- tr\_blk\_arg\_char\_() (see page 16-56)
- tr\_blk\_arg\_dbl() (see page 16-57)
- tr\_blk\_arg\_dbl\_() (see page 16-58)
- tr\_blk\_arg\_flt() (see page 16-59)
- tr\_blk\_arg\_flt\_() (see page 16-59)
- tr\_blk\_arg\_long() (see page 16-60)
- tr\_blk\_arg\_long\_() (see page 16-61)
- tr\_blk\_arg\_long\_bits() (see page 16-62)
- tr\_blk\_arg\_long\_bits\_() (see page 16-63)
- tr\_blk\_arg\_long\_dbl() (see page 16-64)
- tr\_blk\_arg\_long\_dbl\_() (see page 16-64)
- tr\_blk\_arg\_long\_ubits() (see page 16-67)
- tr\_blk\_arg\_long\_ubits\_() (see page 16-68)
- tr\_blk\_arg\_short() (see page 16-69)
- tr\_blk\_arg\_short\_() (see page 16-69)

```
- tr_blk_arg_string() (see page 16-70)
- tr_blk_arg_string_() (see page 16-71)
- tr_blk_arg_ubits() (see page 16-72)
- tr_blk_arg_ubits_() (see page 16-73)
- tr_blk_arg_uchar() (see page 16-74)
- tr_blk_arg_uchar_() (see page 16-75)
- tr_blk_arg_ushort() (see page 16-76)
- tr_blk_arg_ushort_() (see page 16-76)
- tr_pid() (see page 16-77)
- tr_pid_() (see page 16-78)
- tr_tid() (see page 16-79)
- tr_tid_() (see page 16-79)
- tr_thread_id() (see page 16-80)
- tr_thread_id_() (see page 16-81)
- tr_cpu() (see page 16-81)
- tr_cpu_() (see page 16-83)
- tr_node() (see page 16-84)
- tr_node_() (see page 16-84)
- tr process name() (see page 16-85)
- tr_process_name_() (see page 16-86)
- tr_thread_name() (see page 16-86)
- tr_thread_name_() (see page 16-87)
```

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### tr\_id()

tr\_id() returns the trace ID associated with the current trace event.

### **SYNTAX**

```
extern int tr_id (tr_t t);
```

#### **PARAMETERS**

t

data set handle

### **RETURN VALUES**

Returns the trace ID associated with the current trace event.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

• "tr\_t" on page 16-9

### tr\_id\_()

tr\_id\_() returns the trace ID associated with the trace event at the specified offset.

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

offset

offset of the trace event

## **RETURN VALUES**

Returns the trace ID associated with the trace event at the specified offset; returns zero if an invalid offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

# tr\_time()

tr\_time() returns the timestamp (in seconds) of the current trace event.

## **NOTE**

A timestamp is relative to the beginning of the trace logging daemon.

### **SYNTAX**

```
extern double tr_time (tr_t t);
```

### **PARAMETERS**

t

data set handle

## **RETURN VALUES**

Returns the timestamp (in seconds) of the current trace event.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_time\_()

tr\_time\_() returns the timestamp (in seconds) of the trace event at the specified offset.

### NOTE

A timestamp is relative to the beginning of the trace logging daemon.

### **SYNTAX**

### **PARAMETERS**

t data set handle offset

offset of the trace event

## **RETURN VALUES**

Returns the timestamp (in seconds) of the trace event at the specified offset; returns zero if an invalid offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

### tr\_nargs()

tr\_nargs() returns the number of arguments associated with the current trace event.

#### **SYNTAX**

```
extern int tr_nargs (tr_t t);
```

#### **PARAMETERS**

t

data set handle

### **RETURN VALUES**

Returns the number of arguments associated with the current trace event. In the case of a trace event recorded with trace\_event\_string() or trace\_event\_blk(), it returns the number of four-byte integers that would be required to hold the data.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_nargs\_()

 $tr_nargs_()$  returns the number of arguments associated with the trace event at the specified offset.

## **SYNTAX**

#### **PARAMETERS**

```
t
data set handle

offset

offset of the trace event
```

### **RETURN VALUES**

Returns the number of arguments associated with the trace event at the specified offset; returns zero if an invalid offset is specified. In the case of a trace event recorded with trace\_event\_string() or trace\_event\_blk(), it returns the number of four-byte integers that would be required to hold the data.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

#### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## tr\_arg\_int()

tr\_arg\_int() returns the desired integer argument of the current trace event.

#### **SYNTAX**

## **PARAMETERS**

t

data set handle

arg\_number

number of the desired argument

### **RETURN VALUES**

Returns the desired integer argument of the current trace event; returns zero if an invalid offset is specified or an invalid argument number is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

## **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_arg\_int\_()

tr\_arg\_int\_() returns the desired integer argument of the trace event at the specified offset.

### **SYNTAX**

## **PARAMETERS**

```
data set handle

arg_number

number of the desired argument

offset

offset of the trace event
```

#### **RETURN VALUES**

Returns the desired integer argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument number is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## tr\_arg\_dbl()

tr\_arg\_dbl() returns the desired double argument of the current trace event.

### **SYNTAX**

#### **PARAMETERS**

t

data set handle

arg\_number

number of the desired argument

#### **RETURN VALUES**

Returns the desired double argument of the current trace event; returns zero if an invalid offset is specified or an invalid argument number is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

## **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_arg\_dbl\_()

tr\_arg\_dbl\_() returns the desired double argument of the trace event at the specified offset.

## **SYNTAX**

### **PARAMETERS**

t

data set handle

```
arg_number
number of the desired argument

offset

offset of the trace event
```

## **RETURN VALUES**

Returns the desired double argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument number is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

### tr\_arg\_long()

tr\_arg\_long() returns the desired long integer argument of the current trace event.

# **SYNTAX**

## **PARAMETERS**

```
t data set handle arg\_number number of the desired argument
```

### **RETURN VALUES**

Returns the desired long integer argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument number is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

#### **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_arg\_long\_()

tr\_arg\_long\_() returns the desired long integer argument of the trace event at the specified offset.

#### **SYNTAX**

#### **PARAMETERS**

```
data set handle

arg_number

number of the desired argument

offset

offset of the trace event
```

### **RETURN VALUES**

Returns the desired long integer argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument number is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## tr\_arg\_long\_dbl()

tr\_arg\_long\_dbl() returns the desired double argument of the current trace event.

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

arg\_number

number of the desired argument

### **RETURN VALUES**

Returns the desired long double argument of the current trace event; returns zero if an invalid offset is specified or an invalid argument number is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

## **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_arg\_long\_dbl\_()

tr\_arg\_dbl\_() returns the desired long double argument of the trace event at the specified offset.

## **SYNTAX**

### **PARAMETERS**

t

data set handle

```
arg_number
```

number of the desired argument

offset

offset of the trace event

## **RETURN VALUES**

Returns the desired long double argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument number is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## tr\_arg\_long\_long()

 $tr\_arg\_long\_long()$  returns the desired long long integer argument of the current trace event.

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

arg\_number

number of the desired argument

## **RETURN VALUES**

Returns the desired long long integer argument of the current trace event; returns zero if an invalid offset is specified or an invalid argument number is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

• "tr\_t" on page 16-9

### tr\_arg\_long\_long\_()

 $tr\_arg\_long\_long\_($  ) returns the desired double argument of the trace event at the specified offset.

#### **SYNTAX**

#### **PARAMETERS**

```
data set handle

arg_number

number of the desired argument

offset

offset of the trace event
```

### **RETURN VALUES**

Returns the desired double argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument number is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## tr\_arg\_int\_()

tr\_arg\_int\_() returns the desired integer argument of the trace event at the specified offset.

### **SYNTAX**

## **PARAMETERS**

```
t
    data set handle
arg_number
    number of the desired argument

offset
    offset of the trace event
```

### **RETURN VALUES**

Returns the desired integer argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument number is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

# tr\_arg\_dbl()

tr\_arg\_dbl() returns the desired double argument of the current trace event.

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

arg\_number

number of the desired argument

#### **RETURN VALUES**

Returns the desired double argument of the current trace event; returns zero if an invalid offset is specified or an invalid argument number is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

## **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_arg\_dbl\_()

tr\_arg\_dbl\_() returns the desired double argument of the trace event at the specified offset.

## **SYNTAX**

## **PARAMETERS**

t

data set handle

arg\_number

number of the desired argument

offset

offset of the trace event

## **RETURN VALUES**

Returns the desired double argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument number is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

#### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## tr\_arg\_long()

tr\_arg\_long() returns the desired long integer argument of the current trace event.

#### **SYNTAX**

## **PARAMETERS**

t

data set handle

arg\_number

number of the desired argument

### **RETURN VALUES**

Returns the desired long integer argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument number is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

#### **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_arg\_long\_()

tr\_arg\_long\_() returns the desired long integer argument of the trace event at the specified offset.

#### **SYNTAX**

#### **PARAMETERS**

```
data set handle

arg_number

number of the desired argument

offset

offset of the trace event
```

### **RETURN VALUES**

Returns the desired long integer argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument number is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## tr\_arg\_long\_dbl()

tr\_arg\_long\_dbl() returns the desired double argument of the current trace event.

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

arg\_number

number of the desired argument

#### **RETURN VALUES**

Returns the desired long double argument of the current trace event; returns zero if an invalid offset is specified or an invalid argument number is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

## **SEE ALSO**

• "tr\_t" on page 16-9

### tr\_arg\_long\_dbl\_()

tr\_arg\_dbl\_() returns the desired long double argument of the trace event at the specified offset.

## **SYNTAX**

### **PARAMETERS**

t

data set handle

arg\_number

number of the desired argument

offset

offset of the trace event

## **RETURN VALUES**

Returns the desired long double argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument number is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

## **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## tr\_arg\_long\_long()

tr\_arg\_long\_long() returns the desired long long integer argument of the current trace event.

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

arg\_number

number of the desired argument

## **RETURN VALUES**

Returns the desired long long integer argument of the current trace event; returns zero if an invalid offset is specified or an invalid argument number is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_argtype()

tr\_argtype() returns the type of arguments associated with the current event.

### **SYNTAX**

```
extern tr_arg_t tr_argtype (tr_t t);
```

### **PARAMETERS**

t

data set handle

## **RETURN VALUES**

Returns the type of arguments associated with the current event. For events recorded with trace\_event\_blk(), this function returns int\_arg.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_arg\_t" on page 16-3

## tr\_argtype\_()

tr\_argtype\_() returns the type of arguments associated with the event at the specified offset.

#### **SYNTAX**

```
extern tr_arg_t tr_argtype_ (tr_t t, tr_offset_t offset);
```

#### **PARAMETERS**

t

data set handle

offset

offset of the trace event

### **RETURN VALUES**

Returns the type of arguments associated with the current (or optionally specified) event. For events recorded with trace\_event\_blk(), this function returns int\_arg.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

#### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## tr\_blk\_arg()

tr\_blk\_arg() returns the integer argument at a particular byte offset in argument space of the current trace event.

### **SYNTAX**

#### **PARAMETERS**

1

data set handle

byte\_offset

byte offset of the desired argument

### **RETURN VALUES**

Returns the desired integer argument of the current trace event; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

#### **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_blk\_arg\_()

tr\_blk\_arg\_() returns the integer argument at a particular byte offset in argument space of the trace event at the specified offset.

#### **SYNTAX**

### **PARAMETERS**

t

data set handle

byte\_offset

byte offset of the desired argument

offset

offset of the trace event

#### **RETURN VALUES**

Returns the desired integer argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

#### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

#### tr\_blk\_arg\_bits()

**tr\_**blk\_arg\_bits() returns the integer bit field argument of a particular bit size at a particular byte and bit offset offset in argument space of the current trace event.

### **SYNTAX**

#### **PARAMETERS**

t

data set handle

byte\_offset

byte offset of the desired argument

bit\_offset

bit offset of the desired argument

bit\_size

bit size of the desired argument

### **RETURN VALUES**

Returns the desired integer bit field argument of the current trace event; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

## **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_blk\_arg\_bits\_()

tr\_blk\_arg\_bits\_() returns the integer bit field argument of a particular bit size at a particular byte and bit offset offset in argument space of the trace event at the specified offset.

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

byte\_offset

byte offset of the desired argument

bit\_offset

bit offset of the desired argument

bit\_size

bit size of the desired argument

offset

offset of the trace event

## **RETURN VALUES**

Returns the desired integer bit field argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## tr\_blk\_arg\_char()

tr\_blk\_arg\_char() returns the character argument at a particular byte offset in argument space of the current trace event.

### **SYNTAX**

### **PARAMETERS**

t

data set handle

byte\_offset

byte offset of the desired argument

## **RETURN VALUES**

Returns the desired character argument of the current trace event; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

# **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_blk\_arg\_char\_()

tr\_blk\_arg\_char\_() returns the character argument at a particular byte offset in argument space of the trace event at the specified offset.

### **SYNTAX**

# **PARAMETERS**

t

data set handle

```
byte_offset
```

byte offset of the desired argument

offset

offset of the trace event

## **RETURN VALUES**

Returns the desired character argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## tr\_blk\_arg\_dbl()

tr\_blk\_arg\_dbl() returns the double argument at a particular byte offset in argument space of the current trace event.

## **SYNTAX**

### **PARAMETERS**

t

data set handle

byte\_offset

byte offset of the desired argument

## **RETURN VALUES**

Returns the desired double argument of the current trace event; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_blk\_arg\_dbl\_()

tr\_blk\_arg\_dbl\_() returns the double argument at a particular byte offset in argument space of the trace event at the specified offset.

### **SYNTAX**

### **PARAMETERS**

```
t
    data set handle
byte_offset
    byte offset of the desired argument
offset
    offset of the trace event
```

## **RETURN VALUES**

Returns the desired double argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

### tr\_blk\_arg\_flt()

tr\_blk\_arg\_flt() returns the float argument at a particular byte offset in argument space of the current trace event.

### **SYNTAX**

### **PARAMETERS**

t

data set handle

byte\_offset

byte offset of the desired argument

## **RETURN VALUES**

Returns the desired float argument of the current trace event; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_blk\_arg\_flt\_()

tr\_blk\_arg\_flt\_() returns the float argument at a particular byte offset in argument space of the trace event at the specified offset.

### **SYNTAX**

### **PARAMETERS**

t

data set handle

```
byte_offset
```

byte offset of the desired argument

offset

offset of the trace event

## **RETURN VALUES**

Returns the desired float argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

## **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## tr\_blk\_arg\_long()

tr\_blk\_arg\_long() returns the long integer argument at a particular byte offset in argument space of the current trace event.

#### **SYNTAX**

## **PARAMETERS**

t

data set handle

byte\_offset

byte offset of the desired argument

### **RETURN VALUES**

Returns the desired long integer argument of the current trace event; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_blk\_arg\_long\_()

tr\_blk\_arg\_long\_() returns the long integer argument at a particular byte offset in argument space of the trace event at the specified offset.

#### **SYNTAX**

### **PARAMETERS**

```
t

data set handle

byte_offset

byte offset of the desired argument

offset

offset of the trace event
```

## **RETURN VALUES**

Returns the desired long integer argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## tr\_blk\_arg\_long\_bits()

tr\_blk\_arg\_long\_bits() returns the long integer bit field argument of a particular bit size at a particular byte and bit offset offset in argument space of the current trace event.

### **SYNTAX**

### **PARAMETERS**

t

data set handle

byte\_offset

byte offset of the desired argument

bit\_offset

bit offset of the desired argument

bit\_size

bit size of the desired argument

## **RETURN VALUES**

Returns the desired long integer bit field argument of the current trace event; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

# **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_blk\_arg\_long\_bits\_()

tr\_blk\_arg\_long\_bits\_() returns the long integer bit field argument of a particular bit size at a particular byte and bit offset offset in argument space of the trace event at the specified offset.

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

byte\_offset

byte offset of the desired argument

bit\_offset

bit offset of the desired argument

bit\_size

bit size of the desired argument

offset

offset of the trace event

## **RETURN VALUES**

Returns the desired long integer bit field argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

### tr\_blk\_arg\_long\_dbl()

tr\_blk\_arg\_long\_dbl() returns the long double argument at a particular byte offset in argument space of the current trace event.

### **SYNTAX**

### **PARAMETERS**

t

data set handle

byte\_offset

byte offset of the desired argument

## **RETURN VALUES**

Returns the desired long double argument of the current trace event; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

# **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_blk\_arg\_long\_dbl\_()

tr\_blk\_arg\_long\_dbl\_() returns the long double argument at a particular byte offset in argument space of the trace event at the specified offset.

### **SYNTAX**

# **PARAMETERS**

t

data set handle

```
byte_offset
```

byte offset of the desired argument

offset

offset of the trace event

## **RETURN VALUES**

Returns the desired long double argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## tr\_blk\_arg\_long\_long()

 ${\tt tr\_blk\_arg\_long\_long()} \ returns \ the \ long \ long \ integer \ argument \ at \ a \ particular \ byte \ offset \ in \ argument \ space \ of \ the \ current \ trace \ event.$ 

## **SYNTAX**

### **PARAMETERS**

t

data set handle

byte\_offset

byte offset of the desired argument

## **RETURN VALUES**

Returns the desired long long argument of the current trace event; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_blk\_arg\_long\_long\_()

tr\_blk\_arg\_long\_long\_() returns the long long integer argument at a particular byte offset in argument space of the trace event at the specified offset.

### **SYNTAX**

### **PARAMETERS**

data set handle

byte offset of the desired argument

offset

byte\_offset

offset of the trace event

## **RETURN VALUES**

Returns the desired long long integer argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## tr\_blk\_arg\_long\_ubits()

tr\_blk\_arg\_long\_ubits() returns the unsigned long integer bit field argument of a particular bit size at a particular byte and bit offset offset in argument space of the current trace event.

#### **SYNTAX**

### **PARAMETERS**

t

data set handle

byte\_offset

byte offset of the desired argument

bit\_offset

bit offset of the desired argument

bit\_size

bit size of the desired argument

## **RETURN VALUES**

Returns the desired unsigned long integer bit field argument of the current trace event; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

## **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_blk\_arg\_long\_ubits\_()

tr\_blk\_arg\_long\_ubits\_() returns the unsigned long integer bit field argument of a particular bit size at a particular byte and bit offset offset in argument space of the trace event at the specified offset.

### **SYNTAX**

#### **PARAMETERS**

```
data set handle byte_offset
```

byte offset of the desired argument

bit\_offset

bit offset of the desired argument

bit\_size

bit size of the desired argument

offset

offset of the trace event

# **RETURN VALUES**

Returns the desired unsigned long integer bit field argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

### tr\_blk\_arg\_short()

tr\_blk\_arg\_short() returns the short integer argument at a particular byte offset in argument space of the current trace event.

### **SYNTAX**

### **PARAMETERS**

t

data set handle

byte\_offset

byte offset of the desired argument

### **RETURN VALUES**

Returns the desired short integer argument of the current trace event; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_blk\_arg\_short\_()

tr\_blk\_arg\_short\_() returns the short integer argument at a particular byte offset in argument space of the trace event at the specified offset.

### **SYNTAX**

### **PARAMETERS**

t

data set handle

```
byte_offset

byte offset of the desired argument

offset
```

offset of the trace event

## **RETURN VALUES**

Returns the desired short integer argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## tr\_blk\_arg\_string()

tr\_blk\_arg\_string() returns a pointer to the null terminated string argument at a particular byte offset in argument space of the current trace event and limited to a particular string size.

### **SYNTAX**

#### **PARAMETERS**

```
t
    data set handle
byte_offset
    byte offset of the desired argument
string_size
    the maximum length of the string
```

## **RETURN VALUES**

Returns the desired string argument of the current trace event; returns NULL if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_blk\_arg\_string\_()

tr\_blk\_arg\_string\_() returns a pointer to the null terminated string argument at a particular byte offset in argument space of the trace event at the specified offset and limited to a particular string size.

### **SYNTAX**

### **PARAMETERS**

```
data set handle

byte_offset

byte offset of the desired argument

string_size

the maximum length of the string

offset
```

offset of the trace event

### **RETURN VALUES**

Returns the desired string argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

# tr\_blk\_arg\_ubits()

tr\_blk\_arg\_ubits() returns the unsigned integer bit field argument of a particular bit size at a particular byte and bit offset offset in argument space of the current trace event.

### **SYNTAX**

### **PARAMETERS**

t

data set handle

byte\_offset

byte offset of the desired argument

bit\_offset

bit offset of the desired argument

bit\_size

bit size of the desired argument

### **RETURN VALUES**

Returns the desired unsigned integer bit field argument of the current trace event; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

## **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_blk\_arg\_ubits\_()

tr\_blk\_arg\_ubits\_() returns the unsigned integer bit field argument of a particular bit size at a particular byte and bit offset offset in argument space of the trace event at the specified offset.

### **SYNTAX**

## **PARAMETERS**

```
t
data set handle

byte_offset
byte offset of the desired argument
```

bit\_offset
bit offset of the desired argument

bit\_size

bit size of the desired argument

offset

offset of the trace event

### **RETURN VALUES**

Returns the desired unsigned integer bit field argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

## **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## tr\_blk\_arg\_uchar()

tr\_blk\_arg\_uchar() returns the unsigned character argument at a particular byte offset in argument space of the current trace event.

### **SYNTAX**

### **PARAMETERS**

t

data set handle

byte\_offset

byte offset of the desired argument

### **RETURN VALUES**

Returns the desired unsigned character argument of the current trace event; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

## **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_blk\_arg\_uchar\_()

tr\_blk\_arg\_uchar\_() returns the unsigned character argument at a particular byte offset in argument space of the trace event at the specified offset.

## **SYNTAX**

## **PARAMETERS**

```
t
    data set handle
byte_offset
    byte offset of the desired argument
offset
    offset of the trace event
```

### **RETURN VALUES**

Returns the desired unsigned character argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## tr\_blk\_arg\_ushort()

tr\_blk\_arg\_ushort() returns the unsigned short integer argument at a particular byte offset in argument space of the current trace event.

### **SYNTAX**

### **PARAMETERS**

t

data set handle

byte\_offset

byte offset of the desired argument

### **RETURN VALUES**

Returns the desired unsigned short integer argument of the current trace event; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_blk\_arg\_ushort\_()

 $tr\_blk\_arg\_ushort\_()$  returns the unsigned short integer argument at a particular byte offset in argument space of the trace event at the specified offset.

#### **SYNTAX**

# **PARAMETERS**

t

data set handle

byte\_offset

byte offset of the desired argument

offset

offset of the trace event

## **RETURN VALUES**

Returns the desired unsigned short integer argument of the trace event at the specified offset; returns zero if an invalid offset is specified or an invalid argument byte offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## tr\_pid()

tr\_pid() returns the process identifier (PID) associated with the current trace event.

### **SYNTAX**

```
extern int tr_pid (tr_t t);
```

# **PARAMETERS**

t

data set handle

## **RETURN VALUES**

Returns the process ID of the current trace event.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

## **SEE ALSO**

• "tr\_t" on page 16-9

# tr\_pid\_()

tr\_pid\_() returns the process identifier (PID) associated with the trace event at the specified offset.

## **SYNTAX**

## **PARAMETERS**

data set handle

offset

offset of the trace event

## **RETURN VALUES**

Returns the process identifier (*PID*) associated with the trace event at the specified offset; returns zero if an invalid offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## tr\_tid()

tr\_tid() returns the internally-assigned NightTrace thread identifier (TID) associated with the current trace event.

### **SYNTAX**

```
extern int tr_tid (tr_t t);
```

### **PARAMETERS**

t

data set handle

## **RETURN VALUES**

Returns the internally-assigned NightTrace thread identifier (*TID*) associated with the current trace event.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

## **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_tid\_()

 $tr\_tid\_()$  returns the internally-assigned NightTrace thread identifier (TID) associated with the trace event at the specified offset.

### **SYNTAX**

# **PARAMETERS**

t

data set handle

offset

offset of the trace event

## **RETURN VALUES**

Returns the internally-assigned NightTrace thread identifier (*TID*) associated with the trace event at the specified offset; returns zero if an invalid offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## tr\_thread\_id()

 $tr\_thread\_id()$  returns and NightTrace internal thread identifier associated with the current trace event.

## **SYNTAX**

```
extern int tr_thread_id (tr_t t);
```

## **PARAMETERS**

t

data set handle

# **RETURN VALUES**

Returns the thread identifier associated with the current trace event.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_thread\_id\_()

tr\_thread\_id\_() returns the NightTrace internal *thread* identifier associated with the trace event at the specified offset.

### **SYNTAX**

### **PARAMETERS**

t data set handle

offset of the trace event

## **RETURN VALUES**

Returns the thread identifier associated with the trace event at the specified offset; returns zero if an invalid offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

## **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## tr\_cpu()

tr\_cpu() returns the CPU where the current trace event was logged. CPUs are logically numbered starting at 0 and monotonically increase thereafter.

## **NOTE**

The CPU is only recorded for trace events logged by the operating system kernel. Kernel tracing is not supported on all operating system distributions. See "Kernel Dependencies" on page B-1 for more information.

## **SYNTAX**

```
extern int tr_cpu (tr_t t);
```

### **PARAMETERS**

t

data set handle

## **RETURN VALUES**

Returns the CPU where the current trace event was logged. For trace events not logged by the operating system kernel, a value of -1 is returned (which indicates any CPU).

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

## **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_cpu\_()

tr\_cpu\_() returns the CPU where the current trace event was logged. CPUs are logically numbered starting at 0 and monotonically increase thereafter.

### **NOTE**

The CPU is only recorded for trace events logged by the operating system kernel. Kernel tracing is not supported on all operating system distributions. See "Kernel Dependencies" on page B-1 for more information.

#### **SYNTAX**

### **PARAMETERS**

t

data set handle

offset

offset of the trace event

## **RETURN VALUES**

Returns the CPU where the current trace event was logged. For trace events not logged by the operating system kernel, a value of -1 is returned (which indicates any CPU). If an invalid offset is specified, a value of -1 is returned.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## tr\_node()

tr\_node() returns the name of the system where the current trace event was logged.

### **SYNTAX**

```
extern char * tr_node (tr_t t);
```

### **PARAMETERS**

data set handle

## **RETURN VALUES**

Returns the name of the system where the current trace event was logged.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

• "tr\_t" on page 16-9

# tr\_node\_()

 $tr\_node\_($  ) returns the name of the system where the trace event at the specified offset was logged.

#### **SYNTAX**

```
extern char * tr_node_ (tr_t t, tr_offset_t offset);
```

### **PARAMETERS**

t

data set handle

offset

offset of the trace event

## **RETURN VALUES**

Returns the name of the system where the trace event at the specified offset was logged; returns NULL if an invalid offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## tr\_process\_name()

 $\label{tr_process_name} \verb|(|)| returns the name of the process associated with the current trace event.$ 

## **SYNTAX**

```
extern char * tr_process_name (tr_t t);
```

## **PARAMETERS**

t

data set handle

# **RETURN VALUES**

Returns the name of the process associated with the current trace event.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

## **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_process\_name\_()

tr\_process\_name\_() returns the name of the process associated with the trace event at the specified offset.

### **SYNTAX**

### **PARAMETERS**

t data set handle offset

offset of the trace event

## **RETURN VALUES**

Returns the name of the process associated with the trace event at the specified offset; returns zero if an invalid offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

## **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

# tr\_thread\_name()

tr\_thread\_name() returns the thread name associated with the current trace event.

## **SYNTAX**

```
extern char * tr_thread_name (tr_t t);
```

# **PARAMETERS**

t

data set handle

## **RETURN VALUES**

Returns the thread name associated with the current trace event.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

## **SEE ALSO**

• "tr\_t" on page 16-9

## tr\_thread\_name\_()

tr\_thread\_name\_() returns the thread name associated with the trace event at the specified offset.

## **SYNTAX**

## **PARAMETERS**

t

data set handle

offset

offset of the trace event

### **RETURN VALUES**

Returns the thread name associated with the trace event at the specified offset; returns zero if an invalid offset is specified.

See "Basic Event Attribute Functions" on page 16-31 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_offset\_t" on page 16-5

## **Conditions**

The functions that deal with the creation and manipulation of conditions and their requirements are:

- tr\_cond\_create() (see page 16-89)
- tr\_cond\_reset() (see page 16-90)
- tr\_cond\_find() (see page 16-90)
- tr\_cond\_id() (see page 16-91)
- tr\_cond\_id\_range() (see page 16-92)
- tr\_cond\_id\_clear() (see page 16-93)
- tr\_cond\_cpu() (see page 16-94)
- tr\_cond\_cpu\_clear() (see page 16-95)
- tr\_cond\_pid() (see page 16-96)
- tr\_cond\_pid\_name() (see page 16-97)
- tr\_cond\_pid\_clear() (see page 16-98)
- tr\_cond\_tid() (see page 16-99)
- tr\_cond\_tid\_name() (see page 16-100)
- tr\_cond\_tid\_clear() (see page 16-101)
- tr\_cond\_node() (see page 16-102)
- tr\_cond\_node\_clear() (see page 16-103)
- tr\_cond\_func\_or() (see page 16-104)
- tr\_cond\_func\_and() (see page 16-106)
- tr\_cond\_func\_clear() (see page 16-108)
- tr\_cond\_expr\_and() (see page 16-109)
- tr\_cond\_expr\_or() (see page 16-110)
- tr\_cond\_not() (see page 16-111)
- tr\_cond\_or() (see page 16-112)
- tr\_cond\_and() (see page 16-113)
- tr\_cond\_copy() (see page 16-114)
- tr\_cond\_name() (see page 16-116)
- tr\_cond\_satisfy() (see page 16-116)
- tr\_cond\_satisfy\_() (see page 16-117)
- tr\_cond\_register() (see page 16-118)
- tr\_cond\_offset() (see page 16-119)

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

## tr\_cond\_create()

tr\_cond\_create() creates a new condition which will (initially) match all events.

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

name

name to subsequently reference newly-created condition; if the name is non-null, the condition may be retrieved via tr\_cond\_find() subsequently; if a condition with the same name already exists, the existing condition will become unnamed but will not be otherwise modified.

### **RETURN VALUES**

Returns an opaque handle which identifies the condition; in the event there is insufficient memory to create the condition, TR\_NO\_COND will be returned.

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_cond\_find()" on page 16-90

## tr\_cond\_reset()

tr\_cond\_reset() resets the condition to match all events; all previous modifications to the specified condition are discarded.

### **SYNTAX**

### **PARAMETERS**

t data set handle cond

handle of condition to reset

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_cond\_create()" on page 16-89

## tr\_cond\_find()

tr\_cond\_find() locates an existing condition (perhaps imported from a file) and returns its handle.

### **SYNTAX**

### **PARAMETERS**

t data set handle

name used to reference the desired condition as defined in tr\_cond\_create()

### **RETURN VALUES**

Returns the handle of the desired condition; returns TR\_NO\_COND if the named condition does not exist.

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

#### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_cond\_create()" on page 16-89

### tr\_cond\_id()

tr\_cond\_id() appends the specified trace ID to the list of required trace IDs that must be matched for a particular condition to evaluate to TRUE.

### **NOTE**

Before the first tr\_cond\_id() or tr\_cond\_id\_range() call, or after calling tr\_cond\_id\_clear(), the trace ID requirement is empty which matches any ID.

# **SYNTAX**

#### **PARAMETERS**

t

data set handle

cond

handle of the condition with which the given trace ID is to be associated

id

trace ID to add to those that must be matched for the given condition to evaluate to  $\ensuremath{\mathtt{TRUE}}$ 

### **RETURN VALUES**

Returns zero on success or non-zero if insufficient memory is available to register the ID.

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

#### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_cond\_create()" on page 16-89
- "tr\_cond\_id\_range()" on page 16-92
- "tr\_cond\_id\_clear()" on page 16-93

## tr\_cond\_id\_range()

tr\_cond\_id\_range() appends the trace IDs included in the given trace ID range to the list of required trace IDs that must be matched for the given condition to evaluate to TRUE.

#### **NOTE**

Before the first tr\_cond\_id() or tr\_cond\_id\_range() call, or after calling tr\_cond\_id\_clear(), the trace ID requirement is empty which matches any ID.

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

cond

handle of the condition with which the given trace ID range is to be associated

id1

minimum value in the range of trace IDs to be associated with the given condition

id2

maximum value in the range of trace IDs to be associated with the given condition

### **RETURN VALUES**

Returns zero on success or non-zero if insufficient memory is available to register the IDs.

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_cond\_id()" on page 16-91
- "tr\_cond\_id\_clear()" on page 16-93

### tr\_cond\_id\_clear()

tr\_cond\_id\_clear() removes all trace ID requirements from a particular condition.

#### **NOTE**

Before the first tr\_cond\_id() or tr\_cond\_id\_range() call, or after calling tr\_cond\_id\_clear(), the trace ID requirement is empty which matches any ID.

# **SYNTAX**

#### **PARAMETERS**

t

data set handle

cond

handle of the condition from which all trace ID requirements will be removed

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

# **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_cond\_id()" on page 16-91
- "tr\_cond\_id\_range()" on page 16-92

### tr\_cond\_cpu()

tr\_cond\_cpu() sets the CPU requirement to any of the CPUs defined in the specified CPU bias.

#### **SYNTAX**

### **PARAMETERS**

t

data set handle

cond

handle of the condition with which to associate the given CPU bias

cpu bias

CPU bias to apply to the given condition

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_cond\_cpu\_clear()" on page 16-95

## tr\_cond\_cpu\_clear()

tr\_cond\_cpu\_clear() clears the CPU requirement for the given condition.

#### **NOTE**

This function is equivalent to calling tr\_cond\_cpu() with -1 as the CPU bias.

# **SYNTAX**

### **PARAMETERS**

t

data set handle

cond

handle of the condition

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_cond\_cpu()" on page 16-94

### tr\_cond\_pid()

tr\_cond\_pid() appends the specified process ID to the list of required processes that must be matched for the given condition to evaluate to TRUE.

#### **NOTE**

```
Before the first tr_cond_pid() call or tr_cond_pid_name(), or after calling tr_cond_pid_clear(), the process requirement is empty which matches any process.
```

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

cond

handle of the condition

pid

process ID to be added to the list of processes associated with the given condition

# **RETURN VALUES**

Returns zero on success or non-zero if insufficient memory is available to register the specified process ID.

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_cond\_pid\_name()" on page 16-97
- "tr\_cond\_pid\_clear()" on page 16-98

### tr\_cond\_pid\_name()

tr\_cond\_pid\_name() appends the process with the specified name to the list of required processes that must be matched for the given condition to evaluate to TRUE.

#### **NOTE**

Before the first tr\_cond\_pid() call or tr\_cond\_pid\_name(), or after calling tr\_cond\_pid\_clear(), the process requirement is empty which matches any process.

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

cond

handle of the condition

process\_name

name of the process to be added to the list of processes associated with the given condition

## **RETURN VALUES**

Returns zero on success or non-zero if insufficient memory is available to register the process with the specified name.

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_cond\_pid()" on page 16-96
- "tr\_cond\_pid\_clear()" on page 16-98

### tr\_cond\_pid\_clear()

tr\_cond\_pid\_clear() removes all process requirements from a particular condition.

#### **NOTE**

```
Before the first tr_cond_pid() call or tr_cond_pid_name(), or after calling tr_cond_pid_clear(), the process requirement is empty which matches any process.
```

### **SYNTAX**

### **PARAMETERS**

t

data set handle

cond

handle of the condition

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_cond\_pid()" on page 16-96
- "tr\_cond\_pid\_name()" on page 16-97

### tr\_cond\_tid()

tr\_cond\_tid() appends the specified thread ID to the list of required threads IDs that must be matched for the given condition to evaluate to TRUE.

#### **NOTE**

```
Before the first tr_cond_tid() call or tr_cond_tid_name(), or after calling tr_cond_tid_clear(), the thread requirement is empty which matches any thread.
```

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

cond

handle of the condition

tid

thread ID to be added to the list of threads associated with the given condition

# **RETURN VALUES**

Returns zero on success or non-zero if insufficient memory is available to register the specified thread ID.

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_cond\_tid\_name()" on page 16-100
- "tr\_cond\_tid\_clear()" on page 16-101

#### tr\_cond\_tid\_name()

tr\_cond\_tid\_name() appends the thread with the specified name to the list of required threads that must be matched for the given condition to evaluate to TRUE.

#### **NOTE**

```
Before the first tr_cond_tid() call or tr_cond_tid_name(), or after calling tr_cond_tid_clear(), the thread requirement is empty which matches any thread.
```

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

cond

handle of the condition

tid name

name of the thread to be added to the list of threads associated with the given condition

### **RETURN VALUES**

Returns zero on success or non-zero if insufficient memory is available to register the thread with the specified name.

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_cond\_tid()" on page 16-99
- "tr\_cond\_tid\_clear()" on page 16-101

# tr\_cond\_tid\_clear()

tr\_cond\_tid\_clear() removes all thread requirements from a particular condition.

### **NOTE**

Before the first tr\_cond\_tid() call or tr\_cond\_tid\_name(), or after calling tr\_cond\_tid\_clear(), the thread requirement is empty which matches any thread.

### **SYNTAX**

#### **PARAMETERS**

t

data set handle

cond

handle of the condition

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5

### tr\_cond\_node()

tr\_cond\_node() appends the specified system node name to the list of required node names that must be matched for the given condition to evaluate to TRUE.

#### **NOTE**

Before the first tr\_cond\_node() call or after calling tr\_cond\_node\_clear(), the node requirement is empty which matches any node.

### **SYNTAX**

#### **PARAMETERS**

t

data set handle

cond

handle of the condition

node

name of the node to be added to the list of nodes associated with the given condition

### **RETURN VALUES**

Returns zero on success or non-zero if insufficient memory is available to register the specified node.

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_cond\_node\_clear()" on page 16-103

# tr\_cond\_node\_clear()

tr\_cond\_node\_clear() removes all node name requirements from a particular condition.

### **NOTE**

Before the first tr\_cond\_node() call or after calling tr\_cond\_node\_clear(), the node requirement is empty which matches any node.

### **SYNTAX**

#### **PARAMETERS**

t

data set handle

cond

handle of the condition

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_cond\_node()" on page 16-102

### tr\_cond\_func\_or()

tr\_cond\_func\_or() modifies the specified condition to include an additional requirement as specified by the user-callable function. The context parameter will be passed to the specified user function.

#### NOTE

Multiple requirements may be appended by calling  $tr\_cond\_or()/tr\_cond\_and()$  multiple times on the same condition.

#### **SYNTAX**

#### **PARAMETERS**

```
t

data set handle

cond

handle of the condition

func

user-callable function to be associated with the given condition
```

disci-canable function to be associated with the given condition

context

user-defined field to be passed to the specified user function

### **ADDITIONAL INFORMATION**

When the API evaluates the condition, it first ensures that the following requirements (if they exist) are met:

- event's trace ID matches or is within any specified trace ID or trace ID range
- event's process ID matches one of the specified process IDs
- event's thread ID matches one of the specified thread IDs
- event's node name matches one of the specified node names
- event's CPU intersects the specified CPU bias

If and only if these requirements are met, then the user's function is called.

The user function should return 1 (true) if the user's requirement is met or 0 (false) if it is not met.

Before calling  $tr\_cond\_func\_or()$ , the condition will evaluate to TRUE if all other requirements have been met.

User-defined functions may not be called by the API if the initial requirements are not met or if the left hand side of short circuit boolean condition already resolves the condition.

User-defined functions are invoked in reverse order from which they are specified with the following parenthetical relationship:

```
last_function OPERATOR (previous_function)
```

Thus calling:

```
tr_cond_func_or(cond,A);
tr_cond_func_and(cond,B);
tr_cond_func_or(cond,C);
tr cond func and(cond,D);
```

would result in the following evaluation:

```
return D && (C | | (B && A))
```

#### **RETURN VALUES**

Returns zero on success and non-zero if insufficient memory is available to register the user function with the specified condition.

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_cond\_func\_t" on page 16-5
- "tr cond or()" on page 16-112
- "tr\_cond\_and()" on page 16-113
- "tr\_cond\_func\_and()" on page 16-106
- "tr\_cond\_func\_clear()" on page 16-108

### tr\_cond\_func\_and()

tr\_cond\_func\_and() modifies the specified condition to include an additional requirement as specified by the user-callable function. The context parameter will be passed to the specified user function.

#### NOTE

Multiple requirements may be appended by calling  $tr\_cond\_or()/tr\_cond\_and()$  multiple times on the same condition.

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

cond

handle of the condition

func

user-callable function to be associated with the given condition

context

user-defined field to be passed to the specified user function

### **ADDITIONAL INFORMATION**

When the API evaluates the condition, it first ensures that the following requirements (if they exist) are met:

- event's trace ID matches or is within any specified trace ID or trace ID range
- event's process ID matches one of the specified process IDs
- event's thread ID matches one of the specified thread IDs
- event's node name matches one of the specified node names
- event's CPU intersects the specified CPU bias

If and only if these requirements are met, then the user's function is called.

The user function should return 1 (true) if the user's requirement is met or 0 (false) if it is not met.

Before calling  $tr\_cond\_func\_and()$ , the condition will evaluate to TRUE if all other requirements have been met.

User-defined functions may not be called by the API if the initial requirements are not met or if the left hand side of short circuit boolean condition already resolves the condition.

User-defined functions are invoked in reverse order from which they are specified with the following parenthetical relationship:

```
last_function OPERATOR (previous_function)
```

Thus calling:

```
tr_cond_func_or(cond,A);
tr_cond_func_and(cond,B);
tr_cond_func_or(cond,C);
tr cond func and(cond,D);
```

would result in the following evaluation:

```
return D && (C | | (B && A))
```

#### **RETURN VALUES**

Returns zero on success and non-zero if insufficient memory is available to register the user function with the specified condition.

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_cond\_func\_t" on page 16-5
- "tr cond or()" on page 16-112
- "tr\_cond\_and()" on page 16-113
- "tr\_cond\_func\_or()" on page 16-104
- "tr\_cond\_func\_and()" on page 16-106

# tr\_cond\_func\_clear()

 $\verb|tr_cond_func_clear| () clears all previously specified user function requirements.$ 

### **SYNTAX**

### **PARAMETERS**

data set handle

handle of the condition

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_cond\_func\_or()" on page 16-104
- "tr\_cond\_func\_clear()" on page 16-108

### tr\_cond\_expr\_and()

tr\_cond\_expr\_and() modifies the specified condition to include an additional requirement as specified by a valid NightTrace expression.

#### **NOTE**

Multiple requirements may be appended by calling tr\_cond\_or()/tr\_cond\_and() multiple times on the same condition.

### **SYNTAX**

#### **PARAMETERS**

t

data set handle

cond

handle of the condition

expr

string containing the NightTrace expression to be associated with the given condition

# **RETURN VALUES**

Returns zero on success or a character string describing why the specified expression is invalid.

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_cond\_expr\_or()" on page 16-110

### tr\_cond\_expr\_or()

tr\_cond\_expr\_or() modifies the specified condition to include an additional requirement as specified by a valid NightTrace expression.

#### **NOTE**

Multiple requirements may be appended by calling  $tr\_cond\_or()/tr\_cond\_and()$  multiple times on the same condition.

### **SYNTAX**

#### **PARAMETERS**

t

data set handle

cond

handle of the condition

expr

string containing the NightTrace expression to be associated with the given condition

# **RETURN VALUES**

Returns zero on success or a character string describing why the specified expression is invalid.

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_cond\_expr\_and()" on page 16-109

### tr\_cond\_not()

tr\_cond\_not() creates a new condition which evaluates to TRUE only if the specified condition evaluates to FALSE.

#### **NOTE**

The new condition will still reference the specified condition; thus subsequent changes to the specified condition will affect the outcome of the created condition.

### **SYNTAX**

```
extern tr_cond_t tr_cond_not (tr_t t, char* name, tr_cond_t cond);
```

#### **PARAMETERS**

t

data set handle

name

name to reference the newly-created condition; if an existing condition already exists with the specified *name*, it becomes unnamed but remains otherwise unchanged; if *name* is NULL, the newly-created condition will be unnamed

cond

existing condition on which to base the newly-created condition

### **RETURN VALUES**

Returns the handle of the newly-created condition; returns TR\_NO\_COND if insufficient memory is available to create the new condition.

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

# **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_cond\_or()" on page 16-112
- "tr\_cond\_and()" on page 16-113

### tr\_cond\_or()

tr\_cond\_or() creates a new condition which evaluates to TRUE if either of the specified conditions evaluate to TRUE.

#### **NOTE**

The new condition will still reference the specified conditions; thus subsequent changes to the specified conditions will affect the outcome of the created condition.

#### **SYNTAX**

# **PARAMETERS**

t

data set handle

name

name to reference the newly-created condition; if an existing condition already exists with the specified *name*, it becomes unnamed but remains otherwise unchanged; if *name* is NULL, the newly-created condition will be unnamed

left

one of two existing conditions either of which must evaluate to TRUE for the newly-created condition to evaluate to TRUE

right

one of two existing conditions either of which must evaluate to TRUE for the newly-created condition to evaluate to TRUE

#### **RETURN VALUES**

Returns the handle of the newly-created condition; returns TR\_NO\_COND if insufficient memory is available to create the new condition.

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

#### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_cond\_not()" on page 16-111
- "tr\_cond\_and()" on page 16-113

### tr\_cond\_and()

tr\_cond\_and() creates a new condition which evaluates to TRUE only if both of the specified conditions evaluate to TRUE.

#### **NOTE**

The new condition will still reference the specified conditions; thus subsequent changes to the specified conditions will affect the outcome of the created condition.

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

name

name to reference the newly-created condition; if an existing condition already exists with the specified *name*, it becomes unnamed but remains otherwise unchanged; if *name* is NULL, the newly-created condition will be unnamed

left

one of two existing conditions which must both evaluate to TRUE for the newly-created condition to evaluate to TRUE

right

one of two existing conditions which must both evaluate to TRUE for the newly-created condition to evaluate to TRUE

#### **RETURN VALUES**

Returns the handle of the newly-created condition; returns TR\_NO\_COND if insufficient memory is available to create the new condition.

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_cond\_not()" on page 16-111
- "tr\_cond\_or()" on page 16-112

### tr\_cond\_copy()

tr\_cond\_copy() creates a copy of the root of specified condition.

### NOTE

If the specified condition contains references to other conditions, (e.g. it was created by a  $tr\_cond\_or() / tr\_cond\_and()$  call), the references remain (i.e. this operation only copies the root and not all conditions it may reference).

### **SYNTAX**

#### **PARAMETERS**

t

data set handle

name

name to reference the newly-created condition; if an existing condition already exists with the specified *name*, it becomes unnamed but remains otherwise unchanged; if *name* is NULL, the newly-created condition will be unnamed

cond

handle of existing condition to copy to create new condition

### **RETURN VALUES**

Returns the handle of the newly-created copy of the specified condition; returns TR\_NO\_COND if insufficient memory is available to create the new condition.

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_cond\_or()" on page 16-112
- "tr\_cond\_and()" on page 16-113

# tr\_cond\_name()

tr\_cond\_name() returns the name of the specified condition.

#### **SYNTAX**

### **PARAMETERS**

t

data set handle

cond

handle of the condition

### **RETURN VALUES**

Returns the name of the specified condition (for debugging purposes) or NULL if it is unnamed.

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

## **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5

### tr\_cond\_satisfy()

 $tr\_cond\_satisfy()$  is used to determine if the current event satisfies the specified condition.

### **SYNTAX**

#### **PARAMETERS**

t

data set handle

cond

handle of the condition

### **RETURN VALUES**

Returns TRUE if the current event satisfies the specified condition; returns FALSE otherwise.

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

# **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5

# tr\_cond\_satisfy\_()

 $tr\_cond\_satisfy\_($ ) is used to determine if the trace event at the specified offset satisfies the specified condition.

### **SYNTAX**

#### **PARAMETERS**

t

data set handle

cond

handle of the condition

offset

offset of the trace event

# **RETURN VALUES**

Returns TRUE if the trace event at the specified offset satisfies the specified condition; returns FALSE otherwise.

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

# **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_offset\_t" on page 16-5

## tr\_cond\_register()

 $\verb|tr_cond_register|()| registers the specified condition so that it is evaluated for every event.$ 

#### NOTE

Registration of conditions increases processing time.

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

cond

handle of condition to register

### **ADDITIONAL INFORMATION**

This is the implementation of NightTrace "profiles" which are basically conditions that are evaluated as each event is consumed.

tr\_activate() should be called after all desired conditions are registered.

Registering conditions is only necessary if you wish to refer to the offset at which the specified condition was last active.

Failure to call tr\_activate() after registration of conditions will result in erroneous statistics about such conditions.

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

#### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_activate()" on page 16-131
- "Profile References" on page 15-181

### tr\_cond\_offset()

 ${\tt tr\_cond\_offset} \ (\ ) \ returns \ the \ offset \ at \ which \ the \ specified \ condition \ last \ evaluated \ to \ TRUE.$ 

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

cond

handle of the condition

#### **RETURN VALUES**

Returns the offset at which the specified condition last evaluated to TRUE; returns TR\_EOF if the condition has not yet evaluated to true up to the current offset.

See "Conditions" on page 16-88 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5
- "tr\_offset\_t" on page 16-5

# **State-oriented Interfaces**

The functions that deal with the creation, configuration, and activation of states are:

```
- tr state create() (see page 16-120)
- tr_state_find() (see page 16-121)
- tr_state_name() (see page 16-122)
- tr_state_start_id() (see page 16-123)
- tr_state_start_id_range() (see page 16-124)
- tr_state_start_id_clear() (see page 16-125)
- tr_state_end_id() (see page 16-125)
- tr_state_end_id_range() (see page 16-126)
- tr_state_end_id_clear() (see page 16-127)
- tr state start cond() (see page 16-128)
- tr_state_start_cond_clear() (see page 16-129)
- tr_state_end_cond() (see page 16-129)
- tr_state_end_cond_clear() (see page 16-130)
- tr_activate() (see page 16-131)
- tr_state_info() (see page 16-132)
- tr_state_info_() (see page 16-133)
- tr_state_active() (see page 16-134)
- tr_state_active_() (see page 16-135)
```

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### tr\_state\_create()

tr\_state\_create() creates a new state with the following attributes:

Start Events:

ALL

End Events:

ALL

**Start Condition:** 

**TRUE** 

End Condition:

**TRUE** 

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

name

name to reference the newly-created state; if an existing state already exists with the specified *name*, it becomes unnamed but remains otherwise unchanged; if *name* is NULL, the newly-created state will be unnamed

#### **RETURN VALUES**

Returns an opaque handle which identifies the newly-created state; returns TR\_NO\_STATE if there is insufficient memory available to create the state.

See "State-oriented Interfaces" on page 16-120 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

#### **SEE ALSO**

• "tr\_t" on page 16-9

### tr\_state\_find()

tr\_state\_find() locates an existing state (perhaps imported from a file) and returns
its handle.

### **SYNTAX**

### **PARAMETERS**

t

data set handle

name

name used to reference the desired state as defined in tr\_state\_create()

### **RETURN VALUES**

Returns the handle of the desired state; returns TR\_NO\_STATE if the named state does not exist.

See "State-oriented Interfaces" on page 16-120 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

#### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_state\_t" on page 16-8
- "tr\_state\_create()" on page 16-120

### tr\_state\_name()

tr\_state\_name() returns the name of the specified state.

# **SYNTAX**

#### **PARAMETERS**

t

data set handle

state

handle of the state

#### **RETURN VALUES**

Returns the name of the specified state (for debugging purposes) or NULL if the state is unnamed.

See "State-oriented Interfaces" on page 16-120 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_state\_t" on page 16-8

### tr\_state\_start\_id()

tr\_state\_start\_id() appends the specified trace ID to the list of required trace IDs that must be matched for the start event that defines the state.

### **SYNTAX**

### **PARAMETERS**

t

data set handle

state

handle of the state

id

trace ID to add to the list of required trace IDs for the start event that defines the state

### **RETURN VALUES**

Returns zero on success or non-zero if insufficient memory is available to register the ID.

See "State-oriented Interfaces" on page 16-120 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_state\_t" on page 16-8

### tr\_state\_start\_id\_range()

tr\_state\_start\_id\_range() appends the trace IDs included in the given trace ID range to the list of required trace IDs that must be matched for the start event that defines the state.

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

state

handle of the state

id1

minimum value in the range of trace IDs to be associated with the given state

id2

maximum value in the range of trace IDs to be associated with the given state

# **RETURN VALUES**

Returns zero on success or non-zero if insufficient memory is available to register the IDs.

See "State-oriented Interfaces" on page 16-120 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_state\_t" on page 16-8

### tr\_state\_start\_id\_clear()

tr\_state\_start\_id\_clear() removes all trace ID requirements related to the start event that defines a particular state (such that that all events are candidates to start a state).

### **SYNTAX**

#### **PARAMETERS**

t

data set handle

state

handle of the state

See "State-oriented Interfaces" on page 16-120 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_state\_t" on page 16-8

### tr\_state\_end\_id()

tr\_state\_end\_id() appends the specified trace ID to the list of required trace IDs that must be matched for the end event that defines the state.

# **SYNTAX**

#### **PARAMETERS**

t

data set handle

state

handle of the state

id

trace ID to add to the list of required trace IDs for the end event that defines the state

#### **RETURN VALUES**

Returns zero on success or non-zero if insufficient memory is available to register the ID.

See "State-oriented Interfaces" on page 16-120 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

#### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_state\_t" on page 16-8

# tr\_state\_end\_id\_range()

tr\_state\_end\_id\_range() appends the trace IDs included in the given trace ID range to the list of required trace IDs that must be matched for the end event that defines the state.

### **SYNTAX**

#### **PARAMETERS**

t

data set handle

state

handle of the state

id1

minimum value in the range of trace IDs to be associated with the given state

id2

maximum value in the range of trace IDs to be associated with the given state

# **RETURN VALUES**

Returns zero on success or non-zero if insufficient memory is available to register the IDs.

See "State-oriented Interfaces" on page 16-120 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

#### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_state\_t" on page 16-8

# tr\_state\_end\_id\_clear()

tr\_state\_end\_id\_clear() removes all trace ID requirements related to the end event that defines a particular state (such that all events are candidates to end a state).

# **SYNTAX**

#### **PARAMETERS**

t

data set handle

state

handle of the state

See "State-oriented Interfaces" on page 16-120 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_state\_t" on page 16-8

# tr\_state\_start\_cond()

 $\mbox{tr\_state\_start\_cond()} \ associates \ a \ certain \ condition \ with \ start \ of \ a \ particular \ state.$ 

# **SYNTAX**

```
extern void tr_state_start_cond (tr_t t, tr_state_t state, tr_cond_t cond);
```

# **PARAMETERS**

data set handle

state

handle of the state

cond

handle of the condition to associate with the start of the specified state

See "State-oriented Interfaces" on page 16-120 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_state\_t" on page 16-8
- "tr\_cond\_t" on page 16-5

# tr\_state\_start\_cond\_clear()

 ${\tt tr\_state\_start\_cond\_clear()} \ clears \ any \ conditions \ associated \ with \ start \ of \ a$  particular state.

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

state

handle of the state

See "State-oriented Interfaces" on page 16-120 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_state\_t" on page 16-8

# tr\_state\_end\_cond()

tr\_state\_end\_cond() associates a certain condition with end of a particular state.

### **SYNTAX**

#### **PARAMETERS**

t

data set handle

state

handle of the state

cond

handle of the condition to associate with the end of the specified state

See "State-oriented Interfaces" on page 16-120 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

# **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_state\_t" on page 16-8
- "tr\_cond\_t" on page 16-5

# tr\_state\_end\_cond\_clear()

 $\verb|tr_state_end_cond_clear| () clears any conditions associated with end of a particular state.$ 

# **SYNTAX**

#### **PARAMETERS**

t

data set handle

state

handle of the state

See "State-oriented Interfaces" on page 16-120 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_state\_t" on page 16-8

# tr\_activate()

tr\_activate() must be called after the configuration of all states and the registration of all conditions is complete. It may be called multiple times.

#### **NOTE**

Failure to call this function will result in undefined state evaluation and false conditions.

#### **SYNTAX**

```
extern int tr_activate (tr_t t);
```

#### **PARAMETERS**

t

data set handle

# **RETURN VALUES**

Returns zero upon successful activation or -1 if a circular dependency between states is detected.

#### ADDITIONAL INFORMATION

If the current position is other than the beginning of the data set, user-defined functions associated with conditions in states may be called during the invocation of tr\_state\_active().

See "State-oriented Interfaces" on page 16-120 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_state\_active()" on page 16-134

# tr\_state\_info()

tr\_state\_info() returns a structure containing the current values associated with the last completed instance of the specified state

#### **SYNTAX**

# **PARAMETERS**

t data set handle state handle of the state

info

pointer to a structure which will contain the current values associated with the last completed instance of the specified state

# **RETURN VALUES**

The return values are contained in the tr\_state\_info\_t structure (see "tr\_state\_info\_t" on page 16-7).

If the state has never been active, start\_offset and end\_offset are set to TR\_EOF and gap and duration are set to zero.

See "State-oriented Interfaces" on page 16-120 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_state\_t" on page 16-8
- "tr\_state\_info\_t" on page 16-7

# tr\_state\_info\_()

tr\_state\_info\_() returns a structure containing the current values associated with the given state at the specified offset.

#### **NOTE**

Calling tr\_state\_info\_() is an expensive operation if the specified offset is not the current position.

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

state

handle of the state

info

pointer to a structure which will contain the current values associated with the given state at the specified offset

offset

offset of the specifed state

# **RETURN VALUES**

The return values are contained in the tr\_state\_info\_t structure (see "tr\_state\_info\_t" on page 16-7).

If the state has never been active, start\_offset and end\_offset are set to TR EOF and gap and duration are set to zero.

See "State-oriented Interfaces" on page 16-120 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

# **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_state\_t" on page 16-8
- "tr\_state\_info\_t" on page 16-7
- "tr\_offset\_t" on page 16-5

# tr\_state\_active()

tr\_state\_active() is used to determine if the specified state is active at the current
offset.

#### **SYNTAX**

# **PARAMETERS**

t data set handle state

handle of the state

#### **RETURN VALUES**

Returns TRUE if the specified state is active at the current offset; returns FALSE otherwise.

See "State-oriented Interfaces" on page 16-120 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_state\_t" on page 16-8

# tr\_state\_active\_()

tr\_state\_active\_() is used to determine if the given state is active at the specified offset.

#### **NOTE**

Calling tr\_state\_active\_() is an expensive operation if the specified offset is not the current position.

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

state

handle of the state

offset

offset of the specified state

# **RETURN VALUES**

Returns TRUE if the given state is active at the specified offset; returns FALSE otherwise.

See "State-oriented Interfaces" on page 16-120 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_state\_t" on page 16-8
- "tr\_offset\_t" on page 16-5

# **Output Function**

The function dealing with the output of trace data is:

```
tr_copy_input() (see page 16-136)tr_copy_input_range() (see page 16-137)
```

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

# tr\_copy\_input()

tr\_copy\_input() consumes the entire input data set and copies all events which satisfy the specified condition to the output file.

#### **SYNTAX**

#### **PARAMETERS**

```
data set handle

output_file

pathname of the output file

cond

handle of the condition

mode
```

parameter passed to the system call invoked to open/create the specified output file

#### **RETURN VALUES**

Returns zero upon success; returns -1 upon error in which case errno will be set to a value as per open(2) or read(2).

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5

# tr\_copy\_input\_range()

tr\_copy\_input\_range() copies all the events in the data set whose offsets lie in the range specified.

# **SYNTAX**

#### **PARAMETERS**

data set handle

pathname of the output file

mode

output\_file

parameter passed to the system call invoked to open/create the specified output file

start

start of the range

end

end of the range

#### **RETURN VALUES**

Returns zero upon success; returns -1 upon error in which case errno will be set to a value as per open(2) or read(2).

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5

# **String Table Functions**

The following functions are provided to create, manage, and search NightTrace string tables:

```
tr_get_string() (see page 16-138)
tr_get_item() (see page 16-139)
tr_create_table() (see page 16-140)
tr_append_table() (see page 16-141)
```

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

# tr\_get\_string()

tr\_get\_string() returns the string associated with the number of the desired item in the specified table.

#### **SYNTAX**

#### **PARAMETERS**

```
t data set handle table_name name of the string table item
```

position of the desired item in the specified table

# **RETURN VALUES**

Returns the string associated with the number of the desired item in the specified table; returns "" if no match is found.

See "String Table Functions" on page 16-138 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

# **SEE ALSO**

- "tr\_t" on page 16-9
- "String Tables" on page 6-13

# tr\_get\_item()

tr\_get\_item() returns the item number associated with the string entry in the specified table that matches the specified value.

#### **SYNTAX**

# **PARAMETERS**

t

data set handle

table\_name

name of the table to search for the specified string

value

string entry to search for in the specified table

#### **RETURN VALUES**

Returns the item number associated with the string entry in the specified table that matches the specified value; returns zero if no match is found.

See "String Table Functions" on page 16-138 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "String Tables" on page 6-13

#### tr\_create\_table()

tr\_create\_table() is used to create a string table.

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

table\_name

name to subsequently reference the newly-created table

default value

string to associate with integer values that are not explicitly referenced in the table

list

pointer to a list of string table entries

count

number of entries in the list of string table entries

#### **RETURN VALUES**

Returns zero on success; returns -1 if insufficient memory is available to complete the request or invalid values are specified.

# **ADDITIONAL INFORMATION**

All strings referenced by value fields are copied during the operation; therefore the source of the strings need not remain allocated after the call completes.

See "String Table Functions" on page 16-138 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

# **SEE ALSO**

• "tr\_t" on page 16-9

- "tr\_string\_node\_t" on page 16-8
- "String Tables" on page 6-13

# tr\_append\_table()

tr\_append\_table() associates a particular string with a certain position in a given string table.

#### NOTE

If the position specified is already associated with a string, tr\_append\_table() will overwrite the previous entry.

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

table\_name

name of the table to modify

value

character string to assign to the given item number

item

position in the table to associate with the given string

# **RETURN VALUES**

Returns zero on success; returns -1 if insufficient memory is available to complete the request or invalid values are specified.

# ADDITIONAL INFORMATION

All strings referenced by value fields are copied during the operation; therefore the source of the strings need not remain allocated after the call completes.

See "String Table Functions" on page 16-138 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "String Tables" on page 6-13

# Callback Interfaces

The following functions deal with the callback capabilities of the NightTrace Analysis Application Programming Interface:

```
- tr_iterate() (see page 16-143)
```

- tr\_halt() (see page 16-144)
- tr\_cancel\_cb() (see page 16-144)
- tr\_cond\_cb() (see page 16-145)
- tr\_state\_cb() (see page 16-146)

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

# tr\_iterate()

tr\_iterate() iteratively processes all events starting at the current position through the end of the data set. For each event, user-defined callback functions registered with tr\_cond\_cb() or tr\_state\_cb() will be invoked as required.

#### **SYNTAX**

```
extern int tr_iterate (tr_t t);
```

#### **PARAMETERS**

t

data set handle

#### **RETURN VALUES**

Returns zero on success and non-zero if an error occurs. Currently, the only error is to reach the memory limit specified on the tr\_open\_stream() call if the input source is streaming data.

See "Callback Interfaces" on page 16-143 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_cond\_cb()" on page 16-145
- "tr\_state\_cb()" on page 16-146
- "tr\_open\_stream()" on page 16-20

# tr\_halt()

tr\_halt() halts the iteration process, causing tr\_iterate() to return.

#### **SYNTAX**

```
extern void tr_halt (tr_t t);
```

#### **PARAMETERS**

t

data set handle

See "Callback Interfaces" on page 16-143 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

# **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_iterate()" on page 16-143

# tr\_cancel\_cb()

tr\_cancel\_cb() cancels the specified callback.

# **SYNTAX**

```
extern void tr_cancel_cb (tr_t t, tr_cb_t cb);
```

### **PARAMETERS**

t

data set handle

cb

handle of the callback to be cancelled

See "Callback Interfaces" on page 16-143 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

#### **SEE ALSO**

- "tr\_t" on page 16-9
- "tr\_cb\_t" on page 16-4

# tr\_cond\_cb()

tr\_cond\_cb() registers a user-defined callback function which will be iteratively called for every event that satisfies the specified condition.

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

cond

handle of the condition that must be satisfied in order for the callback function to be called

func

function to be called if the given condition is satisfied for a particular event

context

user defined value which is passed to the specified callback function

# **RETURN VALUES**

Returns an opaque handle which identifies the callback; returns TR\_NO\_CB if the specified arguments are invalid or there is insufficient memory available to register the callback function.

See "Callback Interfaces" on page 16-143 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_cond\_t" on page 16-5

- "tr\_cond\_cb\_func\_t" on page 16-4
- "tr\_cb\_t" on page 16-4

# tr\_state\_cb()

tr\_state\_cb() registers a user-defined callback function which will be iteratively invoked for every event that affects the given state in the manner specified.

#### **SYNTAX**

#### **PARAMETERS**

t

data set handle

state

handle of the state

action

specifies the manner in which the given function will be called (see "tr\_state\_action\_t" on page 16-6)

func

function which will be iteratively invoked for every event that affects the given state in the specified manner

context

user defined value which is passed to the specified callback function

#### **RETURN VALUES**

Returns an opaque handle which identifies the callback; returns TR\_NO\_CB if the specified arguments are invalid or there is insufficient memory available to register the callback function.

See "Callback Interfaces" on page 16-143 for related functions.

See "Functions" on page 16-10 for a complete list of functions included in the NightTrace Analysis API.

- "tr\_t" on page 16-9
- "tr\_state\_t" on page 16-8
- "tr\_state\_action\_t" on page 16-6
- "tr\_state\_cb\_func\_t" on page 16-6
- "tr\_cb\_t" on page 16-4

# Α

# NightStar LX Licensing

NightStar LX uses the NightStar License Manager (NSLM) to control access to the NightStar LX tools.

License installation requires a licence key provided by Concurrent (see "License Keys" on page A-1). The NightStar LX tools request a licence (see "License Requests" on page A-2) from a license server (see "License Server" on page A-2).

Two license modes are available, fixed and floating, depending on which product option you purchased. Fixed licenses can only be served to NightStar LX users from the local system. Floating licenses may be served to any NightStar LX user on any system on a network.

Tools are licensed per system, per concurrent user. A single license is shared among any or all of the NightStar LX tools for a particular user on a particular system. The intent is to allow n developers to fully utilize all the tools at the same time while only requiring n licenses. When operating the tools in remote mode, where a tool is launched on a local system but is interacting with a remote system, licenses are required only from the host system.

You can obtain a license report which lists all licenses installed on the local system, current usage, and expiration date for demo licenses (see "License Reports" on page A-3).

The default configuration includes a strict firewall which interferes with floating licenses. See "Firewall Configuration for Floating Licenses" on page A-3 for information on handling such configurations.

See "License Support" on page A-6 for information on contacting Concurrent for additional assistance with licensing issues.

# **License Keys**

Licenses are granted to specific systems to be served to either local or remote clients, depending on the license model, fixed or floating.

License installation requires a license key provided by Concurrent. To obtain a license key, you must provide your system identification code. The system identification code is generated by the nslm\_admin utility:

#### nslm admin --code

System identification codes are dependent on system configurations. Reinstalling Linux on a system or replacing network devices may require you to obtain new license keys.

To obtain a license key, use the following URL and click on the *Licenses* link:

#### http://www.ccur.com/NightStarKeys

Provide the requested information, including the system identification code. Your license key will be immediately emailed to you.

Install the license key using the following command:

```
nslm_admin --install=xxxx-xxxx-xxxx-xxxx
```

where xxxx-xxxx-xxxx-xxxx is the key included in the license acknowledgment email.

# **License Requests**

By default, the NightStar LX tools request a license from the local system. If no licenses are available, they broadcast a license request on the local subnet associated with the system's hostname.

You can control the license requests for an entire system using the /etc/nslm.config configuration file.

By default, the /etc/nslm.config file contains a line similar to the following:

#### :server @default

The argument @default may be changed to a colon-separated list of system names, system IP addresses, or broadcast IP addresses. Licenses will be requested from each of the entities found in the list, until a license is granted or all entries in the list are exhausted.

For example, the following setting prevents broadcast requests for licenses, by only specifying the local system:

#### :server localhost

The following setting requests a license from **server1**, then **server2**, and then a broadcast request if those fail to serve a license:

```
:server server1:server2:192.168.1.0
```

Similarly, you can control the license requests for individual invocations of the tools using the NSLM\_SERVER environment variable. If set, it must contain a colon-separated list of system names, system IP addresses, or broadcast IP addresses as described above. Use of the NSLM\_SERVER environment variable takes precedence over settings defined in /etc/nslm.config.

# **License Server**

The NSLM license server is automatically installed and configured to run when you install NightStar LX.

The **nslm** service is automatically activated for run levels 2, 3, 4, and 5. You can check on these settings by issuing the following command:

```
/sbin/chkconfig --list nslm
```

In rare instances, you may need to restart the license server via the following command:

/sbin/service nslm restart

See nslm(1) for more information.

# **License Reports**

A license report can be obtained using the **nslm\_admin** utility.

```
nslm admin --list
```

lists all licenses installed on the local system, current usage, and expiration date (for demo licenses). Use of the **--verbose** option also lists individual clients to which licenses are currently granted.

Adding the **--broadcast** option will list this information for all servers that respond to a broadcast request on the local subnet associated with the system's hostname.

See nslm\_admin(1) for more options and information.

# **Firewall Configuration for Floating Licenses**

The default operating system configuration includes a strict firewall which interferes with floating licenses.

If such a system is used to serve licenses, then at least one port must be opened in its fire-wall to allow server requests to pass. See "Serving Licenses with a Firewall" on page A-3 for more information.

Similarly, if such a system is host to the NightStar LX tools, then at least one port must be opened in its firewall so that it can receive licenses from the license server. If this is not done, a tool requesting a floating license will not receive it and will not function properly. See "Running NightStar LX Tools with a Firewall" on page A-5 for more information.

# **Serving Licenses with a Firewall**

Following are a few approaches for allowing the NSLM license server to serve floating licences when the system on which it is running is configured with a firewall:

disable the firewall on the system entirely

- allow NSLM license requests from a specific system (or one of several)
- allow NSLM license requests from any system on a particular subnet (or one of several)
- allow NSLM license requests from any system

#### **NOTE**

You must be root in order to modify the firewall configuration.

To disable the firewall entirely, execute:

```
service iptables stop
```

and then remove the /etc/sysconfig/iptables file:

```
rm -f /etc/sysconfig/iptables
```

This option may not be as dangerous as it seems. Often, whole networks are protected with a firewall so it is not necessary for individual systems on the network to be protected further. If unsure, check with your network administrator.

For the remaining cases, a simple modification should be made to the /etc/sysconfig/iptables file to allow license requests on UDP port 25517 and TCP port 25517. By default, that file should contain a line like the following:

```
-A RH-Firewall-1-INPUT -j REJECT --reject-with icmp-host-prohibited
```

To allow NSLM license requests from a specific system, insert the following lines before the REJECT line:

```
-A RH-Firewall-1-INPUT -p udp -m udp -s system --dport 25517 -j ACCEPT -A RH-Firewall-1-INPUT -p tcp -m tcp -s system --dport 25517 -j ACCEPT
```

Those lines can be repeated for multiple systems.

To allow NSLM license requests from any system on a particular subnet, insert the following lines before the REJECT line:

```
-A RH-Firewall-1-INPUT -p udp -m udp -s subnet/mask --dport 25517 -j ACCEPT -A RH-Firewall-1-INPUT -p tcp -m tcp -s subnet/mask --dport 25517 -j ACCEPT
```

The subnet might be of a form like 192.168.1.0 and the mask could be a traditional network mask like 255.255.255.0 or a single number like 24, which indicates the number of bits from the left that are part of the mask. For example, 192.168.1.0/255.255.255.0 and 192.168.1.0/24 are equivalent.

Those lines can be repeated for multiple subnets.

To allow NSLM license requests from any system, insert the following lines before the REJECT line:

```
-A RH-Firewall-1-INPUT -p udp -m udp --dport 25517 -j ACCEPT -A RH-Firewall-1-INPUT -p tcp -m tcp --dport 25517 -j ACCEPT
```

After modifying /etc/sysconfig/iptables, execute:

service iptables restart

# Running NightStar LX Tools with a Firewall

Following are a few approaches for allowing a NightStar LX tool to receive floating licenses from a license server, when the system running the NightStar LX tool is configured with a firewall:

- disable the firewall on the requesting system entirely
- allow NSLM licenses from a specific license server (or one of several)
- allow NSLM licenses from any system on a particular subnet (or one of several)
- allow NSLM licenses from any system

#### NOTE

You must be root in order to modify the firewall configuration.

To disable the firewall entirely, execute:

```
service iptables stop
```

and then remove the /etc/sysconfig/iptables file:

```
rm -f /etc/sysconfig/iptables
```

This option may not be as dangerous as it seems. Often, whole networks are protected with a firewall so it is not necessary for individual systems on the network to be protected further. If unsure, check with your network administrator.

For the remaining cases, a simple modification should be made to the /etc/sysconfig/iptables file to allow license responses from UDP port 25517. By default, that file should contain a line like the following:

```
-A RH-Firewall-1-INPUT -j REJECT --reject-with icmp-host-prohibited
```

To allow NSLM licenses from a specific system running a license server, insert the following line before the REJECT line:

```
-A RH-Firewall-1-INPUT -p udp -m udp -s server --sport 25517 -j ACCEPT
```

That line can be repeated for multiple servers.

To allow NSLM licenses from any system running a license server on a particular subnet, insert the following before the REJECT line:

```
-A RH-Firewall-1-INPUT -p udp -m udp -s subnet/mask --sport 25517 -j ACCEPT
```

The subnet might be of a form like 192.168.1.0 and the mask could be a traditional network mask like 255.255.255.0 or a single number like 24, which indicates the number of bits from the left that are part of the mask. For example, 192.168.1.0/255.255.255.0 and 192.168.1.0/24 are equivalent.

That line can be repeated for multiple subnets.

To allow NSLM licenses from any system running a license server, insert the following line before the REJECT line:

```
-A RH-Firewall-1-INPUT -p udp -m udp --sport 25517 -j ACCEPT
```

After modifying /etc/sysconfig/iptables, execute:

service iptables restart

# **License Support**

For additional aid with licensing issues, contact the Concurrent Software Support Center at our toll free number 1-800-245-6453. For calls outside the continental United States, the number is 1-954-283-1822. The Software Support Center operates Monday through Friday from 8 a.m. to 5 p.m., Eastern Standard Time.

You may also submit a request for assistance at any time by using the Concurrent Computer Corporation web site at <a href="http://www.ccur.com/isd\_support\_contact.asp">http://www.ccur.com/isd\_support\_contact.asp</a> or by sending an email to <a href="mailtosupport@ccur.com">support@ccur.com</a>.

# **Kernel Dependencies**

Additional features and benefits are granted the NightStar tools when operating with real-time kernels from Concurrent Computer Corporation.

#### RedHawk Linux

The RedHawk Linux kernel from Concurrent Computer Corporation (http://www.ccur.com) provides real-time capabilities over and above the Red Hat kernel. RedHawk Linux operates on top of a Red Hat distribution.

# **Advantages for NightView**

The following advantages are afforded NightView when a RedHawk kernel is running:

• Application speed conditions

Provides "execution-speed" patches, conditions, and ignore counts.

Signal handling

Allows NightView to pass signals directly to a particular process, avoiding context switching and stopping the process if the signal is handled.

Branch tracking

Allows NightView to show you a history of branches. This is especially useful for programs that end up in unexpected locations, usually the result of returning from a routine with a corrupted stack frame. The branch history often allows you to locate where the program execution went awry.

# Advantages for NightTrace

The following advantages are afforded NightTrace when a RedHawk tracing kernel is running:

• Kernel tracing

Users of NightTrace gain the ability to obtain kernel trace data and combine that with user trace data. Kernel tracing is an incredibly powerful feature that not only provides insight into the operating system kernel but also provides useful information relating to the execution of user applications.

The RedHawk real-time kernel is provided in three flavors:

- Tracing
- Debug
- Plain

The Tracing and Debug flavors provide the features required for NightTrace kernel tracing. These kernels can be selected at boot-time from the boot-loader menu.

# • CUDA Application Tracing

While not specifically a RedHawk kernel feature, RedHawk provides an optimized NVidia driver along with a pre-built NightTrace Illuminator for the CUDA API library. This illuminator automatically instruments user applications that utilize the CUDA API so that you can see all API function entries and returns. This includes the execution of user routines on the GPU itself along with the amount of time spent executing on the GPU.

# Advantages for NightProbe

The following advantages are afforded NightProbe when a RedHawk kernel is running:

#### Minimal intrusion

Allows NightProbe to read and write variables without stopping the process for each sample or write operation.

# • Sampling performance

Allows NightProbe to use direct memory fetches for data sampling (as opposed to programmed I/O) which is important for high-rate data acquisition.

# • Concurrent debugging/probing

Allows NightProbe to probe programs already under the control of a debugger or another NightProbe session.

# • PCI Device probing

Allows NightProbe to probe PCI device memory via the Base Address Register (BAR) file system.

The PCI BAR File System is only available with the RedHawk kernel from Concurrent Computer Corporation. On other systems, PCI Device probing will be disabled within NightProbe.

# **Advantages for NightTune**

The following advantages are afforded NightTune when a RedHawk kernel is running:

· Context switch rate

Allows NightTune to display the context switch counts per CPU instead of for the overall system.

• CPU shielding

Individual CPUs can be shielded from interrupts and processes allowing CPUs to be dedicated solely to specific interrupts and processes that are bound to the CPU.

• CPU sibling interference

Individual CPUs can be marked down to avoid interfering with hyperthreaded sibling CPUs and dual-core sibling CPUs. Hyperthreaded CPUs share all the resources of their sibling CPU. Dual-core CPUs share the CPU cache and a path to memory with their sibling CPU.

• Detailed memory information

Detailed process memory descriptions include the residency and lock state of any page in a process, and their association with physical memory pools for NUMA systems.

• Kernel Activity and Single Process Activity panels

Provides non-intrusive monitoring of kernel or process/thread activity, including percent of time spent in individual routines in the kernel, in shared libraries, and in user processes. Routines are described using their symbolic name.

• Single Process Counter

Provides non-intrusive monitoring of low-level CPU operations, such as cpu cycles, instructions, bus cycles, branches, cache hits and misses, page faults, cpu migrations, and context switches for individual processes/threads.

· CUDA Configuration and Activity

While not specifically a RedHawk kernel feature, RedHawk provides an optimized NVidia driver that allows NightTune to show detailed CUDA configuration information as well as CUDA device activity, including GPU usage, fan speed, GPU memory usage, etc.

# **Frequency Based Scheduler**

The Frequency Based Scheduler is only available on RedHawk systems from Concurrent Computer Corporation. It is required for all NightSim usage.

FBS Process Deadlines are only available for use on RedHawk 5.2.1 and later systems.

On systems without FBS Process Deadline support, the "Apply Deadline" group box will appear shaded and disabled.

NightSim is only included in NightStar distributions intended for use on RedHawk systems.

Some features of NightTrace require either root access or privileged access as described below.

This chapter provides an overview of the capabilities mechanism support by some operating systems.

The following operating system kernels support the capabilities mechanism:

- RedHawk Linux (all versions)
- SUSE Linux Enterprise Real Time (versions 1.0-1.6 only)

# **Capabilities**

The following capabilities may be required when using NightTrace:

• CAP\_SYS\_NICE

If you wish to run the **ntraceud** daemon with a real-time scheduling policy and priority, you must have this capability. For example:

```
ntraceud --policy=fifo --priority=50 data-file
```

• CAP\_IPC\_LOCK

If you wish to run the **ntraceud** daemon and force shared pages between the user application and the daemon to be locked in memory, you must have this capability. Similarly, this capability is required if you specify page locking when configuring a daemon via the API. For example:

```
ntraceud --lock data-file

or

ntconfig_t config;
  trace_default_config(&config);
  config.ntc_lock_pages = ntp_lock;
  config.ntc_daemon_preferred = false;
  trace_begin("data-file",&config);
```

Linux provides a means to grant otherwise unprivileged users the authority to perform certain privileged operations. The Pluggable Authentication Module (see pam\_capability(8)) is used to manage sets of capabilities, called *roles*, required for various activities.

Linux systems should be configured with an ntraceuser role which provides the CAP\_SYS\_NICE and CAP\_IPC\_LOCK capabilities.

Edit /etc/security/capability.conf and define the ntraceuser role (if it is not already defined) in the "ROLES" section:

```
role ntraceuser CAP_SYS_NICE CAP_IPC_LOCK
```

Additionally, for each NightTrace user on the target system, add the following line at the end of the file:

```
user username ntraceuser
```

where *username* is the login name of the user.

If the user requires capabilities not defined in the ntraceuser role, add a new role which contains ntraceuser and the additional capabilities needed, and substitute the new role name for ntraceuser in the text above.

In addition to registering your login name in /etc/security/capability.conf, certain files under the /etc/pam.d directory must also be configured to allow capabilities to be activated.

To activate capabilities, add the following line to the end of selected files in /etc/pam.d if it is not already present:

```
session required pam capability.so
```

The list of files to modify is dependent on the list of methods that will be used to access the system. The following table presents a recommended configuration that will grant capabilities to users of the services most commonly employed in accessing a system.

Table C-1. Recommended /etc/pam.d Configuration

/etc/pam.d File	Affected Services	Comment
remote	telnet rlogin rsh (when used <u>w/o</u> a command)	Depending on your system, the <b>remote</b> file may not exist. Do not create the <b>remote</b> file, but edit it if it is present.
login	local login (e.g. console) telnet* rlogin* rsh* (when used w/o a command)	*On some versions of Linux, the presence of the remote file limits the scope of the login file to local logins. In such cases, the other services listed here with login are then affected solely by the remote configuration file.
pass- word-auth	Many	Recent versions of the Linux kernel require this file be modified as well.
rsh	rsh (when used with a command)	e.g. rsh system_name a.out

Table C-1. Recommended /etc/pam.d Configuration

/etc/pam.d File	Affected Services	Comment
sshd	ssh	You must also edit /etc/ssh/sshd_config and ensure that the following line is present: UsePrivilegeSeparation no
gdm	gnome sessions	
kde	kde sessions	

If you modify /etc/pam.d/sshd or /etc/ssh/sshd\_config, you must restart the sshd service for the changes to take effect:

service sshd restart
bash /etc/init.d/sshd restart

In order for the above changes to take effect, the user must log off and log back onto the target system.

# **NOTE**

To verify that you have been granted capabilities, issue the following command:

/usr/sbin/getpcaps \$\$
/sbin/getpcaps \$\$

The output from that command will list the roles currently assigned to you.

# **NightTrace Logging API Examples**

This chapter provides several examples using the NightTrace Logging API.

# Single Threaded C Example

This example uses demonstrates a minimalist approach to tracing, foregoing any error checking and logging very simple events.

```
#include <ntrace.h>
main()
{
    volatile double x = 0.0;
    int i,j;

    trace_begin ("data",0);

    for (j=0; j<100; ++j) {
        trace_event (1);
        for (i=0; i<1000; ++i) {
            x = x * x;
        }
        trace_event (2);
    }
}</pre>
```

The call to trace\_begin() initializes tracing with default parameters.

We call trace\_event() with different event identifiers immediately before and after our application's workload, represented by the inner loop.

The following commands could be used to compile, link, and execute the application using command-line daemon execution:

```
$ cc -g file.c -lntrace
$ ntraceud data; ./a.out; ntraceud -q data
```

Using the command line summary option to ntrace, print a summary of each execution of the outer loop:

### NightTrace LX User's Guide

Condition Summary Results

Number of matching events found: 100

Average gap between matching events: 0.000000184

Maximum gap between matching events: 0.00000391

Maximum gap event offset: 1

Minimum gap between matching events: 0.000000165

Minimum gap event offset: 17

# Multi-Threaded C++ Example

This example demonstrates using NightTrace event logging from multiple threads.

```
#include <stdio.h>
#include <stdlib.h>
#include <ntrace.h>
#include <time.h>
#define Start 100
#define End 200
volatile int done = 0;
int work (int input)
   // do something
   return input;
void *
thread_a (void * ptr)
  int i = 0;
  int result;
  trace_set_thread_name ("romeo");
  struct timespec ts = { 0, 20000000};
  while (!done) {
     trace_event_arg (Start, i);
     result = work(i++);
     trace_event_arg(End, result);
     nanosleep(&ts,0);
}
void *
thread_b (void * ptr)
  int i=9999999;
  int result;
  trace_set_thread_name ("juliet");
  struct timespec ts = { 0, 20000000};
   while (!done) {
     trace_event_arg (Start, i);
     result = work(i--);
     trace_event_arg(End, result);
      nanosleep(&ts,0);
}
main (int argc, char * argv[])
  pthread_t thread;
  pthread_attr_t attr;
  int status;
   status = trace_begin ("data",NULL);
   switch (status) {
   case NTLISTEN:
      printf ("No daemon is listening -- "
              "proceeding in case one shows up\n");
```

The call to trace\_begin() initializes tracing with default parameters.

Immediately within the thread routines, each thread identifies itself with a symbolic name via a call to trace\_set\_thread\_name(). If these calls were not made, the threads would be automatically named by NightTrace using the thread's internal gettid(2) integer value.

The following commands could be used to compile, link, and execute the application using command-line daemon execution:

```
$ cc -g file.c -lntrace_thr -lpthread
$ ntraceud data; ./a.out; ntraceud -q data
```

#### **NOTE**

Note the use of the thread-aware version of the NightTrace logging API library, **-lntrace\_thr**. This is required for use with multi-threaded programs if you want to be able to distinguish between individual threads in trace events. See "Threads and Logging" on page 2-31 for more information).

The following command invokes **ntrace** to graphically view the events. A customized page is automatically built which distinguishes events between the two threads: romeo and juliet:

#### \$ ntrace data NightTrace - New Session(Unsaved) Daemons Search Summary Profiles Timelines Tools Help **७** ⊪ **K** Σ ▦ 101 abc • one of the control of Thread: juliet(2841) Thread: romeo(2840) User Events: 0.21s 0.11s 0.31s 0.31s 0.61s 0.91s 0.01s Hover time from current timeline = 0.154125313 Current Time 0.193644625 0.000000000 Start Time End Time 0.387289249 Current offset=59 id=200 proc=a.out thr=juliet Span 0.387289249 time(sec)=0.186645520 (0.006999104 from current time) arg1=0x989676 (1) Hover time from current timeline = 0.154125313

## Figure C-1. Automatically Generated Data Display Page

## **Fortran Example**

This example uses demonstrates a simple Fortran program logging a trace event.

```
program ftrace
include "/usr/include/ntrace_.h"
integer void

void = trace_begin("data",0)

do 10 i=1,10
    void = trace_event_arg(1,i)
continue

void = trace_end()
end
```

The call to trace\_start() initializes tracing with default parameters.

We call trace\_event\_arg() with the loop iterator for each iteration.

The following commands could be used to compile, link, and execute the application using command-line daemon execution:

```
$ g77 -g file.c -lntrace
$ ntraceud data; ./a.out; ntraceud -q data
```

Using the command line listing option to ntrace, we see the values of the iterator as event points are logged:

#### \$ ntrace --listing data

```
0: cpu=?? 1 pid=a.out thr=main time=0.000000000s arg1=0x1
1: cpu=?? 1 pid=a.out thr=main time=0.000002481s arg1=0x2
2: cpu=?? 1 pid=a.out thr=main time=0.000003103s arg1=0x3
3: cpu=?? 1 pid=a.out thr=main time=0.00000356s arg1=0x4
4: cpu=?? 1 pid=a.out thr=main time=0.000003976s arg1=0x5
5: cpu=?? 1 pid=a.out thr=main time=0.000004386s arg1=0x6
6: cpu=?? 1 pid=a.out thr=main time=0.000004882s arg1=0x7
7: cpu=?? 1 pid=a.out thr=main time=0.000005302s arg1=0x8
8: cpu=?? 1 pid=a.out thr=main time=0.000005820s arg1=0x9
9: cpu=?? 1 pid=a.out thr=main time=0.000006294s arg1=0xa
```

# Simple Java Example

This example demonstrates a minimalist approach to tracing in Java, foregoing any error checking and logging very simple events.

```
import ntrace.logging.Trace;

class SimpleTracing {
    public static void main (String args[]) {
        Trace.begin("data");
        for (int j=0; j<10; j++) {
            Trace.event(1,j);
        }
        System.out.println("That was easy!");
    }
}</pre>
```

The call to Trace.begin() initializes tracing with default parameters.

In the code above, we call Trace.event() with different trace argument values inside the loop, but always with the trace event ID of 1.

The following commands could be used to build and execute the application:

```
$ javac -classpath /usr/lib:. SimpleTracing.java
$ ntraceud data
$ java -classpath /usr/lib:. SimpleTracing
That was easy!
$ ntraceud -q data
```

#### NOTE:

Some versions of java require you to explicitly place /usr/lib in your LD\_LIBRARY\_PATH environment variable. If you get an error when invoking the java class that mentions java.lang.UnsatisfiedLinkError, then try setting LD\_LIBRARY\_PATH to include /usr/lib.

Use the command line **--summary** option to **ntrace** to summarize the logged events:

#### \$ ntrace --summary=ev:1 data

# **Multi-Threaded Java Example**

This example demonstrates tracing in a multi-threaded Java program.

```
import ntrace.logging.Trace;
class ThreadedTracing {
  public static class MyThread extends Thread {
      public MyThread (String name) {
         super(name);
      public void run () {
         Trace.setThreadName(getName());
         for (int i=0; i<10; ++i) {
            int nap = (int)(Math.random()*100);
            Trace.event(100,nap);
            try {
               Thread.sleep(nap);
            } catch (InterruptedException e) {}
            Trace.event(101);
      }
   }
   public static void main (String args[]) {
      Trace.begin("data");
      new MyThread("Solo").start();
      new MyThread("Trinil").start();
      System.out.println("That was still easy!");
```

The call to Trace.begin() initializes tracing with default parameters.

In the code above, we create a user-defined thread class called MyThread.

The first thing we do in the body of the thread is tell the NightTrace API the name of our thread by calling <code>Trace.setThreadName()</code>. This is a convenience, but important, so we can subsequently determine in NightTrace which thread logged a specific trace point by using its name, instead of an integer thread ID which changes from run to run and cannot be predicted.

In each iteration of the loop in the run() routine, each thread will sleep for a random amount of time, surrounded by a pair of trace events with ID values of 100, and 101, respectively. When logging event ID 10, we also have chosen to log a string argument which describes the amount of time we will request to sleep.

The main java routine creates two instances of MyThread and names them "Solo" and "Trinil", in honor of Java Man, discovered in 1891 by Eugene Dubois.


The following commands could be used to build and execute the application:

```
$ javac -classpath /usr/lib:. ThreadedTracing.java
$ ntraceud data
$ java -classpath /usr/lib:. ThreadedTracing
That was still easy!
$ ntraceud -q data
```

#### **NOTE**

Some versions of Java require you to explicitly place /usr/lib in your LD\_LIBRARY\_PATH environment variable. If you get an error when invoking the java class that mentions java.lang.UnsatisfiedLinkError, then try setting LD\_LIBRARY\_PATH to include /usr/lib.

If we now invoke the NightTrace analysis program, ntrace(1), we will see a display which breaks down the trace events on a per-thread basis, as seen in the rows in the center of the figure below.



## **Rare Occurrence Example**

This example uses demonstrates how one might use buffer-wrap mode to catch a rare occurrence of bug.

```
#include <ntrace.h>
#include <time.h>
#include <stdio.h>
void
incredibly_rare_event (void)
   trace_event(2);
   time_t t t = time(0);
   printf ("a.out: Badness occurred at %s", asctime(localtime(&t)));
   trace_flush();
main()
   volatile double x = 0.0;
   int j;
   unsigned i = 0;
   trace_begin ("data",0);
   for (;;) {
      trace_event_arg (1,i);
      for (j=0; j<100; ++j) x = x * x;
      if ((++i % 10000000) == 0) {
         incredibly_rare_event();
   }
}
```

The call to trace\_begin() initializes tracing with default parameters.

We call trace\_event\_arg() with the loop iterator for each iteration of the outer loop to simulate logging useful data.

When the process detects something has gone wrong, it logs a new trace event and then flushes the trace buffers with a call to trace\_flush().

The following commands could be used to compile, link, and execute the application using command-line daemon execution:

The program continues to execute despite the detection of the condition, but on each detection, the history of events that were still in the trace shared memory buffers are written to the output file.

The latter invocation of **ntraceud** to stop the daemon, indicates is should not wait for the logging application to complete.

We can now analyze the data from the two occurrences of the problematic event.

Alternatively, we could have started the program without an **ntraceud** daemon running, and subsequently used the **ntrace**, the NightTrace GUI to start a daemon, and immediately analyze the trace data as more data is being collected.

# **CUDA Example**

This small example shows how to log trace events in user code that is executed by an NVIDIA Graphical Processing Unit, using NVIDIA's CUDA API.

```
#include <ntrace_cuda.h>
#include <ntrace_cuda_device.h>
 _global___ void MyKernel (float *result, ntrace_cuda_handle*h)
  int v = threadIdx.x * threadIdx.y;
  ntrace_cuda_event(h,47,v%2);
  result[v] = v;
int main()
  \dim 3 \text{ threads}(8,4,2);
  dim3 grid(16,16,2);
  float * result;
  cudaMalloc(&result, sizeof(float)*16*16*2*8*4*2);
  ntrace_cuda_context ncc = ntrace_cuda_begin("user-data");
  MyKernel<<<grid,threads>>>(result,ntrace_cuda_sync(ncc));
  cudaThreadSynchronize();
  ntrace_cuda_flush(ncc);
}
```

This overly simply example shows how to use the basic NightTrace CUDA API calls to log trace events in code executed by the GPU.

In the main function (code executed by the CPU): we initate the NightTrace session by calling ntrace\_cuda\_begin; we launch our kernel (the line that starts with MyKernel<<<) and pass the return value of ntrace\_cuda\_sync; we wait for the kernel to complete (call to cudaThreadSynchronize); finally we call ntrace\_cuda\_flush to allow the events to be collected by a NightTrace daemon.

When the kernel is launched, the CPU continues on to the next statement (cudaThread-Synchronize) and the GPU begins to execute MyKernel in parallel using its many cores.

You can see that for every invocation of MyKernel, we log a single trace event with an ID value of 47, and an integer argument with the value 0 or 1.

The following commands can be used to compile, link, and execute the program, and then list the generated trace events:

```
$ nvcc \ --gencode=arch=compute_11,code=\"sm_11,compute_11\" \
--gencode=arch=compute_20,code=\"sm_20,compute_20\" \
--compiler-options -DUNIX -g -G -I/usr/include \
-c mycode.cu
$ cc -o mycode mycode.o -lcuda_rt -lntrace_cuda -lntrace
$ ntraceud user-data # This starts a NightTrace daemon
$ ./mycode
$ ntraceud -q user-data # This stops the NightTrace daemon
$ ntrace --listing user-data
0: cpu=?? 47 pid=mycode thr=main time=0.0000000000 argl=0x0 CUDA
thread(0,0,0)/block(14,0,0) on GPU lane=0 warp=15 sm=0 at time=480290
1: cpu=?? 47 pid=mycode thr=main time=0.0000000000 argl=0x0 CUDA
thread(1,0,0)/block(14,0,0) on GPU lane=0 warp=15 sm=0 at time=480290
...
```

Ε

# NightTrace Analysis API Examples

The following programs are given as examples of how to use the NightTrace Analysis Application Programming Interface (see "Using the NightTrace Analysis API" on page 16-1).

#### NOTE

The source files for these programs are installed in /usr/lib/NightTrace/examples.

- list (see "list" on page E-2)

This program simply lists each NightTrace event using a simple main loop to position to the next event.

- **search** (see "search" on page E-4)

This program utilizes the callback features of the API to locate and describe all events which satisfy a specified condition.

- watchdog (see "watchdog" on page E-6)

This program illustrates how to monitor a certain condition in real-time and then act upon it accordingly.

- **ptime** (see "ptime" on page E-9)

This program illustrates how to use the NightTrace GUI to export complex conditions and states to a source file which uses the API.

- **browse** (see "browse" on page E-12)

This program contains a collection of code segments which might be useful for reference.

- **detect** (see "detect" on page E-23)

This program monitors live kernel trace data looking for a user-specified event in the form of a NightTrace expression.

## list

### **Usage**

```
./list trace_data_file
```

This program simply lists each NightTrace event using a simple main loop to position to the next event.

See "NightTrace Analysis API Examples" on page E-1 for other programs demonstrating the capabilities of the NightTrace Analysis Application Programming Interface.

### list.c

```
#include <unistd.h>
#include <stdlib.h>
#include <string.h>
#include <stdio.h>
#include <ntrace_analysis.h>
// Simple example to list all events in a trace data file
// Usage: ./list data_file
static void print (tr_t t, tr_offset_t offset);
int
main (int argc, char * argv[])
  tr_t t;
  tr_string_node_t * list;
  tr_offset_t offset;
  int i;
  int errs;
   if (argc != 2) {
     printf ("Usage: list data_file\n");
     exit(1);
   }
   t = tr_init();
  tr_open_file(t,argv[1]);
   errs = tr_error_check(t,&list);
   if (errs) {
      for (i=0; i<errs; ++i)
         printf (" %s (%s)\n", list[i].value, strerror(list[i].item));
     exit(1);
```

```
for (;;) {
     offset = tr_next_event(t);
     if (offset == TR_EOF) break;
     print(t, offset);
   }
   tr_close(t);
   tr_destroy(&t);
}
static
void
print (tr_t t, tr_offset_t offset)
   int i;
   printf ("%5d pid=%5d id=%4d %8.9f nargs=%1d",
            offset,
            tr_pid(t),
            tr_id(t),
            tr_time(t),
            tr_nargs(t));
   for (i=1; i<=tr_nargs(t); ++i) {</pre>
     printf (" %5d", tr_arg_int(t,i));
  printf ("\n");
}
```

## search

### **Usage**

```
./search trace_data_file "NightTrace_Expression"
```

This program utilizes the callback features of the API to locate and describe all events which satisfy the specified condition.

The *NightTrace\_Expression* is a valid NightTrace expression (see "NightTrace allows you to use expressions to aid in the analysis of trace data." on page 15-1) enclosed by double quotes.

The **search** program builds a *condition* object and assigns the specified expression to that condition. It then registers a callback to the print function for every event that satisfies the *condition*. It then invokes the iterate function to process the entire *trace\_data\_file*.

To call the **search** program with a *trace\_data\_file* named **my\_trace\_data** and the *NightTrace\_Expression*:

```
num_args>1 && arg2==0
```

you would issue the following command:

```
./search my_trace_data "num_args>1 && arg2==0"
```

See "NightTrace Analysis API Examples" on page E-1 for other programs demonstrating the capabilities of the NightTrace Analysis Application Programming Interface.

## search.c

```
#include <stdlib.h>
#include <stdio.h>
#include <string.h>
#include <ntrace_analysis.h>

// Simple example to search for all events in a trace data file
// which satisfy the specified condition.

// Usage: ./search data_file "expression"

// Example: ./search data_file "num_args>1 && arg2 == 1"

static void print (tr_t, tr_cond_t c, tr_offset_t, int, void *, int *);

int
main (int argc, char * argv[])
{
   tr_t t;
   tr_string_node_t * list;
   tr_offset_t offset;
```

```
tr_cond_t cond;
   int i;
   int errs;
   if (argc < 3) {
      printf ("Usage: search data_file \"expression\"\n");
      exit(1);
   }
   // Initialize the API and open the input data file
   t = tr_init();
   tr_open_file(t,argv[1]);
   // Create a condition using the specified expression and
   // register a callback for it.
   cond = tr_cond_create(t, "search");
   tr_cond_expr_and(t,cond,argv[2]);
   tr_cond_cb(t,cond,print,0);
   // Ensure all is copasetic
   errs = tr_error_check(t,&list);
   if (errs) {
      for (i=0; i<errs; ++i)</pre>
         printf (" %s (%s)\n", list[i].value, strerror(list[i].item));
      exit(1);
   }
   // Process all events
   tr_iterate(t);
   tr_close(t);
}
static
void
print (tr_t
                t,
       tr_cond_t c,
       tr_offset_t offset,
                 occurrence,
                * context,
       void
       int
                * disable)
   int i;
   printf ("%5d pid=%5d id=%4d %8.9f nargs=%1d",
            offset,
            tr_pid(t),
            tr_id(t),
            tr_time(t),
            tr_nargs(t));
   for (i=1; i<=tr_nargs(t); ++i) {</pre>
     printf (" %5d", tr_arg_int(t,i));
   }
   printf ("\n");
}
```

## watchdog

#### Usage

```
./watchdog cpu_mask
```

This program illustrates how to monitor a certain condition in real-time and then act upon it accordingly.

In this case, the input to the program is the output of a NightTrace kernel daemon. The program watches for any context switches on the CPU specified in *cpu\_mask*.

This test program make use of kernel tracing which is not available on all operating system distributions. See "Kernel Dependencies" on page B-1 for more information.

For simplicity, this program only lists the time at which the context switch occurred and the process being switched in.

This program may be invoked with the following command:

```
ntracekd --stream /tmp/handle | ./watchdog 1
```

or it can be launched from the NightTrace GUI as part of a streaming kernel daemon definition. See "Consumer" on page 8-10 for more information.

See "NightTrace Analysis API Examples" on page E-1 for other programs demonstrating the capabilities of the NightTrace Analysis Application Programming Interface.

## watchdog.c

```
#include <stdlib.h>
#include <stdio.h>
#include <unistd.h>
#include <string.h>
#include <ntrace_analysis.h>

// Example watchdog program; detect context switches on
// shielded CPU

// Usage: ./watchdog cpu_mask

// stdin is assumed to be the output of ntracekd (or watchdog
// was launched from the NightTrace GUI which set stdin to
// daemon output).

static void print (tr_t, tr_cond_t c, tr_offset_t, int, void *, int *);
int
main (int argc, char * argv[])
{
    tr_t t;
```

```
tr_string_node_t * list;
   tr_offset_t offset;
   tr_cond_t cond;
   int i;
   int cpu;
   int errs;
   if (argc != 2) {
      printf ("Usage: ntracekd --stream handle | watchdog cpu_mask\n");
      exit(1);
   if (isatty(0)) \{
      printf ("error: expect stdin to be streaming data from ntracekd\n");
      exit(1);
   }
   cpu = atoi(argv[1]);
   if (cpu == 0) {
      printf ("error: cpu_mask must be a MASK of CPU bits\n");
      exit(1);
   }
   // Initialize the API
   t = tr_init();
   // Create a condition detecting context switches on specified CPU
   // and register a callback for it.
   cond = tr_cond_create(t, "switch");
   tr_cond_id(t,cond,4150);
   tr_cond_cpu(t,cond,cpu);
   tr_cond_cb(t,cond,print,0);
   // Open the input stream
   tr_open_stream(t, 0, 1024*1024*50, 0);
   // Ensure all is copasetic
   errs = tr_error_check(t,&list);
   if (errs) {
      for (i=0; i<errs; ++i)</pre>
         printf (" %s (%s)\n", list[i].value, strerror(list[i].item));
      exit(1);
   }
   // Process all events
   tr_iterate(t);
   errs = tr_error_check(t,&list);
   if (errs) {
      for (i=0; i<errs; ++i)</pre>
         printf (" %s (%s)\n", list[i].value, strerror(list[i].item));
   }
   tr_close(t);
}
static
void
print (tr_t
                   t,
       tr_cond_t
       tr_offset_t offset,
```

```
int occurrence,
    void * context,
    int * disable)
{
    int pid = tr_pid(t);
    char * name = tr_process_name(t);
    if (!name) name = "<unknown>";
    printf ("context switch: %8.9f %5d %s\n", tr_time(t), pid, name);
}
```

## ptime

This program illustrates how to use the NightTrace GUI to export complex conditions and states to a source file which uses the API.

### **Usage**

```
./ptime kernel_trace_file
```

In this case, **ptime.c** contains the main program and the callback functions; we use the GUI to export an initialization routine which defines the states and registers the callbacks.

A NightTrace session file, **ptime.session**, is provided in this directory which contains a definition of a state called ksoftirgd.

In order to build the program ptime, you need to invoke NightTrace and export the state:

```
ksoftirgd
```

to generate the source file **export\_0.c**.

1. Issue the following command:

```
ntrace ptime.session
```

- From the NightTrace menu, select the Export API Source File... menu item.
- 3. Select ksoftingd in the list.
- 4. Clear checkbox for Generate main() function.
- 5. Clear checkbox for Generate callback function definitions.
- 6. Click on Export Selected.
- 7. Click on Close.
- 8. From the NightTrace menu, select Exit Immediately.

### **NOTE**

Optionally, NightTrace can create a main program and callback bodies for you as well.

The ksoftirgd state tracks when the process **ksoftirgd/0** is active on CPU 0.

The **ptime** program simply collects the durations of each occurrence of the state and prints the total time at the end of the program.

To generate the *kernel trace file*, issue the following command:

```
ntracekd --wait=5 /tmp/kernel-data
```

You may then invoke the program:

```
./ptime /tmp/kernel-data
```

See "NightTrace Analysis API Examples" on page E-1 for other programs demonstrating the capabilities of the NightTrace Analysis Application Programming Interface.

## ptime.c

```
#include <unistd.h>
#include <stdlib.h>
#include <stdio.h>
#include <string.h>
#include <ntrace_analysis.h>
// Example to calculate the amount of time the Kernel daemon
// ksoftirqd/0 spends processing on the CPU.
// The purpose of this example is to demonstrate use of the
// NightTrace GUI export feature to aid in forming conditions,
// states, and registering callbacks.
// Usage: ./ptime kernel_data_file
static double time = 0.0;
extern void tr_session_init(tr_t);
int
main (int argc, char * argv[])
  tr_t t;
  tr_string_node_t * list;
  tr_offset_t offset;
  tr_cond_t cond;
   int i;
   int errs;
   if (argc < 2) {
      printf ("Usage: search data_file\n");
      exit(1);
   }
   // Initialize the API and open the input data file
   t = tr_init();
   errs = tr_open_file(t,argv[1]);
   // Invoke the initialization function generated by the
   // NightTrace GUI to form string tables, conditions,
   // expressions, and register callbacks.
   if (!errs) {
```

```
tr_session_init(t);
      tr_activate(t);
   }
   // Ensure all is copasetic
   errs = tr_error_check(t,&list);
   if (errs) {
      for (i=0; i<errs; ++i)</pre>
         printf (" %s (%s)\n", list[i].value, strerror(list[i].item));
      exit(1);
   }
   // Process all events
   tr_iterate(t);
   tr_close(t);
   tr_destroy(&t);
   printf ("ksoftirqd/0 used %9.8f seconds of CPU time\n", time);
}
void
ksoftirqd_start_func (tr_t input, tr_state_t state,
                      tr_offset_t offset, int occurrence,
                      void * context, int * disable) {
}
void
ksoftirqd_end_func (tr_t input, tr_state_t state,
                    tr_offset_t offset, int occurrence,
                    void * context, int * disable) {
   tr_state_info_t info;
   tr_state_info(input,state,&info);
   time += info.duration;
}
```

## browse

## Usage

```
./browse [-e expression] data_file
```

This program contains a collection of code segments which might be useful for reference.

It implements a simple command-line oriented browser.

#### **NOTE**

The **browse** program is included mainly for reference; the Night-Trace GUI is <u>much</u> more suitable for interactive browsing.

See "NightTrace Analysis API Examples" on page E-1 for other programs demonstrating the capabilities of the NightTrace Analysis Application Programming Interface.

#### browse.c

```
#include <unistd.h>
#include <stdio.h>
#include <string.h>
#include <stdlib.h>
#include "ntrace_analysis.h"
// This test program implements a command-line orienter
// browser. It is provided because some of the code
// segments may be useful for reference. The NightTrace
// GUI tool is *much* more suitable for interactive browsing.
tr_t t;
static char buffer[128];
static char * _c;
static FILE * input;
#define get_line(x) \
  write (1, x, sizeof(x)); \setminus
   _c = fgets(buffer,sizeof(buffer),input); \
  _c[strlen(_c)-1] = '\0'
static
void
print (tr_offset_t offset)
   int i;
```

```
double time = tr_time(t);
   char * process = tr_process_name(t);
   if (process && process[0]) {
      printf ("%5d pid=%s %3d %8.9f %1d", offset, process, tr_id(t), time,
tr_nargs(t));
   } else {
      printf ("%5d pid=%d %3d %8.9f %1d", offset, tr_pid(t), tr_id(t), time,
tr_nargs(t));
   for (i=1; i<=tr_nargs(t); ++i) {
      printf (" %5d", tr_arg_int(t,i));
   printf ("\n");
}
static
biov
print_event (tr_offset_t offset)
   int i;
   double time = tr_time_(t,offset);
   \label{eq:continuity} \texttt{printf} \ (\texttt{"\$5d} \ \texttt{\$5d} \ \texttt{\$3d} \ \texttt{\$8.9f} \ \texttt{\$1d"}, \ \texttt{offset}, \ \textbf{tr\_pid\_}(\texttt{t,offset}) \,,
                                        tr_id_(t,offset), time, tr_nargs_(t,offset));
   for (i=1; i<=tr_nargs_(t,offset); ++i) {</pre>
      printf (" %5d", tr_arg_int_(t,i,offset));
   printf ("\n");
}
typedef enum { CMD_LIST,
                 CMD_NEXT,
                 CMD_PREV,
                CMD_SEEK,
                CMD_SEARCH,
                CMD_COPY_FILE,
                CMD_STATE,
                CMD_CONDITION,
                CMD_CALLBACK,
                 CMD_ITERATE,
                 CMD_REWIND,
                 CMD_QUIT,
                 CMD_UNKNOWN }
   commands;
static commands last_cmd = CMD_QUIT;
static int cond1 (tr_t t, tr_offset_t offset, void * v)
   return tr_nargs_(t,offset) > 0 && tr_arg_int_(t,1,offset) > 10;
static int cond2 (tr_t t, tr_offset_t offset, void * v)
   return tr_time_(t,offset) < 0.03712;</pre>
static int cond3 (tr_t t, tr_offset_t offset, void * v)
   return tr_nargs_(t,offset) > 0 && tr_arg_int_(t,1,offset) > 10;
```

```
static int cond4 (tr_t t, tr_offset_t offset, void * v)
  return tr_nargs_(t,offset) == 4;
static int cond5 (tr_t t, tr_offset_t offset, void * v)
  return tr_id_(t,offset) % 2 == 0;
static
void
event_cb (tr_t t, tr_cond_t c, tr_offset_t offset,
         int count, void * context, int * disable)
  printf ("event callback function\n");
  print(offset);
}
static
void
state_cb (tr_t t, tr_state_t s, tr_offset_t offset, int count, void * context,
         int * disable)
  tr_state_info_t info;
  print (offset);
  printf ("state callback function\n");
  tr_state_info (t, s, &info);
  printf (" active
                           = %d\n", tr_state_active(t,s));
  printf ("
              start_offset = %d\n", info.start_offset);
  printf ("
              end_offset = %d\n", info.end_offset);
  printf ("
              gap
                           = %12.9fs\n", info.gap);
  printf ("
                           = %12.9fs\n", info.duration);
              duration
static
commands
get_cmd (void)
  get_line(": ");
   if (strcmp(buffer,"") == 0) {
     return last_cmd;
   } else if (!strcmp(buffer, "list")) {
     return last_cmd=CMD_LIST;
   } else if (!strcmp(buffer, "next")) {
     return last_cmd=CMD_NEXT;
   } else if (!strcmp(buffer, "prev")) {
     return last_cmd=CMD_PREV;
   } else if (!strcmp(buffer, "seek")) {
     return last_cmd=CMD_SEEK;
   } else if (!strcmp(buffer, "search")) {
     return last_cmd=CMD_SEARCH;
   } else if (!strcmp(buffer, "copy_file")) {
     return last_cmd=CMD_COPY_FILE;
   } else if (!strcmp(buffer, "iterate")) {
     return last_cmd=CMD_ITERATE;
   } else if (!strcmp(buffer, "state")) {
```

```
return last_cmd=CMD_STATE;
   } else if (!strcmp(buffer, "condition")) {
      return last_cmd=CMD_CONDITION;
   } else if (!strcmp(buffer, "callback")) {
      return last_cmd=CMD_CALLBACK;
   } else if (!strcmp(buffer, "rewind")) {
      return last_cmd=CMD_REWIND;
   } else if (!strcmp(buffer, "quit")) {
      return last_cmd=CMD_QUIT;
   } else {
      return last_cmd=CMD_UNKNOWN;
}
static
void
do_search (void)
   tr_cond_t c;
   tr_dir_t dir;
   tr_offset_t o;
   get_line ("forward or backward (f/b): ");
   if (buffer[0] == 'b') {
      dir = tr_backward;
   } else {
      dir = tr_forward;
   get_line ("enter name of condition to search for: ");
   c = tr_cond_find(t,buffer);
   if (c == TR_NO_COND) {
      printf ("could not locate condition \"%s\"\n", buffer);
      return;
   }
   o = tr_search (t, dir, c);
   if (o == TR_EOF) {
      printf ("Event Not Found\n");
   } else {
      print_event(o);
}
static char * expression;
static
void
prime (void)
   tr_cond_t c1, c2, c3, c4, c5;
   char * err;
   c1 = tr_cond_create(t,"_cond1");
   tr_cond_func_and(t,c1,cond5,0);
   c2 = tr_cond_create(t,"_cond2");
   tr_cond_func_and(t,c2,cond4,0);
   c3 = tr_cond_create(t, "_cond3");
```

```
tr_cond_id_range (t, c3, 50, 60);
   c4 = tr_cond_create(t,"_test");
   err = tr_cond_expr_and(t,c4,expression);
   if (err) {
      printf ("%s\n", err);
   c5 = tr_cond_create(t, "_cond5");
  tr_cond_pid_name(t,c5,"foo");
  tr_activate(t);
#if 0
   {
      char * errs;
      int i;
      tr_error_clear(t);
      tr_session_init(t);
      errs = tr_error_check(t,&list);
      if (errs) {
         printf ("tr_session_init() failed:\n");
      for (i=0; i<errs; ++i)</pre>
         printf (" %s (%s)\n", list[i].value, strerror(list[i].item));
   }
#endif
}
static
void
def_state (void)
  tr_state_t s;
  int error;
  int i;
  int low[2], high[2];
  tr_cond_t cond[2];
   for (i=0; i<2; ++i) {
      const char * prompt = (i ? "end: " : "start: ");
      write (1, prompt, strlen(prompt));
      get_line ("enter low bound of id range: ");
      low[i] = atoi(buffer);
      get_line ("enter high bound of id range: ");
      high[i] = atoi(buffer);
   }
   for (i=0; i<2; ++i) {
      const char * prompt = (i ? "end: " : "start: ");
      write (1, prompt, strlen(prompt));
      get_line ("enter condition name or <enter> for none: ");
      if (buffer[0] == '\0') {
         cond[i] = TR_NO_COND;
      } else {
         cond[i] = tr_cond_find(t,buffer);
         if (cond[i] == TR_NO_COND) {
            printf ("no such condition\n");
```

```
return;
         }
      }
   }
   get_line ("enter name of state to be defined: ");
   s = tr_state_create (t, buffer);
   if (s == TR_NO_STATE) {
      printf ("state creation failed\n");
      return;
   }
   error = tr_state_start_id_range(t,s,low[0],high[0]);
   error |= tr_state_end_id_range(t,s,low[1],high[1]);
   if (cond[0] != TR_NO_COND) {
      tr_state_start_cond(t,s,cond[0]);
   if (cond[1] != TR_NO_COND) {
      tr_state_end_cond(t,s,cond[1]);
   if (error) {
      printf ("configuration of state failed\n");
      return;
   }
   tr_activate(t);
   printf ("state \"%s\" has been successfully configured\n", buffer);
}
static
void
def_condition (void)
   tr_cond_t c;
   int low, high;
   int cpu;
   int pid;
   int error;
   int and ;
   tr_cond_func_t func;
   get_line ("enter low bound of id range or <enter> for none: ");
   low = atoi(buffer);
   get_line ("enter high bound of id range or <enter> for none: ");
   high = atoi(buffer);
   get_line ("enter cpu bias or <enter> for none: ");
   cpu = atoi(buffer);
   get_line ("enter pid or <enter> for none: ");
   pid = atoi(buffer);
   get_line ("enter name of condition to be defined: ");
   c = tr_cond_create (t, buffer);
   if (c == TR_NO_COND) {
      printf ("condition creation failed\n");
      return;
```

```
error = 0;
   if (low) error |= tr_cond_id_range(t,c,low,high);
   if (cpu)
                    tr_cond_cpu(t,c,cpu);
   if (pid) error |= tr_cond_pid(t,c,pid);
   for (;;) {
      get_line ("enter \"and\", \"or\", or <enter> for function conditions: ");
      if (buffer[0] == '\0') break;
      else if (!strcmp(buffer, "and")) and_ = 1;
      else if (!strcmp(buffer, "or")) and_ = 0;
      else {
         printf ("illegal response\n");
         return;
      get_line ("enter condition callback function or expression: ");
      func = NULL;
           if (!strcmp(buffer, "cond1")) { func = cond1; }
      else if (!strcmp(buffer, "cond2")) { func = cond2; }
      else if (!strcmp(buffer, "cond3")) { func = cond3; }
      else if (!strcmp(buffer, "cond4")) { func = cond4; }
      else if (!strcmp(buffer, "cond5")) { func = cond5; }
      else func = NULL;
      if (func == NULL) {
         char * err;
         if (and_)
            err = tr_cond_expr_and(t,c,buffer);
            err = tr_cond_expr_or(t,c,buffer);
         if (err) {
            printf ("invalid expression:\n%s\n",err);
            error = 1;
      } else {
         if (and_) {
            error |= tr_cond_func_and(t,c,func,0);
         } else {
            error |= tr_cond_func_or(t,c,func,0);
      }
   }
   if (error) {
      printf ("configuration of condition failed\n");
      printf ("condition has been successfully configured\n");
  tr_activate(t);
static
void
destroy_callback (void)
  tr_cb_t id;
  get_line ("enter callback id to cancel: ");
  id = atoi(buffer);
```

}

```
printf ("cancelling callback with ID %d\n", id);
   tr_cancel_cb (t, id);
}
static
biov
def_callback (void)
   tr_cond_t c;
   tr_state_t s;
  int is_state;
   int id;
   tr_state_action_t a;
  get_line ("create or destroy a callback? (c/d) [c]: ");
  if (buffer[0] == 'd') {
     destroy_callback();
     return;
   }
   get_line ("state or condition callback? (s/c): [c]: ");
   is_state = buffer[0] == 's';
  if (is_state) {
     get_line ("enter state callback trigger: start, end, active, inactive: ");
          else if (!strcmp(buffer, "end"))
                                        a = tr_state_end_action;
     else if (!strcmp(buffer, "active"))     a = tr_state_active_action;
     else if (!strcmp(buffer, "inactive")) a = tr_state_inactive_action;
        printf ("illegal response\n");
        return;
     get_line ("enter state name: ");
     s = tr_state_find(t,buffer);
     if (s == TR_NO_STATE) {
        printf ("unable to locate state \"%s\"\n", buffer);
        return;
     id = tr_state_cb (t, s, a, state_cb, 0);
   } else {
     get_line ("enter condition name: ");
     c = tr_cond_find(t,buffer);
     if (c == TR_NO_COND) {
        printf ("unable to locate condition \"%s\"\n", buffer);
        return;
     id = tr_cond_cb (t, c, event_cb, 0);
   }
   if (id == TR_NO_CB) {
     printf ("callback registration failed\n");
     printf ("callback for %s \"%s\" was successfully registered as id %d\n",
             (is_state ? "state" : "condition"), buffer, id);
   }
int
```

```
main (int argc, char * argv[])
   int status;
   int i;
   int done = 0;
   int arg = 1;
   int streaming = 0;
   int cmd;
   tr_offset_t o;
   char buffer[100];
   expression = "true";
   for (;;) {
      if (argc < 2) {
         printf ("usage: %s [options] trace_data_file\n", argv[0]);
         printf ("options:\n"
                  " -e expr (expr)
                                         Create an expression named \"_test\"\n"
                                         using \mbox{"expr}\mbox{" as the expression}\mbox{"}
                  "\n"
                  "If \t^{"trace\_data\_file\"} is \t^{"-\"}, then we assume stdin\t^{"}
                  "is a stream from a NightTrace daemon\n");
         exit(1);
      }
      if (argv[arg][0] == '-') {
         if (!strcmp(argv[arg],"-e")) {
            --argc;
            expression = argv[++arg];
         } else if (!strcmp(argv[arg],"-")) {
            streaming = 1;
            break;
         } else {
            argc = 0;
      } else {
         break;
      }
      ++arg;
      --argc;
   t = tr_init();
   if (streaming) {
      input = fopen("/dev/tty", "r");
      //status = tr_open_stream(t,0,1024*1024*20, TR_STREAM_SAVE);
      status = 1;
   } else {
      input = stdin;
      status = tr_open_file(t,argv[arg]);
   if (status) {
      tr_string_node_t * list;
      int errs;
      printf ("tr_open_*() failed:\n");
      errs = tr_error_check(t,&list);
      for (i=0; i<errs; ++i)</pre>
         printf (" %s (%s)\n", list[i].value, strerror(list[i].item));
      exit(1);
```

```
}
prime();
cmd = -1;
while (!done) {
   switch (cmd) {
   case CMD_LIST:
      for (;;) {
         o = tr_next_event(t);
         if (o == TR_EOF) break;
         print(o);
      break;
   case CMD_NEXT:
      o = tr_next_event(t);
      print(o);
      break;
   case CMD_PREV:
      o = tr_prev_event(t);
      print(o);
      break;
   case CMD_SEEK:
      printf ("Input event offset of interest: ");
      fflush (stdout);
      o = atoi(fgets(&buffer[0],sizeof(buffer),input));
      printf ("seeking to d\n", o);
      o = tr_seek(t,o);
      print(o);
      break;
   case CMD_SEARCH:
      do_search();
      break;
   case CMD_COPY_FILE:
      {
         tr_cond_t c;
         c = tr_cond_find(t, "copy");
         if (c == TR_NO_COND) {
            printf ("you must first define a condition called \"copy\"\n");
         } else {
            get_line ("Enter output file name: ");
            if (tr_copy_input(t,buffer,c,0666)) {
               printf ("failed to write events\n");
            }
         }
         break;
      }
   case CMD_STATE:
      def_state();
      break;
```

```
case CMD_CONDITION:
      def_condition();
      break;
   case CMD_CALLBACK:
      def_callback();
      break;
   case CMD_ITERATE:
      tr_iterate(t);
      break;
   case CMD_REWIND:
      (void) tr_seek(t,-1);
      break;
   case CMD_QUIT:
      done = 1;
      continue;
      //break;
   default:
      printf ("Commands:\n"
                 list\n"
                 next\n"
                 prev\n"
                  seek\n"
                  search\n"
                  copy_file\n"
                  state\n"
                  condition\n"
                  callback\n"
                  iterate\n"
                  rewind\n"
                  quit\n");
   }
   cmd = get_cmd();
} while (!done);
tr_close (t);
tr_destroy (&t);
return 0;
```

}

## detect

#### Usage

./detect expression

This program monitors live kernel trace data looking for a user-specified event in the form of a NightTrace expression. When the event is detected, it writes out a kernel trace data file which contains the detected event as well as 500 events previous to it. It then terminates.

This program illustrates how to monitor a certain condition in real-time and then save trace data prior to and including the event when the condition was detected.

This would be useful in order to collect kernel trace data continually until some complex event occurs - then to save the relevant kernel data for later analysis.

This program may be invoked with the following command:

```
ntracekd --stream /tmp/handle | ./detect "process_name==\"ntracekd\""
```

or it can be launched from the NightTrace GUI as part of a streaming kernel daemon definition. See "Consumer" on page 8-10 for more information.

In this case, the expression provided instructs the program to look for the first kernel event associated with the daemon that is collecting the kernel data and sending it to our ./detect program. This example is used simply for demonstration - it is not very interesting in and of itself.

After executing has stopped, a kernel trace data file called copy\_current\_input.data has been written to the current working directory. You can invoke ntrace on that data file to view the 500 events just prior to the first ntracekd event:

ntrace copy current input.data

#### NOTE

There may be fewer than 500 events saved since we may encounter **ntracekd** almost immediately.

See "NightTrace Analysis API Examples" on page E-1 for other programs demonstrating the capabilities of the NightTrace Analysis Application Programming Interface.

### detect.c

```
#include <stdlib.h>
#include <stdio.h>
#include <unistd.h>
#include <string.h>
#include <ntrace_analysis.h>
// This program detects the first event where the expression is true
// and saves the desired number of events to the output file.
static char* detect_usage =
"Usage: \n"
"\n"
      ntracekd --stream output | ./detect 500 \"NightTrace Expression\" \n"
"\n"
           This will detect the first event where the condition is met \n"
            and copy the last 500 events prior to that event to the output \n"
            file. Tracing will be stopped at that point. \n"
"\n"
      ntracekd --stream output | ./detect --bracket 500 \"NightTrace Expression\"
\n"
"\n"
           This will detect the first event where the condition is met \n"
          and copy the 500 events prior to and after that event to the \n"
           output file. Tracing will be stopped at that point. \n"
"\n"
// IMPORTANT: stdin is assumed to be the output of ntracekd (or detect was
// launched from the NightTrace GUI which set stdin to daemon output).
// Callbacks
static void copy_input_range_cb
  (tr_t
             t,
  tr_state_t state,
  tr_offset_t offset,
             occurrence,
           * context,
   void
            * disable);
   int
static void copy_current_input_cb
  (tr_t
          t,
  tr_state_t state,
  tr_offset_t offset,
  int
              occurrence,
  void
           * context,
   int
           * disable);
static int range = 0;
int
main (int argc, char * argv[])
```

```
{
  tr_t t;
  tr_cond_t user;
  tr_cond_t start;
  tr_cond_t filter;
  tr_state_t state;
  int copy_range = 0;
  int copy_current = 0;
  char option [1024];
  char range_s [1024];
  char expr [1024];
  if (isatty(0)) {
      printf ("error: expect stdin to be streaming data from ntracekd\n");
      exit(1);
  }
  if ( argc == 3 ) {
     sprintf(option,"%s",argv[1]);
     if (!strcmp(option,"--bracket")) {
      printf(detect_usage);
      exit (1);
     }
     sprintf(expr,"%s",argv[2]);
     sprintf(range_s, "%s", argv[1]);
    range = atoi(range_s);
     copy_current = 1;
   } else if ( argc == 4 ) {
     sprintf(option,"%s",argv[1]);
    if (strcmp(option, "--bracket")) {
      printf(detect_usage);
      exit (1);
     sprintf(expr,"%s",argv[3]);
     sprintf(range_s, "%s", argv[2]);
    range = atoi(range_s);
     if (range <= 0) {
      printf("error: range must be greater than zero \verb|\n"|);
     copy_range = 1;
   } else {
    printf(detect_usage);
     exit (1);
   }
  // Initialize the API
  t = tr_init();
  // Create a condition structure representing the users condition
  user = tr_cond_create(t, "user");
  tr_cond_expr_and(t,user,expr);
```

```
// Create a state which starts when the condition true starts (which
   // will be true for the very first event and stops when the user's
   // condtion is met.
  start = tr_cond_create(t, "start");
  tr_cond_expr_and(t, start, "offset>=0");
   state = tr_state_create(t,"state");
  tr_state_start_cond(t,state,start);
   tr_state_end_cond(t,state,user);
   // Create a condition which is true when the state becomes inactive
   filter = tr_cond_create(t, "filter");
   tr_cond_expr_and(t, filter, "state_status(state)==0");
   // Open the input stream
   tr_open_stream(t, 0, 1024*1024*5, 0);
   if (copy_range){
     tr_cond_cb(t,filter,copy_input_range_cb,0);
     tr_iterate(t);
   } else if (copy_current){
     tr_cond_cb(t,filter,copy_current_input_cb,0);
     tr_iterate(t);
   }
   tr_close(t);
}
static
void
copy_input_range_cb
  (tr_t
            t,
  tr_state_t state,
  tr_offset_t offset,
             occurrence,
  void
           * context,
            * disable)
  int
  int i;
  int errs;
  tr_string_node_t * list;
  int start = offset - range;
  int end = offset + range;
  if (start <= 0) start = 0;
  if (end \le 0) end = 1;
  if (start == end) end++;
  tr_copy_input_range(t, "copy_input_range.data",0666,start,end);
  errs = tr_error_check(t,&list);
  if (errs) {
    for (i=0; i<errs; ++i)</pre>
     printf (" %s (%s)\n", list[i].value, strerror(list[i].item));
```

```
*disable = 1;
}
static
void
copy_current_input_cb
 (tr_t
          t,
   tr_state_t state,
   tr_offset_t offset,
            occurrence,
   int
           * context,
   void
           * disable)
   int
{
  int i;
  int errs;
  tr_string_node_t * list;
  int start = offset - range;
  int end = offset;
  if (start <= 0) start = 0;
  if (end \le 0) end = 1;
  if (start == end) end++;
 tr_copy_input_range(t,"copy_current_input.data",0666,start, end);
  errs = tr_error_check(t,&list);
 if (errs) {
   for (i=0; i<errs; ++i)
     printf (" %s (%s)\n", list[i].value, strerror(list[i].item));
 tr_halt(t);
```

F

# **NightTrace Application Illumination Examples**

This appendix provides several examples using the NightTrace Application Illumination.

Most of these examples build on knowledge and experience obtained from the previous example, so it is best to visit them in order.

These examples utilize Application Illumination's command-line interface. The graphical user interface provides all of these capabilities as well a Wizard which guides you through the steps of illuminating an entire program. We recommend reading this appendix first to become comfortable with the concepts before using the graphical interface. Alternatively, just skip this appendix and go directly to the graphical interface and start with the Wizard. To do this, simply invoke the command nlight without any arguments. A tutorial for the graphical interface is available from the NightStar Tutorial manual which can be accessed from the Help menu of nlight (or any other NightStar tool).

Before you begin the examples, think of an illuminator as an opaque object that automatically instruments object code to issue NightTrace events on entry and exit from functions. For the most part, you don't really need to be concerned with what is actually inside an illuminator, just remember that it is associated with some sort of object code and you link parts of an illuminator into your application.

# **Illuminating Some Object Files**

Often you may have a program which links with some objects files, and you'd like to simply instrument a few of those with NightTrace events.

All you need to do is to create an illuminator using the compiled object files as input and build it -- the object files are not modified at all. Then you can link your application that uses those object files and simply include the illuminator. When linked, your application will execute <u>exactly</u> the same way it did before, because the illuminator will initially be in a disabled state. There is <u>zero</u> runtime overhead for including an illuminator in your application in the disabled state.

Subsequently, when you need to see trace data for code in those object files, you activate the illuminator and run your program while capturing trace data.

This example uses three simple C source files which are included at the end of this chapter: math.c, work.c, and main.c.

For purposes of this example, assume that <u>at each step</u>, you start in a base directory which contains two directories, **objects** and **progs**, and that you build your application from the **progs** directory which uses object files from the **objects** directory.

To get the most benefit from this example, follow along by executing the steps described below.

 Setup a test area for this example and copy the files into the subdirectories as shown below.

```
mkdir /tmp/example1
cd /tmp/example1
mkdir objects
mkdir progs
# Copy math.c and work.c into objects
# Copy main.c into progs
```

- For this example, assume that the following commands are the usual way in which your object files and program are built.

```
cd objects
cc -g -c math.c work.c
```

#### NOTE:

It is important to compile with the **-g** option, which instructs the compiler to generate debug information for use by debuggers and other tools (like NightTrace Application Illumination!). By default, Application Illumination only operates on functions with debug information. This topic is dicussed in more detail in "Illuminating An API -- Libraries Without Source or Debug Info" on page F-9.

```
cd ../progs
cc -g main.c ../objects/*.o -lm
```

- Create an illuminator for the object files in the **objects** directory.

```
cd ../objects
nlight --create=obj.ai *.o
```

What just happened? A new directory called **obj.ai** was created in the **objects** directory. The object files that you put on the command line were not modified in any way, but they are now registered as being associated with the **obj.ai** illuminator. When the illuminator is built, it will read those object files.

- Build the illuminator.

```
nlight --build=obj.ai
```

- Now link your program as usual, <u>but</u>, add some linker options so that the illuminator is included as well.

```
cd ../progs
cc -g main.c ../objects/*.o -lm \
    $(nlight --gcc ../objects/obj.ai main)
```

#### NOTE:

If you copy and paste the last command from above into a shell, it may not execute properly. Try copying and pasting the characters up until the \ and newline and then copy and past the rest of the characters on the second line before pressing <enter>.

The command above includes an invocation of **nlight** that supplies the required linker options so that the illuminator is included in your program.

Note the specification of the predefined **main** illuminator in the command above. It was included because the program did not previously use the NightTrace Logging API. If your program already uses the NightTrace Logging API (and includes a call to trace\_begin()), you should not include the predefined **main** illuminator.

Now the program **a.out** has the capability to generate trace events, but, as it stands now, the illuminators are inert and have no effect on the program.

 Activate the illuminators so that when you next run your program, you can generate and capture trace data.

```
nlight --illuminate=a.out ../objects/obj.ai=3 main
```

Again, the predefined **main** illuminator was activated as well as the illuminator you built for your object files, because the program did not already use the NightTrace Logging API.

Additionally, notice the =3 notation that was applied to the obj.ai illuminator in the command above. This set the illumination level to three (by default there are three levels: 1-3, which generate increasing levels of event detail). The default illumination level is two.

Now we're ready to capture trace data. There are a variety of ways to capture the data, but for simplicity in instruction, we'll use the command line tool ntraceud.

```
ntraceud trace_file
./a.out
ntraceud --quit trace_file
```

The commands above started a user daemon in the background, executed the illuminated program, and then stopped the user daemon. Alternatively, you might want to capture trace data for a short period while your application is already running.

```
./a.out --forever &
ntraceud --join trace_file
sleep 5
ntraceud --quit-now trace_file
```

Notice the **--join** and **--quit-now** options used above. These are required if you are going to start a daemon for a program which is already running and when you want the daemon to stop before the program terminates.

Why did the commands above specify **trace\_file** as the name of the trace data file to **ntraceud**? That's because that is the default trace data file name used by

the predefined **main** illuminator. You can change that file name when you activate the **main** illuminator, or, if your program already used the NightTrace Logging API, you would have specified the filename that your program passed to the trace begin() call instead.

- Regardless of the **ntraceud** method you chose, you can now see a chronological listing of the function calls and returns associated with the object files you illuminated in the third step (see above), by invoking **ntrace**.

```
ntrace --listing a.out
```

Notice that we simply requested a listing and provided the name of the illuminated executable to **ntrace**. **ntrace** examines the executable and knows how to find the required information from the illuminator in the **objects** directory. Alternatively, you could have specified the trace data file and the meta-information included in the illuminator by hand.

```
ntrace --listing trace_file \
    ../objects/obj.ai/obj.ai.map \
    ../objects/obj.ai/obj.ai_3.fmt
```

In addition to the former method being more convenient, specifying the path to the illuminated program file also allows **ntrace** to translate PC values (for callers of illuminated functions) to routine names with source file and line number details.

The following shows partial output from the **ntrace** commands above -- your results will differ in terms of addresses, PC values, times, and white space expansion:

```
c: cpu=?? ENTER_work pid=a.out thr=main time=0.500641565s
    calling work(how_much_pie=6.28318)
        caller=0x804872b [main() at main.c:19]
        frame=0xbffda258

3: cpu=?? ENTER_calc pid=a.out thr=main time=0.500660731s
    calling calc(angle=6.28318)
        caller=0x80487c8 [work() at work.c:27]
        frame=0xbffda218

4: cpu=?? RETURN_calc pid=a.out thr=main time=0.500661643s
    returning from calc()=-5.30718e-06
        errno=3
```

This is the last portion of this example, but you might want to execute **ntrace** without the **--listing** option to see how the graphical interface presents the same data to you.

In the next example, we'll apply the experience from this example to illuminate a library.

# **Illuminating A Library**

In this example, we'll illuminate a library used by our application instead of object files. The library can be an archive of object files or a shared library (e.g. libcode.so.1).

The concepts and commands involved are actually almost identical to illuminating object files. The following steps assume you're familiar with the example above, "Illuminating Some Object Files" on page F-1, and as such, the steps below have curtailed descriptions.

This example uses the same three simple C source files from the previous example, which are included at the end of this chapter: math.c, work.c, and main.c.

- Setup a test area for this example and copy the files from the previous example directory into the subdirectories as shown below.

```
mkdir /tmp/example2
cd /tmp/example2
mkdir libraries
cp /tmp/example1/objects/*.c libraries
mkdir progs
cp /tmp/example1/progs/*.c progs
```

 For this example, assume that the following commands are the usual way in which your object files and program are built.

```
cd libraries
cc -g -c math.c work.c
ar crv libmylib.a *.o

cd ../progs
cc -g main.c -L../libraries -lmylib -lm
```

 Create an illuminator for the library in the libraries directory and build it.

```
cd ../libraries
nlight --create=lib.ai libmylib.a
nlight --build=lib.ai
```

 Now link your program as usual, <u>but</u>, add some linker options so that the illuminator is included as well.

```
cd ../progs
cc -g main.c -L../libraries -lmylib -lm \
    $(nlight --gcc ../libraries/lib.ai main)
```

- Activate the illuminators so that when you next run the program, you can generate and capture trace data.

```
nlight --illuminate=a.out ../libraries/lib.ai=3 main
```

At this point you're ready to run your program and generate and capture trace events.

See the last portion of the first example, "Illuminating Some Object Files" on page F-1, if you need to see instructions on how to do that.

In the next example, we'll illuminate an entire program.

# **Illuminating An Entire Program**

In this example, we'll illuminate an entire application instead of just a few object files or a library.

The concepts and commands involved are similar to the previous examples in this chapter. The following steps assume you're familiar with the example above, "Illuminating Some Object Files" on page F-1, and as such, the steps below have curtailed descriptions.

It may be more convenient to illuminate an entire program than just some pieces, especially if you don't know specifically what you're looking for.

However, if the program is large, you may not be able to illuminate the entire thing without customizing the illuminator to ignore some unimportant functions (each function is assigned a NightTrace identifier which must be unique, and there are a limited number of these values (~32678)). The next example, "Illuminating A C++ Class -- Excluding Some Functions" on page F-7, deals with customizing an illuminator. For the remainder of this example, we'll just operate on the entire program.

This example differs slightly from the previous examples in that we create a new and separate program file when we illuminate an entire program. The reasoning for that will become clear in the description of the steps below.

This example uses the same three simple C source files from the previous examples, which are included at the end of this chapter: math.c, work.c, and main.c.

- Setup a test area for this example and copy the files from the previous example directory into the subdirectories as shown below.

```
mkdir /tmp/example3
cd /tmp/example3
cp /tmp/example1/objects/*.c .
cp /tmp/example1/progs/*.c .
```

- For this example, assume that the following command is the usual way in which your program is built. Build the program.

```
cc -g *.c -lm
```

- Create an illuminator for the program and build it.

```
nlight --create=prog.ai a.out
nlight --build=prog.ai
```

 Now link <u>a new copy</u> of your program using the same command you use for the original program, <u>but</u>, add some linker options so that the illuminator is included as well and a **-o** option to specify a different program file name.

```
cc -g -o a.outAI *.c -lm \
    $(nlight --gcc prog.ai main)
```

Why did we create a separate program file, called **a.outAI**? Because the illuminator prog.ai requires **a.out** as its input file (and will need that program to exist if it needs to be rebuilt or if **a.out** changes in the future).

It is important to keep the original program file and the illuminated program file separate so that we don't try to illuminate an illuminated program file subsequently!

Activate the illuminators so that when you next run the <u>new</u> program, you can capture trace data.

```
nlight --illuminate=a.outAI prog.ai=3 main
```

At this point you're ready to run your <u>new</u> program file and generate and capture trace events.

See the last portion of the first example, "Illuminating Some Object Files" on page F-1, if you need to see instructions on how to do that, but remember that the <u>new</u> program file is called **a.outAI**, not **a.out**.

In the next example, we'll illuminate functions associated with a C++ class.

# Illuminating A C++ Class -- Excluding Some Functions

Assume that we are only interested in illuminating the code associated with a C++ class.

We could either create an illuminator specifically for the object files which comprise the class or we could illuminate the entire program and customize the illuminator so that it only includes functions related to the C++ class.

The latter method may be more effective because it will include out-of-line instances of inlined class member functions. It also may be simpler to illuminate the program than to try to track down all the object files related to a class's implementation.

The following steps assume you're familiar with the example above, "Illuminating An Entire Program" on page F-6, and as such, the steps below have curtailed descriptions.

Assume that your program **a.out** contains lots of code and includes usage of a C++ class called Classy. This example uses two of the source files from our previous example and additional one, all found at the end of this appendix: math.c, work.c, and classy.c.

- Setup a test area for this example and copy some of the files from the previous example directory into the directory as shown below and copy the classy.c from the back of this chapter into the directory as well.

```
mkdir /tmp/example4
cd /tmp/example4
cp /tmp/example1/objects/*.c .
# Copy classy.c into this directory
```

- For this example, assume that the following command is the usual way in which your program is built. Build the program.

```
g++ -g *.c -lm
```

- Create an illuminator for your program, but add the following options as shown here.

```
nlight --create=prog.ai \
    --xregex='.*' --iregex='.*Classy.*' a.out
```

The first option, --xregex='.\*', instructed nlight to exclude all functions from illumination, effectively giving us a clean regular expression base from which to add back specific functions.

The second option, --iregex='.\*Classy.\*', instructed nlight to include all functions that have the word Classy in their name. Since all C++ functions associated with a class will include the demangled class name in them, this effectively identifies the code associated with your class. Alternatively, you could have specified '.\*Classy::.\*', which would further restrict functions to being actual members of the class (otherwise an unrelated function named AClassy-Function would also match).

- Build the illuminator.

```
nlight --build=prog.ai
```

- Link a new program file with the illuminator, activate the illuminator, and execute the program capturing NightTrace data.

```
g++ -o a.outAI -g *.c -lm \
    $(nlight --gcc prog.ai main)
nlight --illuminate=a.outAI prog.ai=3 main
ntraceud trace_file
./a.outAI
ntraceud --quit trace_file
```

- Invoke **ntrace** and request a summary of all instances of the function Classy::crunch.

```
ntrace --summary=fs:Classy::crunch trace_file \
   prog.ai/*.map
```

Example output from the command in the last step is shown below; your time values will differ and the white space has been compressed for inclusion here.

```
Summary: Classy::crunch Function entry/return states
State Summary Results
Number of states found:
Maximum state duration:
                           0.000027885 at offset: 9
                           0.000015472 at offset: 11
Minimum state duration:
Average state duration:
                           0.000021678
Total of state durations:
                           0.000043357
Number of state gaps found:
0.000000296 at offset: 11
Maximum state gap:
                           0.000000296 at offset: 11
Minimum state gap:
Average state gap:
                           0.00000148
Total of state gaps:
                           0.000000296
```

In the next example, we'll examine a nifty method for illuminating third-party libraries.

# Illuminating An API -- Libraries Without Source or Debug Info

By default, Application Illumination works on the debug information found in object files when they were compiled with the -g option. If you have a third party library without debug information and no source code from which to rebuild it, your illumination options are limited.

You could illuminate the library and instruct **nlight** to illuminate functions without debug information (via the **--do\_nodebug** option), but no argument information will be logged and returns from functions cannot be traced.

An alternative is to illuminate the functions associated with the Application Programming Interface of the library (if one exists).

Typically, such libraries will ship with C/C++ header files which declare the function prototypes of all API functions. The trick is to copy the header file into a dummy source file and turn all function prototypes into dummy function bodies.

The following steps assume you're familiar with the example above, "Illuminating Some Object Files" on page F-1, and as such, the steps below have curtailed descriptions. It also assumes you have built a library as shown in "Illuminating A Library" on page F-5.

Consider the api.h file found at the end of this chapter. We'll use the main.c source file from previous examples and the library we built in the second example ("Illuminating A Library" on page F-5).

- Setup a test area for this example and copy files as shown.

```
mkdir /tmp/example5
cd /tmp/example5
cp /tmp/example2/libraries/libmylib.a .
cp /tmp/example2/progs/main.c .
# Copy api.h into this directory
```

- Strip the library of all debug symbols.

```
strip -g libmylib.a
ls
    api.h libmylib.a main.c
```

We have no simulated a third-party library without debug information or source files to rebuild it, but with a header file which defines the API.

- Create a dummy source file which provides dummy functions for each function in the header file.

```
cat api.h | sed "s/)[ ]*;/){}/" > dummy.c
```

Obviously that command isn't sufficient for header files in general, but for our purposes, it shows how you can fairly easily copy a function prototype and add two braces to create a dummy function body.

- Now compile the dummy source file and illuminate the resultant object.

```
cc -g -c dummy.c
nlight --create=api.ai dummy.o
nlight --build=api.ai
```

- Now build your program as usual, but add the illuminator we created.

```
cc -g main.c -L. -lmylib -lm \
    $(nlight --gcc api.ai main)
nlight --illuminate=a.out api.ai=3 main
```

- Run the program and generate a listing of entry and exit to all API functions declared in the header file.

```
ntraceud trace_file
./a.out
ntraceud --quit trace_file
ntrace --listing a.out
```

The following is an excerpt from such a listing, which includes the API entry and exit points from the library **libmylib.a**, even no there was no debug information in the library.

```
4: cpu=?? ENTER_work pid=a.out thr=main time=0.004399090s
      calling work(how_much_pie=6.28318)
        caller=0x804872b [main() at main.c:19]
        frame=0xbfa834f8
5: cpu=?? ENTER_calc pid=a.out thr=main time=0.004418028s
      calling calc(angle=6.28318)
        caller=0x8048784 [work+52()]
        frame=0xbfa834b8
6: cpu=?? RETURN_calc pid=a.out thr=main time=0.004427885s
     returning from calc()=-5.30718e-06
        errno=2
7: cpu=?? ENTER calc pid=a.out thr=main time=0.004428331s
      calling calc(angle=6.26573)
        caller=0x8048784 [work+52()]
        frame=0xbfa834b8
8: cpu=?? RETURN_calc pid=a.out thr=main time=0.004428825s
     returning from calc()=-0.0174577
        errno=2
```

In the next example, we'll customize an illuminator to log additional information.

# **Customizing an Illuminator -- Logging Extra Information**

This example assumes you are familiar with the concepts of Application Illumination and you have tried or read the previous examples in this chapter.

Customization options include filtering functions for illumination, adjusting the default amount of data logged for aggregate arguments and pointers to such arguments, changing the behavior of illumination levels, or requested that specific global variables be logged with function return events.

This example will do the latter; we'll request that the global variable state be logged on all returns from the function, calc().

This example uses the three simple C source files which were used in Example 1 ("Illuminating Some Object Files" on page F-1) and assumes you are familiar with the setup and procedures described in the example.

 Setup a test area for this example and copy the files into the subdirectories as shown below.

```
mkdir /tmp/example6
cd /tmp/example6
mkdir objects
mkdir progs
cp /tmp/example1/objects/*.c objects
cp /tmp/example1/progs/*.c progs
```

 For this example, assume that the following commands are the usual way in which your object files and program are built.

```
cd objects
cc -g -c math.c work.c

cd ../progs
cc -g main.c ../objects/*.o -lm
```

- Create an illuminator for the object files in the **objects** directory.

```
cd ../objects
nlight --create=obj.ai *.o
```

- Populate the illuminator with function information from its associated object files so that it is easier to customize.

```
nlight --populate=obj.ai
```

At this point the illuminator's configuration file (obj.ai/config.xml) file has an entry for every function that can be illuminated.

- Edit the obj.ai/config.xml file and add the following XML element immediately before the first line which starts with <function.

```
<group name="mygroup">
<variable name="state" />
<level name="3" aggregate_limit="24" />
</group>
```

The group element is a basic means of customizing selected functions, as opposed to making changes that apply globally to the illuminator.

The variable sub-element indicates that the named global variable (state in this case), will be logged with all function return events for functions that are members of the group my\_group.

The level sub-element specifies that when level 3 is active, functions which belong to this group will log up to 24 bytes of data for aggregates (instead of the default limit of 16 bytes).

9. Edit the **obj.ai/config.xml** file, locate the function element for calc, and make that function a member of group my\_group.

The element for function calc should look like the above now. Be sure that its first line does not end in />, but rather just >.

The function element for calc already existed because we populated the illuminator in step 1. It is not strictly necessary to populate the illuminator; you could create the function element manually instead.

 Now build the illuminator, link the application with the illuminator and activate it.

```
nlight --build=obj.ai
cd ../progs
cc -g main.c ../objects/*.o -lm \
    $(nlight --gcc ../objects/obj.ai main)
nlight --illuminate=a.out ../objects/obj.ai=3 main
```

 Now execute the application while capturing the trace data and then create a listing of the traced data.

```
ntraceud trace_file
./a.out
ntraceud --quit trace_file
ntrace --listing a.out
```

The following is an example of a portion of such output, showing the event logged during a return from function calc:

```
6: cpu=?? RETURN_calc pid=a.out thr=main time=0.002270483s
    returning from calc()=-5.30718e-06
    state={
        counter=1,
        last_angle=6.28318,
        last_sine=-5.30718e-06}
    errno=2
```

The graphical interface to **nlight** (invoke **nlight** without any arguments), provides a more convenient way to customize illuminators.

This concludes the example on customizing an illuminator.

## **Tutorial Files**

## main.c

```
int main(int argc, char * argv[])
{
  int forever = 0;
  if (argc > 1 && strcmp(argv[1],"--forever")==0) {
    forever = 1;
  }
  extern double work(double);

  do {
    work(2*3.14159);
    usleep(100000);
  } while (forever);

  return 0;
}
```

## math.c

```
#include <math.h>

typedef struct {
   int   counter;
   double last_angle;
   double last_sine;
} state_t;

state_t state;

double calc (double angle)
{
   state.counter++;
   state.last_angle = angle;
   state.last_sine = sin(angle);
   return state.last_sine;
}
```

## work.c

```
#include <stdlib.h>
#include <math.h>
extern double calc(double);
double work (double how_much_pie)
   double * results = (double*)
      malloc(sizeof(double)*100000);
   double * result = results;
   double
            ret;
   while (how_much_pie > 0.0) {
      *result++ = calc(how_much_pie);
      how_much_pie -= M_PI/180.0;
   ret = results[0] + results[7];
   free(results);
   return ret;
}
```

## classy.c

```
#include <stdio.h>
#include <math.h>
class Classy {
public:
   Classy (double angle);
   void crunch();
  bool operator > (Classy &);
private:
   double angle;
   double value;
};
Classy::Classy(double angle) : angle(angle), value(0.0) {}
void Classy::crunch() {
   extern double work(double);
   value = work(angle);
bool Classy::operator > (Classy & right) {
   return value > right.value;
}
int main ()
```

```
{
   Classy raspberry(M_PI/4.0+0.2);
   Classy pumpkin(M_PI/4.0);

   pumpkin.crunch();
   raspberry.crunch();

   printf ("raspberry > pumpkin ? %s\n", raspberry > pumpkin
? "yes" : "no");
}
```

## api.h

```
extern double calc(double angle);
extern double work (double how_much_pie);
```

## **Answers to Common Questions**

What can I do if trace events are not logging at all?

Verify that the trace event file name on the trace\_begin() call matches the one on the user daemon invocation. Furthermore, check that the file exists and that you have permission to read and write it. Check the return codes from the API calls. See "trace\_begin, Trace.begin" on page 2-7 for more information.

When should I log a different trace event ID number?

Each endpoint of a state should have a different trace event ID number. Usually each trace event logging routine logs a different trace event ID number. This lets you easily identify which source line logged the trace event, how often that source line executed, and what order source lines executed in. However, it is sometimes useful to log the same trace event ID in multiple places. This makes it possible to group trace events from related, but not identical, activities. For more information, see "trace\_event, Trace.event and their variants" on page 2-13.

How can I prevent user trace events from being discarded or lost?

Use expansive mode; avoid use of buffer or file wrapping options. Flush the shared memory buffer more often by tuning:

- The shared memory buffer sizes
- The number of shared memory buffers
- Increase the priority of the user trace daemon
- Bind the user trace daemon to a CPU with minimal activity

See "Preventing Trace Event Loss" on page 5-1 and Chapter 3 for more information.

What can I do if trace events are not appearing in an ntrace display?

Press Refresh, fill out the Search Form, fill in values in the interval control area, use the interval scroll bar, keep pressing the Zoom Out icon until you see trace events, examine a display object configuration so you know what it is "listening" for, add or reconfigure display objects on the grid.

How can I prevent kernel trace events from being lost?

- Verify that the raw kernel trace output file (if not streaming) is on a local file system and not an NFS file system.
- Increase the size and number of the kernel trace buffers
- Increase the priority of the kernel trace daemon

• Bind the kernel trace daemon to a CPU with minimal activity

See "Preventing Trace Event Loss" on page 5-1 and Chapter 3 for more information.

Why can't I see my individual thread names?

In order to distinguish between threads, you must link with the thread-aware version of the NightTrace Logging API. You can name your threads with meaningful symbolic names by using the trace\_set\_thread\_name routine. See "Threads and Logging" on page 2-31 for more information.

# H Glossary

This glossary defines terms used in the documentation. Terms in *italics* are defined here.

#### argument

See trace event argument.

#### boolean table

A pre-defined *string table* which associates 0 with false and all other values with true.

#### buffer-wraparound mode

The mode that causes the **ntraceud** daemon to treat the *shared memory buffer* as a circular queue and to overwrite the oldest *trace events* with the newest ones; this means that **ntraceud** intentionally discards the oldest trace events to make room for the newest ones. Invoke **ntraceud** with the **-bufferwrap** option to obtain this behavior. The two other **ntraceud** modes are *expansive mode* and *file-wrap-around mode*.

## button

See mouse button, push button, and radio button.

#### click

To press and release a *mouse button* without moving the pointer. Usually you do this in NightTrace to select menu items, *push buttons*, or *radio buttons*.

#### Close

A *push button* that closes a *dialog box*. This can also be a menu item that makes a *window* close.

## Column

A display object that constrains the width of State Graphs, Event Graphs, Data Graphs, and Rulers.

## configuration

The definition of a display object or profile.

## configuration file

An NightTrace-generated ASCII file that holds *display pages*, and *profile* definitions. This can also be a hand-edited table file, containing definition of *string tables* and/or *format tables*.

#### context switch

An action that occurs inside the kernel. Its functions are to save the state of the process that is currently executing, to initialize the state of the process to be run, and to begin execution of the new process.

#### context switch line

A vertical line superimposed on an *exception graph* or a *syscall graph* on a kernel *display page*. It indicates that the kernel has switched out the process that was previously running on the CPU and switched in a new process.

#### control

See mouse button, push button and radio button.

#### **CPU** box

A *Grid Label* on a kernel *display page*. It identifies which <u>logical</u> central processing unit the displayed data corresponds to. Logical CPU numbers are related to, but not necessarily identical to, physical CPU numbers.

#### current instance of a state

The instance of a *state* which has begun but has not yet completed. Thus, the *current time line* would be positioned within the region from the <u>start event</u> up to, but not including, the <u>end event</u>.

#### current time

The time in the *interval* up to which all *display objects* on a *display page* have been updated.

## current time line

The dashed vertical bar that represents the *current time* in a *Column*.

## current trace event

The last trace event on or before the current time line.

## cursor

See text cursor.

#### daemon definition

The configuration of a particular trace daemon which includes daemon collection modes and settings, daemon priorities and CPU bindings, and data output formats, as well as which trace event types are handled by that daemon.

#### **Data Box**

A display object that displays possibly variable textual or numeric information.

#### **Data Graph**

A scrollable *display object* that graphically displays a bar chart of an *expression*'s value as it changes over the *interval*.

## **Default Kernel Page**

A menu item that automatically creates a *display page* to depict *context switches*, *interrupts*, *exceptions*, and system calls with *display objects* for each CPU on the system.

## **Default Page**

A menu item that automatically creates a *display page* with a *State Graph* for each trace event logging process in your *trace event file(s)*.

#### device table

A pre-defined, dynamically generated *string table* in the **vectors** file created by **ntrace** when consuming raw kernel trace data files. string table contains the names of the devices that are currently configured in the kernel.

## dialog box

A transient secondary *window* that accepts input or conveys a message, for example information, errors, warnings, and questions. This construct is occasionally called a pop-up window.

#### dimmed

See disabled.

#### disabled

To flag a component, such as a menu item or *push button*, as temporarily unavailable by graying out the label.

#### discarded trace event

A trace event that **ntraceud** intentionally did not log in buffer-wraparound or file-wraparound mode.

## display object

A user-configured graphical component of a display page that shows trace events, states, trace event arguments, other numeric and text data. Display objects include the following: Grid Labels, Data Boxes, Columns, State Graphs, Event Graphs, Data Graphs and Rulers.

#### display page

The NightTrace window that allows you to layout display objects and see trace event and state information in them. You can store display pages in configuration files.

#### dotted area

See grid.

#### drag

To press and hold down a *mouse button* while moving the *mouse*. Usually you do this in NightTrace to position a *display object*.

#### duration

The period of time between the start and end *trace events* of some *state*.

#### Edit mode

The *display-page* mode that allows you to create, edit, and configure *display objects*. The other display-page mode is *View mode*.

## ellipses (...)

An indicator at the end of a menu item that tells you this selection makes a *dialog* box appear. Also, an indicator in command line option summaries and syntax listings that tells you more than one occurrence of the previous syntactic component is allowed.

#### end function

A state function that provides information about the <u>ending</u> trace event of the last completed instance of a state. The state to which the end function applies is either the state specified to the function, or the state being currently defined. Thus, if a qualfied state is not specified, end functions are only meaningful when used in expressions associated within a state definition.

#### event

See trace event.

#### event arg dbl summary table

A pre-defined *format table* which contains formats for statistical displays of trace event *matches* and type double *arguments*.

#### event\_arg\_summary table

A pre-defined *format table* which contains formats for statistical displays of trace event *matches* and type long *arguments*.

#### **Event Graph**

A scrollable *display object* that graphically displays *trace events* as vertical lines in a *Column*.

#### event ID

See trace event ID.

## event map file

User-generated ASCII file that lets you associate or map short mnemonic names with numeric *trace event IDs*.

#### event table

A pre-defined, dynamically generated *string table*. It is internal to NightTrace and maps all known numeric *trace event ID*s with symbolic trace event names.

## exception

An event internal to the currently executing process that stops the current execution stream. Exceptions can be suspended and resumed.

#### exception graph

A *State Graph* on a kernel *display page*. It displays *states* representing *exceptions* executing on the associated CPU.

## expansive mode

The (default) mode that causes the **ntraceud** daemon to copy all *trace events* that ever reach the *shared memory buffer* to the indefinitely-sized *trace event file*. Invoke **ntraceud** without the **-filewrap** and **-bufferwrap** options to obtain this behavior. The two other **ntraceud** modes are *buffer-wraparound mode* and *file-wraparound mode*.

## expression

A combination of operators and operands that evaluate to a value. Operands include constants, *function* calls, *and profile references*.

#### **Exit**

A menu item that terminates an NightTrace session.

#### file-wraparound mode

The mode that causes the **ntraceud** daemon to overwrite the oldest *trace events* in the beginning of the *trace event file* with the newest ones; this means that **ntraceud** intentionally *discards* the oldest trace events to make room for the newest ones. Invoke **ntraceud** with the **-filewrap** option to obtain this behavior. The two other **ntraceud** modes are *expansive mode* and *buffer-wrap-around mode*.

## flushing the buffer

The process of the **ntraceud** daemon copying *trace events* from the *shared memory buffer* to a *trace event file*.

font

A style of text characters.

#### format function

A function that allows you to display a string.

#### format table

The pre-defined or user-defined structure that allows you to group related integer values together and associate each one with a corresponding dynamically-formatted and generated character string. You hand-edit format tables into *configuration files*. The related structure is a *string table*.

#### function

A pre-defined NightTrace entity that may be used in an *expression*. NightTrace provides several classes of functions: *trace event*, *multi-event*, *start*, *end*, *multi-state*, *offset*, *summary*, *format*, and *table functions*.

#### gap

The period of time between two *trace events*, possibly the end of one *state* and the beginning of another.

## global process identifier

See PID.

#### **Global Window**

The NightTrace *window* that displays summary statistics pertaining to your *trace event files* and allows you to open NightTrace-related files.

#### graphical user interface

The mechanism NightTrace uses to receive input and provide displays. It is based on the X Window System and Motif.

grid

The region of the *display page* filled with parallel rows and columns of dots that holds *display objects*.

**Grid Label** 

A display object that displays constant textual information.

**GUI** 

See graphical user interface.

Help

A menu item that presents the online manual using the HyperHelp viewer.

host system

The system on which the NightTrace GUI is running.

icon

The small graphical image and/or text label that represents a *window* or window family when the window is minimized. The text label is either the window title or an abbreviated form of the title. Iconified windows are still active.

ID

See trace event ID.

#### instrumented code

Source code after you have put calls to NightTrace library routines into it.

## interrupt

An event external to the currently executing process; an interrupt stops the current execution stream to begin execution of a higher-priority execution stream. There are device-related and software-generated interrupts. Interrupts have an associated priority known as the interrupt priority level (IPL), which allows an interrupt to interrupt the execution stream of a lower-IPL interrupt.

## interrupt graph

A *Data Graph* on a kernel *display page*. It displays *states* representing *interrupts* executing on the associated CPU.

## interrupt priority level (IPL) register

A system register than can be used by the NightTrace library to prevent rescheduling and interrupts during trace event logging.

#### interval

A time period in the trace session delimited by the Start Time and End Time fields of the *interval control area*.

#### interval control area

The region of the *display page* that holds nine numeric fields that define and manipulate the *interval* and the *display objects* on the *grid*.

#### interval timer

The system timer on the NightHawk 6000 Series and TurboHawk systems that *NightTrace* uses to timestamp *trace events*.

#### **Kernel Trace Event File**

A trace event file is generated by a kernel trace daemon. This file contains raw kernel data and is automatically transformed into a filtered file (with a new filename using the ".ntf" suffix) by ntrace. Either a raw kernel trace event file or a filtered file may be specified to ntrace. The filtering process also creates a vectors file which is formed by appending a ".vec" suffix to the original trace event file name.

## keyboard

A traditional input device for entering text into fields. In this manual, this is a standard 101-key North American keyboard.

## last completed instance of a state

The most recent instance of a *state* that has already completed. Thus, the *current time line* would be positioned either on, or after, the *end event* for a state.

## last exception box

A *Data Box* on a kernel *display page*. It displays the last *exception* prior to the *current time line* that executed (and may still be executing) on the associated CPU.

## last interrupt box

A *Data Box* on a kernel *display page*. It displays the name of the last *interrupt* prior to the *current time line* that executed (and may still be executing) on the associated CPU.

#### last syscall box

A *Data Box* on a kernel *display page*. It displays the last *syscall* prior to the *current time line* that executed (and may still be executing) on the associated CPU.

#### lost trace event

A *trace event* **ntraceud** was unable to log. Several **ntraceud** options exist to prevent this trace event loss.

mark

The solid triangle on a *Ruler* that points to a particular time.

match

A trace event or state that meets user-defined qualifying configuration criteria.

menu

A list of user-selectable choices.

menu bar

The horizontal band near the top of a *window* that contains a list of labeled *pull-down menus*.

## message display area

The scrolling region of the *Global Window* or the *display page* that holds textual statistics, as well as error and warning messages.

#### most recent instance of a state

If the *current time line* is positioned within a *current instance of a state*, then it is that instance of the *state*. Otherwise, it is the *last completed instance of a state*.

mouse

In this manual, a three-button pointing device for point-and-click interfaces.

## mouse button

A part of the *mouse* that you can press to alter aspects of the application. Each mouse button has a different purpose. Button 1 is usually for selecting or dragging. Button 2 is usually for moving *display objects*. Button 3 is usually for resizing display objects. You can make multiple selections by simultaneously pressing <Shift> and clicking mouse button 1. You may *click*, *drag*, *press*, and *release* mouse buttons.

## multi-event function

Multi-event functions return information about ocurrences of events, or relationships between occurrences of events, before the *current time line*.

#### multi-state function

Multi-state functions return information about instances of states, or relationships between instances of states, before the *current time line*.

## name\_pid table

A pre-defined, dynamically generated *string table*. It is internal to NightTrace and associates node ID numbers with the the name of each node's process ID table.

#### name\_tid table

A pre-defined, dynamically generated *string table*. It is internal to NightTrace and associates node ID numbers with the the name of each node's thread ID table.

## **New Page**

A menu item that creates an empty display page.

## **NightTrace**

The interactive debugging and performance analysis tool that is part of the Night-Star tool kit. It consists of the **ntraceud** daemon, NightTrace library routines, and the **ntrace** display utility. This product allows you to log *trace events* and data from applications written in C or Fortran; these applications may be composed of one or more processes, running on one or more CPUs. You can then examine these trace events and those from the kernel through the **ntrace** display utility.

## NightTrace thread

A NightTrace thread is either a process or a POSIX thread (or a set of any combination of these). The name of a thread is either a numeric value representing a threads internal identifier (usually its gettid(2) value), or a symbolic name assigned by various parties. NightTrace defaults the name of the main thread of a process to "main". The user can set the name of a thread using trace\_set\_thread\_name. See "Threads and Logging" on page 2-31 for more information.

#### NightTrace thread identifier

See TID.

#### **NightView**

A symbolic debugger that is part of the NightStar tool kit. It lets you debug C and Fortran applications; these applications may be composed of one or more processes, running on one or more CPUs. Among other things, NightView can automatically patch trace event logging routines into your executable application.

#### node

A system from which a trace event file can come from.

#### node box

If the RCIM synchronized tick clock is used to timestamp events, this is a *Grid Label* on a kernel *display page*. It identifies which *node* to which the displayed data corresponds.

#### node ID

A unique identifier internally assigned by NightTrace to every *node* that has an *trace* event file in a trace file analysis.

#### node name

The name of a system from which a trace event file can come.

## node\_name table

A pre-defined, dynamically generated *string table*. It is internal to NightTrace and associates *node ID* numbers with *node names*.

#### node PID table

A pre-defined, dynamically generated *string table*. It is internal to NightTrace and associates process identifiers (*PIDs*) with process names for a particular *node*. The name of each node's table is pid\_*nodename* where *nodename* is the node's name. If kernel tracing, this table is stored in the **vectors** file.

## node TID table

A pre-defined, dynamically generated *string table*. It is internal to NightTrace. If user tracing, it associates NightTrace thread ID numbers with thread names for a particular *node*. If kernel tracing, this table is not used. The name of each node's table is tid\_*nodename* where *nodename* is the node's name.

## NT\_ASSOC\_PID

An overhead *trace event* that **ntraceud** logs at the beginning and end of each process.

## NT\_ASSOC\_TID

An overhead *trace event* that **ntraceud** logs at the beginning and end of each *thread*.

## NT\_CONTINUE

An overhead *trace event* that **ntraceud** logs for multi-argument trace events.

## ntrace display utility

The part of *NightTrace* that graphically displays *trace events*, trace event data, and *states* for debugging and performance analysis.

#### ntraceud

The *NightTrace* daemon process that allows you to log user-defined *trace events* and data from user applications written in C or Fortran. These applications may be composed of one or more processes, running on one or more CPUs.

## object

See display object.

#### offset

The number that identifies the position of a *trace event* in the chronologically-ordered sequence of trace events, regardless of the *trace event ID*. Counting starts from zero. For example, if a trace event with trace event ID 71 is the third trace event in the trace session, then its offset is 2.

#### offset function

A function that takes an expression that evaluates to an offset as a parameter.

## OK

A push button that acknowledges the warning in a dialog box.

## Open

A menu item and *push button* that opens an existing file.

## ordinal trace event number

See offset.

## panel

A window component that groups related buttons, for example push buttons.

#### **PID**

A 32-bit integer that represents an operating system process, which is normally the value returned by getpid(2) for single-threaded applications, and gettid(2) for multi-threaded application in kernel data.

## PID table

A pre-defined, dynamically generated *string table*. It is internal to NightTrace and associates process identifiers (*PIDs*) with process names. If kernel tracing, the pid string table in the **vectors** file.

## point

To move the *mouse* so the mouse pointer is positioned at the place of interest.

pointer

A graphical symbol that represents the mouse pointer's current location in the *window*. The shape of the pointer shows the current usage. Usually a pointer is shaped like an arrow pointing to the upper left.

pop-up window

See dialog box.

press

To hold down a mouse button without releasing it or to depress a keyboard key.

profile

The "logical and" of several criteria such as event codes, processes, and threads. conditions used to identify an event or a state.

profile reference

The name of a profile.

pull-down menu

A set of critera defining conditions for an event or state; e.g event IDs, argument values, CPU, process, thread.

push button

A graphic image of a labeled button. Click on a push button to select it.

radio button

A graphic, labeled diamond-shape that represents a mutually exclusive selection from related radio buttons. *Click* on a radio button to select it.

Read

A menu item and *push button* that read an existing file.

record

See trace event.

region

The period of time between the *mark* and the *current time*.

release

To let go of the currently-pressed mouse button.

Reset

A push button that cancels (undoes) all unapplied changes.

Restore

A push button that cancels all changes since the dialog box was displayed.

Ruler

A scrollable *display object* that appears as a hash-marked timeline within a *Column*. The Ruler may also contain reverse video "L"s indicating *lost trace events* and user-defined *marks*.

running process box

A *Data Box* that shows the process that is executing at the *current time line* on the associated CPU.

Save

A menu item and *push button* that overwrite an existing *configuration file* with the current *display page*.

Save As

A menu item that saves the current display page in a new configuration file.

**Save Text** 

A menu item that overwrites an existing summary text file with text from the summary display area.

**Save Text As** 

A menu item that saves the current summary text from the *summary display area* into a new summary text file.

**SBC** 

Single-board computer.

scroll bar

The narrow, rectangular graphic device used to change a display that would not otherwise fit in the *window*. It consists of a *trough*, a *slider*, and arrowhead buttons. If the slider does not fill the trough, there is a gap on one or both sides.

#### Search Form

The NightTrace form that allows you to define criteria to be used to locate a *trace event* in a *trace event file* by its configured characteristics and its location in the file.

#### selection

The *display object* that you *clicked* on. Alternatively, a selection may be the region of a text field you *dragged* the *mouse* over. For menu items, *push buttons*, and *radio buttons* NightTrace indicates selection by highlighting your choice. For *display objects*, NightTrace places handles on the display object. For dragged-over text fields, NightTrace displays that text in reverse video.

#### separator

A line that groups related *window* components or menu components.

#### session

A session consists of daemon definitions, display page configurations, string tables, profiles, named tags, previously-executed searches, and previously-executed summaries. A session also includes references to saved trace data segment files, kernel trace files, and user trace files. A session can be saved to a session configuration file and reloaded in subsequent invocations of NightTrace.

# shared memory buffer

The intermediate destination of *trace events* before **ntraceud** copies them to the *trace event file* on disk.

#### slider

The graphic part of a *scroll bar* that you move in the *trough* to change the display. This component is sometimes called a thumb.

#### spin lock

A device used to protect a resource, for example, the *shared memory buffer*.

# start function

A state function that provides information about the <u>start</u> event of the most recent instance of a state. The state to which the start function applies is either the state specified to the function, or the state being currently defined. Thus, if a state is not specified, start functions are only meaningful when used in expressions associated within a state definition. In addition, start functions should not be used in a recursive manner in a Start Expression; a start function should not be specified in a Start Expression that applies to the state definition containing that Start Expression. Conversely, an End Expression may include start functions that apply to the state definition containing that End Expression.

#### state

A state is a region of time bounded by two trace events, a *start event* and an *end event*. An instance of a state is the period of time between the start event and end event, including the start and end events themselves. Additional conditions may be specified in a state definition to further constrain the state. Instances of states do not nest; that is, once a state becomes active, events that might normally satisfy the conditions for the start event are ignored until the end event is encountered.

#### state function

The class of NightTrace functions which provide information about states, including: start functions, end functions, and multi-state functions.

# **State Graph**

A scrollable *display object* that graphically displays *states* as bars and *trace events* as vertical lines in a *Column*.

## streaming

The method used by the NightTrace of sending trace data from daemons directly to the NightTrace display.

# string table

The pre-defined or user-defined structure that allows you to group related integer values together and associate each one with a corresponding static character string. You hand-edit string tables into *configuration files*. The related structure is a *format table*.

## **Summarize Form**

The NightTrace form that allows you to obtain *trace event* and *state* statistics, such as minimum, maximum, average, and total values of *gaps*, *durations*, and *trace event arguments*.

## summary display area

The scrolling region of the Summarize Form that holds textual summary statistics.

## summary function

A function that takes another expression as a parameter (except for summary\_matches()).

#### summary syscall

A system call that is a special type of *exception*. A *syscall* is made when a user program forces a trap into the operating system via a special machine instruction. A syscall is used to request a given service from the kernel. Many library routines

supplied as part of the operating system make syscalls to accomplish their functions. Syscalls can be suspended and resumed.

syscall

System call.

syscall graph

A *State Graph* on a kernel *display page*. It displays *states* representing system calls (*syscalls*) executing on the associated CPU.

syscall table

A pre-defined, dynamically generated *string table* in the **vectors** file. This string table contains the names of all the possible system calls (*syscalls*) that can occur on the system.

table

See format table and string table.

table function

A *function* that allows you to extract information from user-defined and pre-defined *string tables* and *format tables*.

tag

A uniquely-numbered indicator on a *Ruler* that represents an individual point of interest in the trace data (either a particular time or event) and which can be identified by a name.

text cursor

The blinking vertical bar in an editable text field that shows your current edit position within the field.

thread

A sequence of instructions and associated data that is scheduled and executed as an independent entity. Every process linked with the Threads Library contains at least one, and possibly many, threads. Threads within a process share the address space of the process.

thread ID

A 16-bit integer chosen by the threads library that uniquely identifies a *thread* within a given process.

#### TID

A 32-bit integer that represents an internal NightTrace context to which *trace events* can be associated.

## **TID table**

A pre-defined, dynamically generated *string table*. It is internal to NightTrace and associates NightTrace thread identifiers (*TIDs*) with thread names. This table is not used in kernel tracing.

## timestamp

The time at which a specific *trace event* was logged. This provides the means by which the chronology of the trace events logged by multiple processes can be assembled.

# time quantum

The fixed period of time for which the kernel allocates the CPU to a process.

#### trace event

A user-defined point of interest in an application's source code that NightTrace represents with an integer *trace event ID*. Alternatively this may be a predefined point of interest in the kernel. Along with the trace event ID, *NightTrace* records the *timestamp* when the trace event occurred, any arguments logged with the trace event, and the logging process identifier (*PID*).

# trace event argument

A user-defined numeric value logged by an application via a trace event.

#### trace event file

An **ntraceud**-created binary file that contains sequences of *trace events* and data that your application and the **ntraceud** daemon logged.

## trace event function

The class of NightTrace *functions* that provide information about *trace events*. They operate on either the *profile* specified to that function or, if unspecified, the *current trace event*. Trace event functions include *multi-event functions*.

# trace event ID

An integer that identifies a *trace event*. User trace event IDs are in the range 0-4095, inclusive. Kernel trace event IDs are in the range 4100-4300, inclusive.

#### trace point

A place of interest in the source code. In user tracing, at each trace point in your application you call a trace event logging routine to log a *trace event*, possibly with

additional data describing part of your program's *state* at that time. Kernel trace points and trace events are already defined and embedded in the kernel source.

trough

The graphic part of a *scroll bar* that holds the *slider*.

vector table

A pre-defined, dynamically generated *string table* in the **vectors** file. This string table contains the *interrupt* and *exception* vector names associated with the system on which the kernel tracing was performed.

View mode

The display page mode that allows you to see, search for, and summarize trace event information in the message display area, the summary display area, and display objects on the grid.

widget

A window component, for example a scroll bar or push button.

window

A rectangular screen area that permits the display and/or entry of data. The Night-Trace display utility consists of several windows.

window manager

The program that controls window placement, size, and operations.

wraparound mode

The mode that causes the **ntraceud** daemon to intentionally discard old events. There are two forms of wraparound mode: *buffer-wraparound* and *file-wraparound*. The other **ntraceud** mode is *expansive mode*.

# Index

Symbols	arg_long_long function 16-25, 16-67
	arg1 function 7-22, 16-5, 16-190
/usr/bin/ntracekd 4-1	arg2 function 16-9
/usr/bin/ntraceud 3-1	args 5-19, 5-20
/usr/include/ntrace.h 2-1	avg function 16-179
/usr/lib/libntrace.a 2-31	
/usr/lib/libntrace_thr.a 2-31	В
/usr/lib/NightTrace/illuminators 5-10	В
"wrapper" routines 5-1	
comment 5-14	blk_arg function 16-26
«config» 5-14	blk_arg_bits function 16-27
declare 5-15	blk_arg_char function 16-28
«defaults» 5-16	blk_arg_dbl function 16-29
«exclude» 5-16	blk_arg_flt function 16-30
<pre><function> 5-17</function></pre>	blk_arg_long function 16-31
<pre><group> 5-18</group></pre>	blk_arg_long_bits function 16-32
<li>devel&gt; 5-18</li>	blk_arg_long_dbl function 16-33
<pre><options> 5-21</options></pre>	blk_arg_long_long function 16-34
<variable> 5-22</variable>	blk_arg_long_ubits function 16-35
<pre><wrapper_file_scope> 5-23</wrapper_file_scope></pre>	blk_arg_short function 16-36
<pre><wrapper_post> 5-23</wrapper_post></pre>	blk_arg_string function 16-37
<pre><wrapper_pre> 5-24</wrapper_pre></pre>	blk_arg_ubits function 16-38
<pre><wrapper_real> 5-24</wrapper_real></pre>	blk_arg_uchar function 16-39
<pre><wrapper> 5-23</wrapper></pre>	blk_arg_uint function 16-40
	blk_arg_ulong_long function 16-41
	blk_arg_ushort function 16-42
A	boolean table 7-18
7	Box
	interrupt 17-12
a.link 5-11	syscall 17-13
a.out 5-14	Box exception 17-12
Ada language	BUFFER_LENGTH 5-13
compiling and linking 2-32	Buffer-wraparound mode 2-23
Ada task identifier 16-8, 16-46, 16-88, 16-125, 16-166, 18-82	Burier-wraparound mode 2-23
addr 5-19	
addr_args 5-19, 5-20	С
addr_ret 5-19, 5-20	
aggregate_limi 5-20	<b>C1</b>
aggregate_limit 5-19, 5-22	C language
Application Illumination 5-1	compiling and linking 2-32
arg function 16-4, 16-21	source considerations 2-1
arg_dbl function 16-22, 16-23	caller 5-19, 5-20
arg_long_dbl function 16-24	ccur_rt 5-2, 5-12
<b></b>	character entities 5-15

clock_synchronize(1M) command 2-9	end_blk_arg_bits function 16-106
Comments	end_blk_arg_char function 16-107
event-map file 7-11	end_blk_arg_dbl function 16-108
Configuration parameters	end_blk_arg_flt function 16-109
Then-Expression 16-188	end_blk_arg_long function 16-110
Conserving disk space 6-3	<pre>end_blk_arg_long_bits function 16-111</pre>
Constant string literals 7-22, 16-11, 16-186	end_blk_arg_long_dbl function 16-112
Constant times 16-3	end_blk_arg_long_long function 16-113
Context switch	<pre>end_blk_arg_long_ubits function 16-114</pre>
lines 17-11, 17-12, 17-13	end_blk_arg_short function 16-115
Context-sensitive help 8-22	end_blk_arg_string function 16-116
cpu function 16-48	end_blk_arg_ubits function 16-117
Current time line 17-10, 17-12, 17-13	end_blk_arg_uchar function 16-118
	end_blk_arg_uint function 16-119
	end_blk_arg_ulong_long function 16-120
B	end_blk_arg_ushort function 16-121
D	end_cpu function 16-127
	end_id function 16-99
Data Box 16-188, 17-12, 17-13, 17-14	end_node_id function 16-130
Data Graph 17-12	end_node_name function 16-133
detail leve 5-13	end_num_args function 16-122
detail level 5-7	end_offset function 16-128
Detail Levels 5-2	end_pid function 16-123
device table 7-19, 17-4, 17-16	end_pid_table_name function 16-131
device_nodename table 7-20, 17-17	end_task_id function 16-125
Disabling	end_thread_id function 16-124
library routines 2-18, 2-29	end_tid function 16-126
trace events 2-19	end_tid_table_name function 16-132
tracing 2-18, 2-29	end_time function 16-129
Discarding trace events 2-23, E-1	Environment variable
Display object	NSLM SERVER A-2
Data Box 16-188, 17-12, 17-13, 17-14	errno 5-19, 5-20, 18-139, 18-140
Data Graph 17-12	Event
Event Graph 17-14	
State Graph 17-14 State Graph 17-13, 17-14	gap 16-58 matches 16-59
•	
Display object configuration parameters  Then Eventsein 16, 188	qualified 16-191
Then-Expression 16-188	Event ID and Transport
Display page area	Event ID. see Trace event
interval scroll bar E-2	ID
Duration	event table 7-17
state 16-135	Event. see Trace event
	event_gap function 16-58
	event_ids 5-21
E	event_matches function 16-59
	Event-map file 2-15, 7-2, 7-11
T	Exception 17-3, 17-12, 17-15, 17-17
Enabling	graph 17-12
trace events 2-19	resumption 17-12
End functions 16-97	suspension 17-12
end_arg function 16-100	Exception box 17-12
end_arg_dbl function 16-101, 16-102	exclude 5-19, 5-20
end_arg_long_dbl function 16-103	execve(2) service 2-8
end_arg_long_long function 16-104	Expressions
end blk arg function 16-105	constant string literals 7-22, 16-11, 16-186

functions 16-4	blk_arg_uint 16-40
operands 16-1	blk_arg_ulong_long 16-41
operators 16-1	blk_arg_ushort 16-42
	cpu 16-48
	end 16-97
F	end_arg 16-100
Г	end_arg_dbl 16-101,16-102
	end_arg_long_dbl 16-103
File	end_arg_long_long 16-104
/usr/bin/ntracekd 4-1	end_blk_arg 16-105
/usr/bin/ntraceud 3-1	end_blk_arg_bits 16-106
/usr/include/ntrace.h 2-1	end_blk_arg_char 16-107
/usr/lib/libntrace.a 2-31	end_blk_arg_dbl 16-108
/usr/lib/libntrace_thr.a 2-31	end_blk_arg_flt 16-109
event-map 2-15, 7-2, 7-11	end_blk_arg_long 16-110
trace event 2-6, 3-1, 7-10	end_blk_arg_long_bits 16-111
vectors 7-17, 17-2, 17-15, 17-16, 17-17	end_blk_arg_long_dbl 16-112
File system	end_blk_arg_long_long 16-113
NFS E-2	end_blk_arg_long_ubits 16-114
filename 5-22	end_blk_arg_short 16-115
Fixed licenses A-1	end_blk_arg_string 16-116
Floating licenses A-1	end_blk_arg_ubits 16-117
Flushing shared memory buffer 2-22	end_blk_arg_uchar 16-118
fork(2) service 2-8	end_blk_arg_uint 16-119
Format	end_blk_arg_ulong_long 16-120
functions 16-184	end_blk_arg_ushort 16-121
format function 16-190	end_cpu 16-127
Format table 7-20, 16-188	end_id 16-99
get_format function 16-188	end_node_id 16-130
Fortran language	end_node_name 16-133
compiling and linking 2-32	end_num_args 16-122
frame 5-19, 5-20	end_offset 16-128
Functions 16-4	end_pid 16-123
arg 16-4,16-21	end_pid_table_name 16-131
arg_dbl 16-22,16-23	end_task_id 16-125
arg_long_dbl 16-24	end_thread_id 16-124
arg_long_long 16-25, 16-67	end_tid 16-126
arg1 7-22, 16-5, 16-190	end_tid_table_name 16-132
arg2 16-9	end_time 16-129
avg 16-179	event_gap 16-58
blk_arg 16-26	event_matches 16-59
blk_arg_bits 16-27	format 16-184
blk_arg_char 16-28	format 16-190
blk_arg_dbl 16-29	get_format 16-188
blk_arg_flt 16-30	get_item 16-186
blk_arg_long 16-31	get_string 7-22,16-184
blk_arg_long_bits 16-32	id 16-20, 16-188, 16-190
blk_arg_long_dbl 16-33	max 16-178
blk_arg_long_long 16-34	max_offset 16-182
blk_arg_long_ubits 16-35	min 16-177
blk_arg_short 16-36	min_offset 16-181
blk_arg_string 16-37	multi-event 16-58
blk_arg_ubits 16-38	multi-state 16-134
blk arg uchar 16-39	node id 16-51

node_name 16-54	start_blk_arg_long_dbl 16-75
num_args 16-43	start_blk_arg_long_long 16-76
offset 16-138	start_blk_arg_long_ubits 16-77
offset 7-22, 16-49	start_blk_arg_short 16-78
offset_arg 16-141	start_blk_arg_string 16-79
offset_arg_dbl 16-142, 16-143	start_blk_arg_ubits 16-80
offset_arg_long_dbl 16-144	start_blk_arg_uchar 16-81
offset_arg_long_long 16-145	start_blk_arg_uint 16-82
offset_blk_arg 16-146	start_blk_arg_ulong_long 16-83
offset_blk_arg_bits 16-147	start_blk_arg_ushort 16-84
offset_blk_arg_char 16-148	start_cpu 16-90
offset_blk_arg_dbl 16-149	start_id 16-5, 16-62
offset_blk_arg_flt 16-150	start_node_id 16-93
offset_blk_arg_long 16-151	start_node_name 16-96
offset_blk_arg_long_bits 16-152	start_num_args 16-85
offset_blk_arg_long_dbl 16-153	start_offset 16-91
offset_blk_arg_long_long 16-154	start_pid 16-86
offset_blk_arg_long_ubits 16-155	start_pid_table_name 16-94
offset_blk_arg_short 16-156	start_task_id 16-88
offset_blk_arg_string 16-157	start_thread_id 16-87
offset_blk_arg_ubits 16-158	start_tid 16-89
offset_blk_arg_uchar 16-159	start_tid_table_name 16-95
offset_blk_arg_uint 16-160	start_time 16-92
offset_blk_arg_ulong_long 16-161	state_dur 16-135
offset_blk_arg_ushort 16-162	state_gap 16-5, 16-134
offset_cpu 16-168	state_matches 16-136
offset_id 16-140, 16-181, 16-182	state_status 16-137
offset_node_id 16-170	string 16-16
offset_node_name 16-173	sum 16-180
offset_num_args 16-163	summary 16-177
offset_pid 16-164	summary_matches 16-183
offset_pid_table_name 16-171	table 16-184
offset_process_name 16-174	task_id 16-46
offset_task_id 16-166	task_name 16-56
offset_task_name 16-175	thread_id 16-45
offset_thread_id 16-165	thread_name 16-57
offset_thread_name 16-176	tid 16-47
offset_tid 16-167	tid_table_name 16-53
offset_tid_table_name 16-172	time 16-50
offset_time 16-169	trace event 16-18
pid 16-44, 16-188	
pid_table_name 16-52	
process_name 16-55	G
start 16-60	•
start_arg 16-63	
start_arg_dbl 16-64,16-65	Gap
start_arg_long_dbl 16-66	event 16-58
start_blk_arg 16-68	state 16-134
start_blk_arg_bits 16-69	get_format function 16-188
start_blk_arg_char 16-70	get_item function 16-186
start_blk_arg_dbl 16-71	get_string function 7-22, 16-184
start_blk_arg_flt 16-72	glibc 5-2, 5-12
start_blk_arg_long 16-73	Global process identifier 16-7, 16-44
start_blk_arg_long_bits 16-74	Graph

data 17-12	Interval
event 17-14	scroll bar E-2
exception 17-12	iregex 5-22
interrupt 17-12	IRQ_ENTRY trace event 17-2
state 17-13, 17-14	IRQ_EXIT trace event 17-3
syscall 17-13	<b>\-</b>
2,22	
	17
н	К
П	
	Kernel tracing 7-17, 7-18, 17-1
Hardclock interrupts 17-12	
Help	
On Context 8-22	L
	L
1	Language
	Ada 2-32
	C 2-1, 2-32
id function 16-20, 16-188, 16-190	Fortran 2-32
illuminate 5-12	level, detail 5-13
illuminator 5-1, 5-4	libntrace.a 2-31
ada 5-11	libntrace_tjr.a 2-31
aggregate_limit 5-4	Library routines 2-1
build 5-7	overloading in Ada 2-3
cf77 5-11	return values 2-2
config 5-4	trace_begin 2-17, 2-21, 2-25, 3-1, E-1
create 5-4	trace_close_thread 2-24
do_nodebug 5-5	trace_disable 2-18
dont_nodebug 5-5	trace_disable_all 2-18,2-29
event_ids 5-5	trace_disable_range 2-18
g77 5-11	trace_enable 2-18
gcc 5-11	trace_enable_all 2-18
i 5-5	trace_enable_range 2-18
install 5-5	trace_end 2-9, 2-22, 2-25, 3-2
iregex 5-6	trace_event 2-12
istd 5-7	trace_flush 2-22,3-2
iunderscores 5-6	trace_open_thread 2-11,2-24
populate 5-7	trace_trigger 2-22,3-2
report 5-9	licences 1-1
x 5-5	License A-1
xregex 5-6	firewall configurations A-4, A-5, A-7, A-8
xstd 5-7	fixed A-1
xunderscores 5-6	floating A-4
illuminator.h 5-8	installation A-1
illuminator.map 5-8	keys A-1
illuminator.o 5-9	modes A-1
illuminator_level.fmt 5-9	nslm_admin A-1, A-3
illuminators 5-10	report A-3
Inter-process communication 2-4	requests A-2
Interrupt 17-2, 17-12, 17-15, 17-17	server A-3, A-4, A-5
graph 17-12	support A-10
hardclock 17-12	License manager 1-1
Interrupt box 17-12	lluminator_level.list 5-9

lluminator_level.o 5-9	ordinal trace event 16-173
-Intrace 5-10	starting trace event 16-96
-Intrace_thr 5-10	node_id function 16-51
Loading	node_name function 16-54
trace event 7-5	node_name table 7-19, 17-16
Logging	nodebug 5-22
trace event 6-4, E-1	nslm_admin A-1, A-3
Loss	NSLM_SERVER A-2
trace event 2-17, E-1	ntrace 1-4
	format tables 7-20
	functions 16-4
••	operands 16-1
M	operators 16-1
	performance considerations 7-5
Macros 16-191	string tables 7-15
main 5-2, 5-12	ntrace functions 16-4
Map file. see Event-map file	ntrace option
Matches	end (load events before constraint) 7-4
event 16-59	listing (list trace events) 7-12
state 16-136	start (load events after constraint) 7-4
summary 16-183	ntrace qualified states 16-62, 16-63, 16-64, 16-65,
max function 16-178	16-66, 16-67, 16-68, 16-69, 16-70, 16-71,
max_offset function 16-182	16-72, 16-73, 16-74, 16-75, 16-76, 16-77,
Maximum value 16-178, 16-182	16-72, 16-73, 16-74, 16-73, 16-74, 16-77, 16-78, 16-79, 16-80, 16-81, 16-82, 16-83,
Menu option	16-84, 16-85, 16-86, 16-87, 16-88, 16-89,
÷	
On Context 8-22	16-90, 16-91, 16-92, 16-93, 16-94, 16-95,
On Help 8-22, 8-23	16-96, 16-97, 16-99, 16-100, 16-101, 16-102,
min function 16-177	16-103, 16-104, 16-105, 16-106, 16-107,
min_offset function 16-181	16-108, 16-109, 16-110, 16-111, 16-112,
Minimum value 16-177, 16-181	16-113, 16-114, 16-115, 16-116, 16-117,
Mode	16-118, 16-119, 16-120, 16-121, 16-122,
buffer-wraparound 2-23	16-123, 16-124, 16-125, 16-126, 16-127,
Multi-event functions 16-58	16-128, 16-129, 16-130, 16-131, 16-132,
Multi-state functions 16-134	16-133, 16-134, 16-135, 16-136, 16-137
	ntrace.h 2-1
	ntracekd
N	daemon 4-1
	ntraceud
	daemon 3-1
name_pid table 7-18, 17-16	invoking 3-6
name_tid table 7-18	ntraceud mode
next_event.txt 5-8	buffer-wraparound 2-23
NFS file system E-2	num_args function 16-43
NightStar Licence Manager 1-1	NUM_BUFFERS 5-13
NightTrace thread identifier 16-8, 16-47, 16-89, 16-126, 16-167, 18-79	
NLSM 1-1	0
Node identifer 16-51	
Node identifier	
ending trace event 16-130	Offset 7-4, 16-4, 16-9, 16-10, 16-138, 16-140, 16-141,
offset 16-170	16-142, 16-143, 16-144, 16-145, 16-146,
starting trace event 16-93	16-147, 16-148, 16-149, 16-150, 16-151,
Node name 16-54	16-152, 16-153, 16-154, 16-155, 16-156,
ending trace event 16-133	16-157, 16-158, 16-159, 16-160, 16-161,

16-162, 16-163, 16-164, 16-165, 16-166,	16-108, 16-109, 16-110, 16-111, 16-112,
16-167, 16-168, 16-169, 16-170, 16-171,	16-113, 16-114, 16-115, 16-116, 16-117,
16-172, 16-173, 16-174, 16-175, 16-176	16-118, 16-119, 16-120, 16-121, 16-122,
offset function 7-22, 16-49	16-123, 16-124, 16-125, 16-126, 16-127,
Offset functions 16-138	16-128, 16-129, 16-130, 16-131, 16-132,
offset_arg function 16-141	16-133, 16-134, 16-135, 16-136, 16-137
offset_arg_dbl function 16-142, 16-143	Operands in expressions 16-1
offset_arg_long_dbl function 16-144	Operators in expressions 16-1
offset_arg_long_long function 16-145	•
offset_blk_arg function 16-146	
offset_blk_arg_bits function 16-147	_
offset_blk_arg_char function 16-148	Р
offset_blk_arg_dbl function 16-149	
offset_blk_arg_flt function 16-150	Performance considerations
offset_blk_arg_long function 16-151	ntrace 7-5
offset_blk_arg_long_bits function 16-152	PID 16-7, 16-44
offset_blk_arg_long_dbl function 16-153	pid function 16-44, 16-188
offset_blk_arg_long_long function 16-154	pid table 7-17, 17-17
offset_blk_arg_long_ubits function 16-155	PID table name 16-52
offset_blk_arg_short function 16-156	pid_nodename table 7-19, 17-16
offset_blk_arg_string function 16-157	pid_table_name function 16-52
	<del>-</del>
offset_blk_arg_ubits function 16-158	Pre-defined tables 7-17, 17-4, 17-15 printf(3) routine 7-13, 7-21
offset_blk_arg_uchar function 16-159	•
offset_blk_arg_uint function 16-160	printf(3S) routine 16-190
offset_blk_arg_ulong_long function 16-161	Process identifier
offset_blk_arg_ushort function 16-162	ending trace event 16-131
offset_cpu function 16-168	offset 16-171
offset_id function 16-140, 16-181, 16-182	starting trace event 16-94
offset_node_id function 16-170	Process identifier table name 16-52
offset_node_name function 16-173	Process name 16-55
offset_num_args function 16-163	ordinal trace event 16-174
offset_pid function 16-164	process_name function 16-55
offset_pid_table_name function 16-171	pthread 5-2, 5-12
offset_process_name function 16-174	Push button
offset_task_id function 16-166	Zoom Out E-2
offset_task_name function 16-175	
offset_thread_id function 16-165	
offset_thread_name function 16-176	Q
offset_tid function 16-167	<b>Q</b>
offset_tid_table_name function 16-172	
offset_time function 16-169	Qualified events 16-191
On Context menu option 8-22	Qualified states 16-62, 16-63, 16-64, 16-65, 16-66,
On Help menu option 8-22, 8-23	16-67, 16-68, 16-69, 16-70, 16-71, 16-72,
Operands	16-73, 16-74, 16-75, 16-76, 16-77, 16-78,
constants 16-2	16-79, 16-80, 16-81, 16-82, 16-83, 16-84,
functions 16-4	16-85, 16-86, 16-87, 16-88, 16-89, 16-90,
qualified states 16-62, 16-63, 16-64, 16-65, 16-66,	16-91, 16-92, 16-93, 16-94, 16-95, 16-96,
16-67, 16-68, 16-69, 16-70, 16-71, 16-72,	16-97, 16-99, 16-100, 16-101, 16-102, 16-103,
16-73, 16-74, 16-75, 16-76, 16-77, 16-78,	16-104, 16-105, 16-106, 16-107, 16-108,
16-79, 16-80, 16-81, 16-82, 16-83, 16-84,	16-109, 16-110, 16-111, 16-112, 16-113,
16-85, 16-86, 16-87, 16-88, 16-89, 16-90,	16-114, 16-115, 16-116, 16-117, 16-118,
16-91, 16-92, 16-93, 16-94, 16-95, 16-96,	16-119, 16-120, 16-121, 16-122, 16-123,
16-97, 16-99, 16-100, 16-101, 16-102,	16-124, 16-125, 16-126, 16-127, 16-128,
16-103, 16-104, 16-105, 16-106, 16-107,	16-129, 16-130, 16-131, 16-132, 16-133,
10-103, 10-104, 10-103, 10-100, 10-107,	10-129, 10-130, 10-131, 10-132, 10-133,

16-134, 16-135, 16-136, 16-137	start_time function 16-92
	State 2-16, 17-12
	duration 16-135
_	gap 16-134
R	matches 16-136
	State Graph 17-13, 17-14
Record. see Trace event	state_dur function 16-135
Return values 2-2	state_gap function 16-5, 16-134
return_val 5-19, 5-20	state_matches function 16-136
	state_status function 16-137
	Statistics
	multi-event 16-58
\$	multi-state 16-134
	summary 16-177
SCHED_CHANGE trace event 17-2	std 5-22
Scroll bar E-2	strcmp function 16-16
Shared memory	String functions
failure to attach 2-9	strcmp 16-16
	<del>-</del>
flushing 2-22	strncmp 16-17
SOFT_IRQ_ENTRY trace event 17-3	String table 7-15, 16-184, 16-186
SOFT_IRQ_EXIT trace event 17-3	boolean 7-18
Start functions 16-60	device 7-19, 17-4, 17-16
start_arg function 16-63	device_nodename 7-20, 17-17
start_arg_dbl function 16-64, 16-65	event 7-17
start_arg_long_dbl function 16-66	get_item function 16-186
start_blk_arg function 16-68	get_string function 7-22, 16-184
start_blk_arg_bits function 16-69	name_pid 7-18, 17-16
start_blk_arg_char function 16-70	name_tid 7-18
start_blk_arg_dbl function 16-71	node_name 7-19, 17-16
start_blk_arg_flt function 16-72	pid 7-17, 17-17
start_blk_arg_long function 16-73	pid_nodename 7-19, 17-16
start_blk_arg_long_bits function 16-74	syscall 7-19, 17-4, 17-15
start_blk_arg_long_dbl function 16-75	syscall_nodename 7-19, 17-16
start_blk_arg_long_long function 16-76	tid 7-18
start_blk_arg_long_ubits function 16-77	tid_nodename 7-19
start_blk_arg_short function 16-78	vector 7-19, 17-2, 17-3, 17-15
start_blk_arg_string function 16-79	vector_nodename 7-19, 17-16
start_blk_arg_ubits function 16-80	strncmp function 16-17
start_blk_arg_uchar function 16-81	sum function 16-180
start_blk_arg_uint function 16-82	Summary
start_blk_arg_ulong_long function 16-83	matches 16-183
start_blk_arg_ushort function 16-84	Summary functions 16-177
start_cpu function 16-90	summary_matches function 16-183
start_id function 16-5, 16-62	Syscall 17-4, 17-13, 17-15
start_node_id function 16-93	graph 17-13
start_node_name function 16-96	suspension 17-13
start_num_args function 16-85	Syscall box 17-13
start_offset function 16-91	syscall table 7-19, 17-4, 17-15
start_pid function 16-86	SYSCALL_EXIT trace event 17-4
start_pid_table_name function 16-94	syscall_nodename table 7-19, 17-16
start_task_id function 16-88	SYSCALL_RESUME trace event 17-5
start_thread_id function 16-87	SYSCALL_SUSPEND trace event 17-5
start_tid function 16-89	System call 17-4, 17-13, 17-15
start_tid_table_name function 16-95	-

T	tr_arg_int() 18-37
	tr_arg_int_() 18-38, 18-45
Table	tr_arg_long() 18-40, 18-47
boolean 7-18	tr_arg_long_() 18-41, 18-48
device 7-19, 17-4, 17-16	tr_arg_long_dbl() 18-42, 18-49
device_nodename 7-20, 17-17	tr_arg_long_dbl_() 18-42, 18-49
	tr_arg_long_long() 18-43, 18-50
event 7-17	tr_arg_long_long_() 18-44, 18-51
format 7-20, 16-188	tr_arg_t 18-2
functions 16-184	tr_argtype 18-51
name_pid 7-18, 17-16	tr_argtype_ 18-52
name_tid 7-18	tr_blk_arg() 18-52
node_name 7-19, 17-16	tr_blk_arg_() 18-53
pid 7-17, 17-17	tr_blk_arg_bits() 18-54
pid_nodename 7-19, 17-16	tr_blk_arg_bits_() 18-55
pre-defined 7-17, 17-4, 17-15	tr_blk_arg_char() 18-56, 18-74
string 7-15, 16-184, 16-186	tr_blk_arg_char_() 18-56
syscall 7-19, 17-4, 17-15	tr_blk_arg_dbl() 18-57
syscall_nodename 7-19, 17-16	tr_blk_arg_dbl_() 18-58
tid 7-18	tr_blk_arg_flt() 18-59
tid_nodename 7-19	tr_blk_arg_flt_() 18-59
vector 7-19, 17-2, 17-3, 17-15	tr_blk_arg_long() 18-60
vector_nodename 7-19, 17-16	tr_blk_arg_long_() 18-61
Task name 16-56	tr_blk_arg_long_bits) 18-62
ordinal trace event 16-175	
task_id function 16-46	tr_blk_arg_long_bits_() 18-63
task_name function 16-56	tr_blk_arg_long_dbl() 18-64
Then-Expression configuration parameter 16-188	tr_blk_arg_long_dbl_() 18-64
Thread event	tr_blk_arg_long_long() 18-65
ordinal 16-172	tr_blk_arg_long_long_() 18-66
Thread identifier	tr_blk_arg_long_ubits() 18-67
ending trace event 16-132	tr_blk_arg_long_ubits_() 18-68
offset 16-172	tr_blk_arg_short() 18-69
starting trace event 16-95	tr_blk_arg_string() 18-70
Thread identifier table name 16-53	tr_blk_arg_string_() 18-71
Thread name 16-57	tr_blk_arg_ubits() 18-72
ordinal trace event 16-176	tr_blk_arg_ubits_() 18-73
Thread names 7-2, 7-18	tr_blk_arg_uchar_() 18-75
thread_id function 16-45	tr_blk_arg_ushort() 18-76
thread_name function 16-57	tr_blk_arg_ushort_() 18-69, 18-76
TID 16-8, 16-47, 16-89, 16-126, 16-167, 18-79	tr_cancel_cb() 18-147
tid function 16-47	tr_cb_t 18-3
tid table 7-18	tr_close() 18-20
TID table name 16-53	tr_cond_and() 18-116
tid_nodename table 7-19	tr_cond_cb() 18-148
tid_table_name function 16-53	tr_cond_cb_func_t 18-3
time function 16-50	tr_cond_copy() 18-117
	tr_cond_cpu() 18-97
Times	tr_cond_cpu_clear() 18-98
constant 16-3	tr_cond_create() 18-92
Timestamp 7-2, 16-50, 16-92, 16-129, 16-169	tr_cond_expr_and() 18-112
tr_activate() 18-134	tr_cond_expr_or() 18-113
tr_append_table() 18-144	tr_cond_find() 18-93
tr_arg_dbl() 18-39, 18-46	tr_cond_func_and() 18-109
tr_arg_dbl_() 18-39, 18-46	tr_cond_func_clear() 18-111
	~

tr_cond_func_or() 18-107	tr_open_stream() 18-19
tr_cond_func_t 18-4	tr_pid() 18-77
tr_cond_id() 18-94	tr_pid_() 18-78
tr_cond_id_clear() 18-96	tr_prev_event() 18-27
tr_cond_id_range() 18-95	tr_prev_event_() 18-28
tr_cond_name() 18-118	tr_process_name() 18-86
tr_cond_node() 18-105	tr_process_name_() 18-87
tr_cond_node_clear() 18-106	tr_search() 18-29
tr_cond_not() 18-114	tr_seek() 18-30
tr_cond_offset() 18-122	tr_state_action_t 18-5
tr_cond_or() 18-115	tr_state_active() 18-137
tr_cond_pid() 18-99	tr_state_active_() 18-138
tr_cond_pid_clear() 18-101	tr_state_cb() 18-149
tr_cond_pid_name() 18-100	tr_state_cb_func_t 18-5
tr_cond_register() 18-121	tr_state_create() 18-123
tr_cond_reset() 18-93	tr_state_end_cond() 18-132
tr_cond_satisfy() 18-119	tr_state_end_cond_clear() 18-133
tr_cond_satisfy_() 18-120	tr_state_end_id() 18-128
tr_cond_t 18-4	tr_state_end_id_clear() 18-130
tr_cond_tid() 18-102	tr_state_end_id_range() 18-129
tr_cond_tid_clear() 18-104	tr_state_find() 18-124
tr_cond_tid_name() 18-103	tr_state_info() 18-135
tr_copy_input() 18-139	tr_state_info_() 18-136
tr_copy_input_range() 18-140	tr_state_info_t 18-6
tr_cpu() 18-83	tr_state_name() 18-125
tr_cpu_() 18-84	tr_state_start_cond() 18-131
• "	
tr_create_table() 18-143	tr_state_start_cond_clear() 18-131
tr_destroy() 18-14	tr_state_start_id() 18-126
tr_dir_t 18-4	tr_state_start_id_clear() 18-128
TR_EOF 18-4, 18-26, 18-27, 18-28, 18-29, 18-122,	tr_state_start_id_range() 18-127
18-135, 18-136	tr_state_t 18-7
tr_error_check() 18-17	tr_stream_event_t 18-7
tr_error_clear() 18-16	tr_stream_func_t 18-7
tr_free() 18-25	tr_stream_notify() 18-21
tr_get_item() 18-142	tr_stream_read() 18-23
tr_get_string() 18-141	TR_STREAM_SAVE 18-19
tr_halt() 18-147	tr_stream_size() 18-24
tr_id() 18-33	tr_string_node 18-7
tr_id_() 18-33	TR_SYSCALL_ENTRY trace event 17-4
tr_init() 18-14	tr_t 18-8
tr_iterate() 18-146	tr_task_id() 18-82
tr_nargs() 18-36	tr_task_id_() 18-82
tr_nargs_() 18-36	tr_task_name() 18-87
tr_next_event() 18-26	tr_task_name_() 18-88
tr_next_event_() 18-27	tr_thread_id() 18-80
TR_NO_CB 18-148, 18-149	tr_thread_id_() 18-81
TR_NO_COND 18-92, 18-94, 18-114, 18-116, 18-117,	tr_thread_name() 18-89
18-118	tr_thread_name_() 18-89
TR_NO_HANDLE 18-14	tr_tid() 18-79
TR_NO_STATE 18-124, 18-125	tr_tid_() 18-79
tr_node() 18-85	tr_time() 18-34
tr_node_() 18-85	tr_time_() 18-35
tr_offset_t 18-4	Trace event 1-2
tr_open_file() 18-18	arguments 2-15, 7-2, 7-12, 7-14, 16-21, 16-22,

16-23, 16-24, 16-25, 16-26, 16-27, 16-28,	SOFT_IRQ_EXIT 17-3
16-29, 16-30, 16-31, 16-32, 16-33, 16-34,	syscall 17-4
16-35, 16-36, 16-37, 16-38, 16-39, 16-40,	SYSCALL_EXIT 17-4
16-41, 16-42, 16-43, 16-63, 16-64, 16-65,	SYSCALL_RESUME 17-5
16-66, 16-67, 16-68, 16-69, 16-70, 16-71,	SYSCALL_SUSPEND 17-5
16-72, 16-73, 16-74, 16-75, 16-76, 16-77,	task name 16-56
16-78, 16-79, 16-80, 16-81, 16-82, 16-83,	task name (ordinal trace event) 16-175
16-84, 16-85, 16-100, 16-101, 16-102,	thread identifer (ending trace event) 16-132
16-103, 16-104, 16-105, 16-106, 16-107,	thread identifier (offset) 16-172
16-108, 16-109, 16-110, 16-111, 16-112,	thread identifier (starting trace event) 16-95
16-113, 16-114, 16-115, 16-116, 16-117,	thread identifier table name 16-53
16-118, 16-119, 16-120, 16-121, 16-122,	thread name 16-57
16-141, 16-142, 16-143, 16-144, 16-145,	thread name (ordinal trace event) 16-176
16-146, 16-147, 16-148, 16-149, 16-150,	TID table name 16-53
16-151, 16-152, 16-153, 16-154, 16-155,	timestamp 7-2, 16-50, 16-92, 16-129, 16-169
16-156, 16-157, 16-158, 16-159, 16-160,	TR_SYSCALL_ENTRY 17-4
16-161, 16-162, 16-163	TRAP_ENTRY 17-3
context switch 17-2	TRAP_EXIT_17-3
disabling 2-19	TRAP_RESUME 17-4
discarding 2-19 discarding 2-23, E-1	TRAP_SUSPEND 17-4
enabling 2-19	
exception 17-3	Trace point 1-2, 2-15
file 2-6, 3-1, 7-10	trace_begin 2-17, 2-21, 2-25, 3-1, E-1
	trace_close_thread 2-24
functions 16-18	trace_disable 2-18
ID 1-2, 2-15, 2-19, 7-2, 7-10, 7-12, E-1	trace_disable_all 2-18, 2-29
information 16-18	trace_disable_range 2-18
interrupt 17-2	trace_enable 2-18
IRQ_ENTRY 17-2	trace_enable_all 2-18
IRQ_EXIT 17-3	trace_enable_range 2-18
loading 7-5	trace_end 2-9, 2-22, 2-25, 3-2
logging 6-4, E-1	trace_event 2-12
loss 2-17, E-1	TRACE_FILE 5-13
node identifer (ending trace event) 16-130	trace_flush 2-22, 3-2
node identifer (offset) 16-170	trace_open_thread 2-11,2-24
node identifer (starting trace event) 16-93	trace_trigger 2-22,3-2
node identifier 16-51	Tracing
node name 16-54	disabling 2-18, 2-29
node name (ending trace event) 16-133	kernel 7-17, 7-18, 17-1
node name (ordinal trace event) 16-173	TRAP_ENTRY trace event 17-3
node name (starting trace event) 16-96	TRAP_EXIT trace event 17-4
offset 16-138	TRAP_RESUME trace event 17-4
offset. see Offset	TRAP_SUSPEND trace event 17-4
ordinal 16-170, 16-171, 16-173, 16-174, 16-175,	
16-176	
ordinal number, see Offset	U
PID table name 16-52	
process identifer (ending trace event) 16-131	1 5.22
process identifer (offset) 16-171	underscores 5-22
process identifer (starting trace event) 16-94	
process identifier table name 16-52	
process name 16-55	V
process name (ordinal trace event) 16-174	
SCHED_CHANGE 17-2	. 11
SOFT_IRQ_ENTRY 17-3	variables 5-19, 5-20

vector table 7-19, 17-2, 17-3, 17-15 vector\_nodename table 7-19, 17-16 vectors file 7-17, 17-2, 17-15, 17-16, 17-17

W

-Wl,--emit-relocs 5-10

X

xregex 5-22

Z

Zoom Out push button E-2