



**KVM-RT™**

# Version 2.1 Release Notes

March 2026

0898603-2.1



---

## Disclaimer

The information contained in this document is subject to change without notice. Concurrent Real-Time has taken efforts to remove errors from this document, however, Concurrent Real-Time's only liability regarding errors that may still exist is to correct said errors upon their being made known to Concurrent Real-Time.

---

## License

Duplication of this manual without the written consent of Concurrent Real-Time is prohibited. Any copy of this manual reproduced with permission must include the Concurrent Real-Time copyright notice.

---

## Trademark Acknowledgments

Concurrent Real-Time and its logo are registered trademarks of Concurrent Real-Time. All other Concurrent Real-Time product names are trademarks of Concurrent Real-Time while all other product names are trademarks or registered trademarks of their respective owners. Linux® is used pursuant to a sublicense from the Linux Mark Institute.

# Contents

1.0	Introduction	1
1.1	Product Description	1
1.2	The KVM-RT Product	1
1.2.1	KVM-RT Product Specifications	1
1.3	Related Publications	2
1.4	Syntax Notation	2
2.0	Prerequisites	3
2.1	Host Hardware Considerations	3
2.2	Firmware Configuration	3
2.3	Software Requirements	3
3.0	Changes in the RedHawk 9.X Releases	4
3.1	Changes in KVM-RT Version 2.1	4
3.2	Changes in KVM-RT Version 2.0	4
3.3	Changes in KVM-RT Version 1.6	4
3.4	Changes in KVM-RT Version 1.5	5
4.0	Known Issues	6
5.0	Installation & Upgrade Procedures	7
6.0	Software Removal	8
7.0	Software Updates and Support	9
7.1	Direct Software Support	9
7.2	Software Updates	9
7.2.1	Updating via NUU	9
7.2.2	Installing Manually Downloaded RPMs	10
7.2.3	Customized Update Discs	13
7.3	Documentation Updates	13



---



---

## 1.0. Introduction

This document provides release information and installation instructions for Concurrent Real-Time's RedHawk KVM-RT™ Version 2.1.

### 1.1 Product Description

RedHawk KVM-RT is a Real-Time Hypervisor solution that utilizes QEMU/KVM and RedHawk real-time features to extend RedHawk's real-time determinism to guest RedHawk virtual machines.

It supports multiple guests, both real-time and non real-time, running in virtual machines on a host system.

### 1.2 The KVM-RT Product

At this time, Concurrent has pre-qualified the KVM-RT product to achieve real-time performance with a specific hardware and software configuration.

Pre-qualification ensures that all of Concurrent's real-time benchmarking and validation software has been extensively run, both natively and inside virtual machines, with all results indicating acceptable real-time performance. Latencies under 100us were measured in all cases, including real-time scenarios utilizing PCI passthrough, with latencies in most cases measuring under 30us.

The pre-qualified configuration should be suitable for most customers to utilize real-time virtualization without any additional services needed from Concurrent. However, Customers utilizing uncommon or custom PCI Express devices with both open source and proprietary drivers may still need to contact Concurrent for KVM-RT tuning assistance and or driver consultation.

#### 1.2.1 KVM-RT Product Specifications

The KVM-RT product requires specific hardware and software. The following three products have been pre-qualified:

Hardware:

- Supermicro M12SWA-TF AMD Ryzen Threadripper PRO 5975WX
- Supermicro M12SWA-TF AMD Ryzen Threadripper PRO 5965WX
- ASUS Pro WS WRX90E-SAGE SE AMD Ryzen Threadripper PRO 7000 WX-Series

Specifications:

Host Firmware:	Supermicros: UEFI only, revision 2.1 ASUS: UEFI only, revision 0803
Host OS:	RedHawk-9.6 (w/latest updates) on Rocky/RHEL 9.6 or Ubuntu 24.04 RedHawk 9.2 (w/latest updates) on Rocky/RHEL 9.2 or Ubuntu 22.04 RedHawk 8.4 (w/latest updates) on

Rocky/RHEL 8.4 or Ubuntu 20.04

RT guest Firmware:	UEFI or Legacy
RT guest OS:	RedHawk 7.5 or newer
Non-RT guest Firmware:	UEFI or Legacy
Non-RT guest OS:	Any OS

### 1.3 Related Publications

The following table lists Concurrent Real-Time documentation. Depending upon the document, they are available online on RedHawk Linux systems or from the Concurrent Real-Time documentation web site at <http://redhawk.concurrent-rt.com/docs>

<b>RedHawk KVM-RT</b>	<b>Pub. Number</b>
<i>RedHawk KVM-RT Release Notes</i>	0898603
<i>RedHawk KVM-RT User's Guide</i>	0898604
<b>RedHawk Architect</b>	
<i>RedHawk Architect Release Notes</i>	0898600
<i>RedHawk Architect User's Guide</i>	0898601
<b>RedHawk Linux</b>	
<i>RedHawk Linux Release Notes</i>	0898003
<i>RedHawk Linux User's Guide</i>	0898004
<b>NightStar RT Development Tools</b>	
<i>NightView User's Guide</i>	0898395
<i>NightTrace User's Guide</i>	0898398
<i>NightProbe User's Guide</i>	0898465
<i>NightTune User's Guide</i>	0898515

### 1.4 Syntax Notation

The following notation is used throughout this document:

<i>italic</i>	Books, reference cards, and items that the user must specify appear in <i>italic</i> type. Special terms may also appear in <i>italic</i> .
<b>list bold</b>	User input appears in <b>list bold</b> type and must be entered exactly as shown. Names of directories, files, commands, options and man page references also appear in <b>list bold</b> type.
list	Operating system and program output such as prompts, messages and listings of files and programs appears in list type.
[]	Brackets enclose command options and arguments that are optional. You do not type the brackets if you choose to specify these options or arguments.

---

---

## 2.0. Prerequisites

This section describes the hardware, firmware and software considerations in KVM-RT.

Note that the pre-qualified KVM-RT product has specific firmware and software requirements differing from those listed below. It also requires specific hardware. Refer to the "The KVM-RT Product" on page 1.

### 2.1 Host Hardware Considerations

Concurrent Real-Time recommends KVM-RT applications use the latest available Intel or AMD CPUs that support x86 virtualization technology.

The CPUs on the host must support Virtual Machine Extensions (VMX). Different providers have different names for the virtualization technology; on Intel CPUs look for VT-x and on AMD CPUs look for AMD V.

The CPU must also support I/O MMU virtualization. This support is necessary for virtual machines to directly use IO devices such as PCI Express (PCIe) cards, network interface cards (NIC), and hard disk drives (HDD) controllers. This support is provided on Intel's VT-d and AMD's AMD-Vi.

It is also highly recommended the CPUs support Interrupt virtualization with either Intel's APICv or AMD's AVIC.

### 2.2 Firmware Configuration

UEFI firmware on the host is required for PCI passthrough of NVIDIA graphics cards.

Virtualization extensions must be enabled on the host. Enable all VMX capabilities supported by your processors and PCI subsystem. Once booted, the **lscpu(1)** command can be used to verify that the vmx flag is set.

Guest firmware may be configured as UEFI or Legacy.

Host Firmware: UEFI (required for passthrough) or Legacy

Guest Firmware: UEFI or Legacy

### 2.3 Software Requirements

KVM-RT requires the host system to be running the RedHawk operating system 8.4 or newer, while a real-time guest VM requires 7.0 or newer. Any operating system can be run in a non real-time guest VM.

Host OS: RedHawk 8.4 or newer

RT Guest OS: RedHawk 7.0 or newer

Non-RT guest OS: Any OS

## 3.0. Changes in the RedHawk 9.X Releases

This section describes enhancements and other changes to KVM-RT in this release and previous releases in the RedHawk 9.x. timeline.

### 3.1 Changes in KVM-RT Version 2.1

- Support for RedHawk version 9.6.
- Includes version 1.8 of the RedHawk real-time tools package **ccur-rttools**.
- Enhancements to the **kvmrt-gui** tool.
- A kernel boot option, *idle.shielded* is recommended to be set. See the Kernel Boot Parameters section in the RedHawk KVM-RT User's Guide.
- Miscellaneous bug fixes and enhancements to several tools and man pages.

### 3.2 Changes in KVM-RT Version 2.0

- A new graphical user interface, **kvmrt**, serves as an alternate to the CLI tools to create, manage and control a KVM-RT virtual machine configuration. The GUI may be used in conjunction with the CLI tools. A **kvmrt-gui(1)** man page is available.
- Support for the Threadripper Pro 7000 as a new pre-qualified platform for KVM-RT.
- Includes version 1.7 of the RedHawk real-time tools package **ccur-rttools**.
- Miscellaneous bug fixes and enhancements to several tools and man pages.

### 3.3 Changes in KVM-RT Version 1.6

- Changes to the KVM-RT configuration file **/etc/kvmrt.cfg**:
  - a new attribute, *pcidevs*, used to configure and validate PCI device passthrough to VMs.
  - a new value option, **auto**, for the existing *nr\_vcpus* attribute. When this attribute is set to **auto**, *nr\_vcpus* will be automatically set to all the CPUs specified in the attribute *cpuset* minus 1.
- Additions to the KVM-RT User's Guide:
  - new chapter: "I/O Device Utilization in Virtual Environment"
  - new appendices: "SR-IOV Setup" and "PCI Passthrough Boot Parameters"
- New commands added to the RedHawk Real-time tools package (**ccur-rttools**). Added since the last release of KVM-RT:
  - **cpu(1)** Displays per-CPU interrupt counts of IRQs.
  - **cpus(1)** Displays or changes the state of CPUs.
  - **irqs(1)** Displays information about IRQs on the system.
  - **pci(1)** Displays PCI device information.
  - **tasks(1)** Displays information about tasks (threads) on the system.
- New man pages for tools; for both the RedHawk Real-time and the KVM-RT tools.

- Miscellaneous bug fixes and enhancements to tools and library.

### 3.4 Changes in KVM-RT Version 1.5

- Support for RedHawk 9.2 as both host and guest.
- Support for RedHawk 9.2 on the KVM-RT qualified Threadripper Pro platforms. See section "The KVM-RT Product" on page 1 for information on the KVM-RT product.
- Support for Oracle 9.2 as a supported base for the KVM-RT product.
- The latest version of the RedHawk real-time tools package, **ccur-rttools**, is now included with KVM-RT.
- New appendix in the KVM-RT User's Guide describes the NUMA node mappings for the motherboard I/O controllers and PCIe slots on the qualified Threadripper Pro platforms.
- Miscellaneous bug fixes.

---

---

## 4.0. Known Issues

Special consideration should be given to the following areas:

### Graphics intensive programs

If a graphics intensive VM does not use dedicated GPU hardware, emulated graphics or any graphics intensive programs can cause VMs to affect the real-time performance of other virtual machines. The onboard graphics of a CPU rely on the memory controllers on the chip for accessing VRAM memory for the host and the VMs. If the memory controllers are overloaded with graphical accesses, the real-time VMs can suffer from performance hits. For this reason, you should not run the VM in graphical mode but instead in multi-user mode whenever possible.

### Real-time VMs running RedHawk 7.0-7.3

In RedHawk releases 7.0 through 7.3, the default kernel idle algorithm is to spin and poll. This can cause a VM to busy-spin idle virtual CPUs, and therefore the physical CPUs on the host. On VMs configured for real-time, the QEMU threads on the host spin at a high FIFO priority and when the VM is configured to use an entire host NUMA node this could result in the *host* system to become sluggish or even lock up.

To fix this problem we recommend using the following kernel boot options in real-time VMs running RedHawk 7.0-7.3:

```
idle=halt
idle.forcespin=shielded
```

### VMs running the Windows operating system

There is a "per socket" license for Windows operating systems that will dramatically reduce the performance of a Windows virtual machine if you use the default libvirt CPU topology settings. The user should adjust the *cpu\_topology* setting in the KVM-RT configuration to be many cores/threads on a single socket. It is recommended that the *cpu\_topology* parameter be set to **auto** for VMs running Windows. If the CPU topology setting is not adjusted, the Windows VM will act like it is a single CPU system and system performance will be slow.

### UEFI booting

UEFI booting is supported if OVMF software is installed on the system. Some distributions, like Red Hat 7.x releases do not provide OVMF natively.

### IRQs that cannot be migrated

In some architectures, IRQs may be bound to the first CPU in each socket and cannot be migrated to another CPU. These IRQs may affect the performance of real-time VMs running on those CPUs. If such IRQs exist, it is recommended that those CPUs not be allocated to a real-time VM.

---

---

## 5.0. Installation & Upgrade Procedures

Perform the following installation steps as the root user to both install and upgrade KVM-RT. Note that step 7 is only applicable to Upgrades.

1. Insert the installation CD in the CD-ROM drive.
2. The CD should normally be automatically mounted under the `/run/media/root` directory. If it does not mount automatically, create a mount point directory and invoke the `mount` command as follows:  
**mount /dev/cdrom /media/cdrom**

### NOTE

`/media/cdrom` is used in the examples in this section, however any other unique mount point directory can be used instead.

### NOTE

On Ubuntu systems you may encounter a directory access problem. To work around it, execute the following command after inserting the DVD:  
**sudo setfacl -m g::5,0::5 /media/\***

3. Change the current working directory to the directory containing the installation script:  
**cd /media/cdrom**
4. Invoke the installation script. When prompted, you must accept EULA to continue.  
**/install-kvmrt**
5. When installation is complete, change the current working directory outside of `/media/cdrom`:  
**cd /**
6. Unmount the CD-ROM device (may be required to remove the installation CD from the CD-ROM device):  
**umount /media/cdrom**
7. If upgrading, force re-synchronization of any existing KVM-RT configurations you may have as follows:  
**kvmrt-sync-config --force**

---

---

## 6.0. Software Removal

Should you desire to uninstall RedHawk KVM-RT, perform the following steps as the root user:

1. Insert the installation CD in the CD-ROM drive.
2. Mount the CD-ROM drive.

**mount /dev/cdrom /media/cdrom**

### NOTE

**/media/cdrom** is used in the examples in this section, however any other unique mount point directory can be used instead.

### NOTE

On Ubuntu systems you may encounter a directory access problem. To work around it, execute the following command after inserting the DVD:

**sudo setfacl -m g::5,o::5 /media/\***

3. Change the current working directory to the directory containing the installation script:  
**cd /media/cdrom**
4. Invoke the uninstall script:  
**./uninstall-kvmrt**
5. When the uninstall is complete, change the current working directory outside of **/media/cdrom**:  
**cd /**
6. Unmount the CD-ROM device (may be required to remove the installation CD from the CD-ROM device):  
**umount /media/cdrom**

---

---

## 7.0. Software Updates and Support

### 7.1 Direct Software Support

Software support is available from a central source. If you need assistance or information about your system, please contact the Concurrent Real-Time Software Support Center at our toll free number 1-800-245-6453. For calls outside the continental United States, the number is 1-954-283-1822. The Software Support Center operates Monday through Friday from 8 a.m. to 5 p.m., Eastern Standard Time.

Calling the Software Support Center gives you immediate access to a broad range of skilled personnel and guarantees you a prompt response from the person most qualified to assist you. If you have a question requiring on-site assistance or consultation, the Software Support Center staff will arrange for a field analyst to return your call and schedule a visit.

You may also submit a request for assistance at any time by using the Concurrent Real-Time, Inc. web site at <http://concurrent-rt.com/support>.

### 7.2 Software Updates

Updates to Concurrent Real-Time RedHawk software can be obtained via Concurrent Real-Time's Software Portal. There are three ways of installing product updates:

- Using the Network Update Utility (NUU) installed on your RedHawk system
- Manual installation after browsing and downloading individual RPMs from Concurrent Real-Time's software repositories
- Building a customized Update disc using Concurrent Real-Time's web site for immediate download

#### 7.2.1 Updating via NUU

NUU supports installation and updating of software products from Concurrent Real-Time software repositories over a network. NUU utilizes Yum and the RPM subsystems to install and update software.

NUU is installed automatically with RedHawk, however, you should configure it to include all of the Concurrent Real-Time software products installed on your system.

Clicking on the "Updates (NUU)" icon on your desktop launches NUU to check to see if Concurrent Real-Time updates are available for your system.

#### NOTE

It is recommended that all CentOS repositories should be disabled when checking for Concurrent Real-Time updates. In NUU, select the **Repositories -> Edit Configuration** menu item and ensure that the *base*, *updates* and *extras* repositories are disabled.

Instructions for configuring NUU can be found in the QuickStart.pdf document available when you click on the NUU link on the redhawk.concurrent-rt.com website or directly via this link <http://redhawk.concurrent-rt.com/network/QuickStart.pdf>


The first time you invoke NUU you will need to specify your redhawk.concurrent-rt.com Login ID and Password that were provided in the shipping documents accompanying your system.

Before using NUU to install any updated software modules, check for NUU updates separately. Apply any NUU updates and then restart NUU before applying any other updates.

## 7.2.2 Installing Manually Downloaded RPMs


You can browse Concurrent's software repositories to locate updated RPMs and download them for manual installation.

Start by accessing Concurrent's RedHawk site at <http://redhawk.concurrent-rt.com/>. You will see a page similar to the one below. Note that only the top section of the page is displayed.



The screenshot shows the top portion of the redhawk.concurrent-rt.com website. At the top left is the Concurrent Real-Time logo, which consists of a blue stylized 'C' icon followed by the text 'concurrent REAL-TIME'. Below this is a red hawk logo and the URL 'redhawk.concurrent-rt.com'. To the right of the logo is a hamburger menu icon. Below the logo and URL is a horizontal line. Underneath the line is the heading 'Overview:' followed by a paragraph: 'This site provides you access to Concurrent Real-Time software products and updates to those products that execute on the following platforms:'. This is followed by a bulleted list of operating systems: RedHawk Linux, Red Hat Enterprise Linux, Ubuntu Linux, CentOS Linux, Rocky Linux, and Oracle Linux. Below the list is another paragraph: 'You can download NUU, Concurrent Real-Time's Network Update and Installation utility, browse product repositories to manually download software packages, download original product ISOs or create customized Update CD images for immediate download.' Below this paragraph is a red-bordered box containing two lines of text: 'Click on My Account or use the menu icon at the top to access your software and for other services specific to your system.' and 'The menu icon is at the top of all pages on redhawk.concurrent-rt.com.' Below the box is the heading 'Links:' followed by a bulleted list of links: My Account, Document Library, Network Repositories, and Manage NightStar Licenses.

Clicking on the My Account link takes you to an authentication page.



Enter your redhawk.concurrent-rt.com Login ID and Password and click the Submit button.

On the My Software Products page that comes up next, click on the three horizontal bars on the top to get the drop down menu shown below and select the Browse Repositories option.



You are then presented with the list of products purchased and the latest release of each as shown in the example below. You may change the release to an earlier release by clicking on the release box.

Select the architecture from the following page to see the list of RPMs in the product software repository that you may then download.

## Index of /swdist/repos/RedHawk/KVM-RT/2.1

<a href="#">Name</a>	<a href="#">Last modified</a>	<a href="#">Size</a>	<a href="#">Description</a>
<a href="#">Parent Directory/</a>		-	
<a href="#">aarch64/</a>	27-Jan-2026 11:45	-	
<a href="#">i386/</a>	27-Jan-2026 11:45	-	
<a href="#">x86_64/</a>	27-Jan-2026 11:45	-	

After locating the RPMs of interest and downloading them to your system, you can manually install them.

To install newly downloaded packages, follow these steps:

1. Log in as root and take the system down to single-user mode:
  - a. Right click on the desktop and select **Open Terminal**.
  - b. At the system prompt, type **init 1**.
2. Change directory to the location of the updates and issue the following command:

```
rpm -Uvh *.rpm
```

The time it takes to install will vary depending on the number of updates being installed.

3. When complete, exit single-user mode (Ctrl-D).

#### NOTE

If you have installed an update containing new RedHawk kernels on a system that has post-installation loadable modules present, those modules must be recompiled for the new kernel; for example, an NVIDIA driver that is a later version than the one included with RedHawk or any third party package that uses loadable modules.

### 7.2.3 Customized Update Discs

You can use Concurrent Real-Time's Software Portal to create a customized Update Disc for your system which you can then download and burn onto physical media, or simply mount as an ISO9660 image.

Update discs have customized copies of product software repositories and a simple graphical interface for selecting packages for update and installation. These discs use NUU (described above) to talk to the disc to obtain packages -- no network access is required during installation via Update Discs.

Access the RedHawk Updates web site (<http://redhawk.concurrent-rt.com>) by clicking on the "Concurrent Real-Time Software Portal" icon on the desktop, then click on **Create Update Images**.

You will need to enter your [redhawk.concurrent-rt.com](http://redhawk.concurrent-rt.com) Login ID and Password and then you can select the products to update. A disc image is built as part of the web session. At the end of the session, you can immediately download it for subsequent installation.

## 7.3 Documentation Updates

For the latest documents, including updated Release Notes and User Guides, go to Concurrent Real-Time's documentation web site at <http://redhawk.concurrent-rt.com/docs>.





